

# //makegamesplay


.i.games

## WebGL Build Host

User Guide - run your Unity Web build on any device and read its console live

**Unity 2022.3 LTS+ · WebGL & WebGPU · Windows / macOS / Linux Editor · No dependencies**

Point WebGL Build Host at your build folder and press Start. It serves the build over HTTPS on your network, shows a QR code and copyable URLs, and gives every browser that opens it a live console tab inside the Editor - so you can watch what happens on the actual device.



### IN THIS GUIDE

- 1. Install and quick start
- 2. The window
- 3. The device console
- 4. Public link (cloudflared)
- 5. Troubleshooting

# 1 Install and quick start

---

## Install

- **Asset Store:** import the package; it lands under `Assets/MakeGamesPlay/WebBuildHost/`.
- **UPM git URL:** Window > Package Manager > + > Add package from git URL:  
<https://github.com/MakeGamesPlay/unity-webgl-build-host.git>


Requirements: Unity 2022.3 LTS or newer (covers the Unity 6 Web platform). The Editor can run on Windows, macOS, or Linux; a prebuilt server is bundled for each. No Python, Node, or other runtime needed.

## Quick start

1. Open **Tools > WebGL Build Host**.
2. Choose your Web build output folder.
3. Press **Start**.
4. Scan the QR code with your device, or open one of the listed URLs.
5. Accept the self-signed certificate prompt on the device (Advanced, then Proceed).
6. Each device appears as a console tab. Press **Stop** when you are done.

**Why HTTPS?** The self-signed certificate gives every device a secure context, which browsers require for the camera, microphone, WebXR, and multithreading (`SharedArrayBuffer`).


## 2 The window



| Control               | What it does                                                                                                                                                      |
|-----------------------|-------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Build folder</b>   | The Web build output folder to serve (the one containing index.html).                                                                                             |
| <b>Start / Stop</b>   | Starts or stops the server. It runs as its own process, so it keeps serving across recompiles, new builds, and Editor restarts; the window reconnects on its own. |
| <b>URLs + QR code</b> | Copyable local and HTTPS LAN URLs, and a scan-to-open QR code for the recommended URL.                                                                            |
| <b>Public link</b>    | Optional Cloudflare quick tunnel for testers outside your network. See section 4.                                                                                 |
| <b>Headers</b>        | The server always sends what Unity Web builds need: Content-Encoding for .br/.gz files, application/wasm, and COOP/COEP.                                          |
| <b>Dev builds</b>     | Development Builds are served with Cache-Control: no-store, so a reload on the device always picks up the latest build.                                           |

## 3 The device console

Every browser that opens the build gets its own tab streaming its console output and uncaught errors into the Editor.



- **Tabs per device** with live/stale indicators.
- **Colour-coded levels** with per-level filters and counts, search, frame numbers, and duplicate collapsing.
- **Copy** (multi-select), **Save** to a text file, and **Clear** (also frees the server-side buffer).
- **Per-device actions:** Reload the page, Identify (flashes the device), and Copy bug report (a ready-to-paste Markdown summary).

## 4 Public link (cloudflared)

---

By default the build is reachable only on your local network. The public link option serves it through a Cloudflare quick tunnel: a temporary public HTTPS URL, with no Cloudflare account needed. Useful when the tester is somewhere else, the network blocks device-to-device traffic (common on guest and corporate Wi-Fi), or you want to test over mobile data.

Quick tunnels use Cloudflare's free `cloudflared` tool. The window checks whether it is installed and shows the install command for your platform if not:

| Platform | Install                                                        |
|----------|----------------------------------------------------------------|
| Windows  | <code>winget install --id Cloudflare.cloudflared</code>        |
| macOS    | <code>brew install cloudflared</code>                          |
| Linux    | Cloudflare's apt/rpm repo, or a binary from the releases page. |

The host checks the tunnel's health every 15 seconds and marks it offline if it stops responding (for example after the machine sleeps); Stop and Start to reconnect.

## 5 Troubleshooting

---

| Symptom                                  | Fix                                                                                                                                                                            |
|------------------------------------------|--------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <b>Certificate warning on the device</b> | Expected: the HTTPS certificate is self-signed for local use. Tap Advanced, then Proceed.                                                                                      |
| <b>No public link appears</b>            | Install c1oudflared (section 4) and confirm it is on the PATH, or use the LAN URL.                                                                                             |
| <b>A device cannot reach the LAN URL</b> | The device and the Editor need to be on the same network, and the firewall needs to allow the port. The public link works around networks that block device-to-device traffic. |
| <b>Public link shows offline</b>         | The quick tunnel stopped responding (machine sleep and network changes are common causes). Stop and Start the server to reconnect.                                             |
| <b>Build loads but no logs appear</b>    | The console streams from pages served by this host. Confirm the device opened one of the window's URLs and the tab shows a live indicator.                                     |

More: the project README at [github.com/MakeGamesPlay/unity-webgl-build-host](https://github.com/MakeGamesPlay/unity-webgl-build-host).