Chapter 9: Virtual Memory

Chapter 9: Virtual Memory

- Background
- Demand Paging
- Copy-on-Write
- Page Replacement
- Allocation of Frames
- Thrashing
- Memory-Mapped Files
- Allocating Kernel Memory
- Other Considerations
- Operating-System Examples


Objectives

- To describe the benefits of a virtual memory system
- To explain the concepts of demand paging, page-replacement algorithms, and allocation of page frames
- To discuss the principle of the working-set model


Background

- Virtual memory separation of user logical memory from physical memory.
 - Only part of the program needs to be in memory for execution
 - Logical address space can therefore be much larger than physical address space
 - Allows address spaces to be shared by several processes
 - Allows for more efficient process creation
- Virtual memory can be implemented via:
 - Demand paging
 - Demand segmentation


Virtual Memory That is Larger Than Physical Memory



Virtual-address Space




Shared Library Using Virtual Memory



Demand Paging

- Bring a page into memory only when it is needed
 - Less I/O needed
 - Less memory needed
 - Faster response
 - More users
- Page is needed ⇒ reference to it
 - invalid reference ⇒ abort
 - not-in-memory ⇒ bring to memory
- Lazy swapper never swaps a page into memory unless page will be needed
 - Swapper that deals with pages is a pager

Transfer of a Paged Memory to Contiguous Disk Space




Valid-Invalid Bit

- With each page table entry a valid—invalid bit is associated (v ⇒ in-memory, i ⇒ not-in-memory)
- Initially valid—invalid bit is set to i on all entries
- Example of a page table snapshot:

Frame #	valid-invalid bit	
	V	
	V	
	V	
	V	
	i	
	i	
	i	

• During address translation, if valid—invalid bit in page table entry is $I \Rightarrow$ page fault

Page Table When Some Pages Are Not in Main Memory



Page Fault


• If there is a reference to a page, first reference to that page will trap to operating system:

page fault

- 1. Operating system looks at another table to decide:
 - - Invalid reference ⇒ abort
 - Just not in memory
- 2. Get empty frame
- 3. Swap page into frame
- 4. Reset tables
- 5. Set validation bit = v
- 6. Restart the instruction that caused the page fault


Page Fault (Cont.)

- Restart instruction
 - block move



• auto increment/decrement location

Steps in Handling a Page Fault



Performance of Demand Paging

- Page Fault Rate $0 \le p \le 1.0$
 - if p = 0 no page faults
 - if p = 1, every reference is a fault
- Effective Access Time (EAT)

```
EAT = (1 - p) x memory access
+ p (page fault overhead
+ swap page out
+ swap page in
+ restart overhead
```

Demand Paging Example

- Memory access time = 200 nanoseconds
- Average page-fault service time = 8 milliseconds
- EAT = $(1 p) \times 200 + p$ (8 milliseconds) = $(1 - p \times 200 + p \times 8,000,000$ = $200 + p \times 7,999,800$
- If one access out of 1,000 causes a page fault, then EAT = 8.2 microseconds.

This is a slowdown by a factor of 40!!

Process Creation

- Virtual memory allows other benefits during process creation:
 - Copy-on-Write
 - Memory-Mapped Files (later)


Copy-on-Write

 Copy-on-Write (COW) allows both parent and child processes to initially share the same pages in memory


If either process modifies a shared page, only then is the page copied

- COW allows more efficient process creation as only modified pages are copied
- Free pages are allocated from a **pool** of zeroed-out pages

Before Process 1 Modifies Page C



After Process 1 Modifies Page C




What happens if there is no free frame?

- Page replacement find some page in memory, but not really in use, swap it out
 - algorithm
 - performance want an algorithm which will result in minimum number of page faults
- Same page may be brought into memory <u>several times</u>

Page Replacement

- Prevent over-allocation of memory by modifying page-fault service routine to include page replacement
- Use modify (dirty) bit to reduce overhead of page transfers – only modified pages are written to disk
- Page replacement completes separation between logical memory and physical memory — large virtual memory can be provided on a smaller physical memory


Need For Page Replacement



Basic Page Replacement

- 1. Find the location of the desired page on disk
- 2. Find a free frame:
 - If there is a free frame, use it
 - If there is no free frame, use a page replacement algorithm to select a victim frame
- 3. Bring the desired page into the (newly) free frame; update the page and frame tables
- 4. Restart the process

Page Replacement




Page Replacement Algorithms

- Want lowest page-fault rate
- Evaluate algorithm by running it on a particular string of memory references (reference string) and computing the number of page faults on that string
- In all our examples, the reference string is

1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5

Graph of Page Faults Versus The Number of Frames




First-In-First-Out (FIFO) Algorithm

- Reference string: 1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5
- 3 frames (3 pages can be in memory at a time per process)


• 4 frames

Belady's Anomaly: more frames ⇒ more page faults

FIFO Page Replacement



FIFO Illustrating Belady's Anomaly




Optimal Algorithm

- Replace page that will not be used for longest period of time
- 4 frames example

- How do you know this?
- Used for measuring how well your algorithm performs

Optimal Page Replacement



Least Recently Used (LRU) Algorithm


• Reference string: 1, 2, 3, 4, 1, 2, 5, 1, 2, 3, 4, 5

1	1	1	1	5
2	2	2	2	2
3	5	5	4	4
4	4	3	3	3

Counter implementation

- Every page entry has a counter; every time page is referenced through this entry, copy the clock into the counter,
- When a page needs to be changed, look at the counters to determine which are to change.

LRU Page Replacement




LRU Algorithm (Cont.)

- Stack implementation keep a stack of page numbers in a double link form:
 - Page referenced:
 - move it to the top
 - requires 6 pointers to be changed
 - No search for replacement

Use Of A Stack to Record the Most Recent Page References

reference string



LRU Approximation Algorithms


Reference bit

- With each page associate a bit, initially = 0
- When page is referenced bit set to 1
- Replace the one which is 0 (if one exists)
 - We do not know the order, however

Second chance

- Need reference bit
- Clock replacement
- If page to be replaced (in clock order) has reference bit = 1 then:
 - set reference bit 0
 - leave page in memory
 - replace next page (in clock order), subject to same rules

Second-Chance (clock) Page-Replacement Algorithm



Counting Algorithms

- Keep a counter of the number of references that have been made to each page
- LFU Algorithm: replaces page with smallest count
- MFU Algorithm: based on the argument that the page with the smallest count was probably just brought in and has yet to be used

Allocation of Frames

- Each process needs *minimum* number of pages
- Example: IBM 370 6 pages to handle SS MOVE instruction:
 - instruction is 6 bytes, might span 2 pages
 - 2 pages to handle from
 - 2 pages to handle to
- Two major allocation schemes
 - fixed allocation
 - priority allocation

Fixed Allocation

- Equal allocation For example, if there are 100 frames and 5 processes, give each process 20 frames.
- Proportional allocation Allocate according to the size of process

$$-s_i$$
 = size of process p_i

$$-S = \sum s_i$$

$$-m = total number of frames$$

$$-a_i$$
 = allocation for $p_i = \frac{s_i}{S} \times m$

$$m = 64$$

$$s_i = 10$$

$$s_2 = 127$$

$$a_1 = \frac{10}{137} \times 64 \approx 5$$

$$a_2 = \frac{127}{137} \times 64 \approx 59$$

Priority Allocation

- Use a proportional allocation scheme using priorities rather than size
- If process P_i generates a page fault,
 - select for replacement one of its frames
 - select for replacement a frame from a process with lower priority number

Global vs. Local Allocation


- Global replacement process selects a replacement frame from the set of all frames; one process can take a frame from another
- Local replacement each process selects from only its own set of allocated frames

Thrashing

- If a process does not have "enough" pages, the pagefault rate is very high. This leads to:
 - low CPU utilization
 - operating system thinks that it needs to increase the degree of multiprogramming
 - another process added to the system
- Thrashing

 a process is busy swapping pages in and out


Thrashing (Cont.)



Demand Paging and Thrashing

- Why does demand paging work?
 Locality model
 - Process migrates from one locality to another
 - Localities may overlap
- Why does thrashing occur? Σ size of locality > total memory size

Locality In A Memory-Reference Pattern



Working-Set Model

- Δ = working-set window = a fixed number of page references Example: 10,000 instruction
- WSS_i (working set of Process P_i) = total number of pages referenced in the most recent Δ (varies in time)
 - if Δ too small will not encompass entire locality
 - if Δ too large will encompass several localities
 - if $\Delta = \infty \Rightarrow$ will encompass entire program
- $D = \sum WSS_i \equiv \text{total demand frames}$
- if $D > m \Rightarrow$ Thrashing
- Policy if *D* > m, then suspend one of the processes


Working-set model

Keeping Track of the Working Set


- Approximate with interval timer + a reference bit
- Example: $\Delta = 10,000$
 - Timer interrupts after every 5000 time units
 - Keep in memory 2 bits for each page
 - Whenever a timer interrupts copy and sets the values of all reference bits to 0
 - If one of the bits in memory = $1 \Rightarrow$ page in working set
- Why is this not completely accurate?
- Improvement = 10 bits and interrupt every 1000 time units

Page-Fault Frequency Scheme

- Establish "acceptable" page-fault rate
 - If actual rate too low, process loses frame
 - If actual rate too high, process gains frame




Working Sets and Page Fault Rates




Memory-Mapped Files

- Memory-mapped file I/O allows file I/O to be treated as routine memory access by mapping a disk block to a page in memory.
- A file is initially read using demand paging. A page-sized portion of the file is read from the file system into a physical page. Subsequent reads/writes to/from the file are treated as ordinary memory accesses.
- Simplifies file access by treating file I/O through memory rather than read() write() system calls.
- Also allows several processes to map the same file allowing the pages in memory to be shared.

Memory Mapped Files



Memory-Mapped Shared Memory in Windows



Memory-Mapped Files in Java

```
import java.io.*;
import java.nio.*;
import java.nio.channels.*;
public class MemoryMapReadOnly
  // Assume the page size is 4 KB
  public static final int PAGE_SIZE = 4096;
  public static void main(String args[]) throws IOException {
     RandomAccessFile inFile = new RandomAccessFile(args[0], "r");
     FileChannel in = inFile.getChannel();
    MappedByteBuffer mappedBuffer =
      in.map(FileChannel.MapMode.READ_ONLY, 0, in.size());
     long numPages = in.size() / (long)PAGE_SIZE;
     if (in.size() % PAGE_SIZE > 0)
       ++numPages;
     // we will "touch" the first byte of every page
     int position = 0;
     for (long i = 0; i < numPages; i++) {
       byte item = mappedBuffer.get(position);
       position += PAGE_SIZE;
     in.close();
     inFile.close();
```

Allocating Kernel Memory


- Treated differently from user memory
- Often allocated from a free-memory pool
 - Kernel requests memory for structures of varying sizes
 - Some kernel memory needs to be contiguous

Buddy System

- Allocates memory from fixed-size segment consisting of physicallycontiguous pages
- Memory allocated using power-of-2 allocator
 - Satisfies requests in units sized as power of 2
 - Request rounded up to next highest power of 2
 - When smaller allocation needed than is available, current chunk split into two buddies of next-lower power of 2
 - Continue until appropriate sized chunk available

Buddy System Allocator


physically contiguous pages



Slab Allocator

- Alternate strategy
- Slab is one or more physically contiguous pages
- Cache consists of one or more slabs
- Single cache for each unique kernel data structure
 - Each cache filled with objects instantiations of the data structure
- When cache created, filled with objects marked as free
- When structures stored, objects marked as used
- If slab is full of used objects, next object allocated from empty slab
 - If no empty slabs, new slab allocated
- Benefits include no fragmentation, fast memory request satisfaction

Slab Allocation



Other Issues -- Prepaging

Prepaging

- To reduce the large number of page faults that occurs at process startup
- Prepage all or some of the pages a process will need, before they are referenced
- But if prepaged pages are unused, I/O and memory was wasted
- Assume s pages are prepaged and α of the pages is used
 - Is cost of $s * \alpha$ save pages faults > or < than the cost of prepaging $s * (1-\alpha)$ unnecessary pages?
 - α near zero \Rightarrow prepaging loses

Other Issues – Page Size

- Page size selection must take into consideration:
 - fragmentation
 - table size
 - I/O overhead
 - locality

Other Issues – TLB Reach

- TLB Reach The amount of memory accessible from the TLB
- TLB Reach = (TLB Size) X (Page Size)
- Ideally, the working set of each process is stored in the TLB
 - Otherwise there is a high degree of page faults
- Increase the Page Size
 - This may lead to an increase in fragmentation as not all applications require a large page size
- Provide Multiple Page Sizes
 - This allows applications that require larger page sizes the opportunity to use them without an increase in fragmentation

Other Issues – Program Structure

- Program structure
 - Int[128,128] data;
 - Each row is stored in one page
 - Program 1

128 x 128 = 16,384 page faults

• Program 2

```
for (i = 0; i < 128; i++)

for (j = 0; j < 128; j++)


data[i,j] = 0;
```

128 page faults

Other Issues – I/O interlock

- I/O Interlock Pages must sometimes be locked into memory
- Consider I/O Pages that are used for copying a file from a device must be locked from being selected for eviction by a page replacement algorithm

Reason Why Frames Used For I/O Must Be In Memory



Operating System Examples

• Windows XP

• Solaris


Windows XP

- Uses demand paging with **clustering**. Clustering brings in pages surrounding the faulting page.
- Processes are assigned working set minimum and working set maximum.
- Working set minimum is the minimum number of pages the process is guaranteed to have in memory.
- A process may be assigned as many pages up to its working set maximum.
- When the amount of free memory in the system falls below a threshold, automatic working set trimming is performed to restore the amount of free memory.
- Working set trimming removes pages from processes that have pages in excess of their working set minimum.

Solaris

- Maintains a list of free pages to assign faulting processes
- Lotsfree threshold parameter (amount of free memory) to begin paging
- *Desfree* threshold parameter to increasing paging
- *Minfree* threshold parameter to being swapping
- Paging is performed by pageout process
- Pageout scans pages using modified clock algorithm
- Scanrate is the rate at which pages are scanned. This ranges from slowscan to fastscan
- Pageout is called more frequently depending upon the amount of free memory available

Solaris 2 Page Scanner



End of Chapter 9