```
* kernel/workqueue.c - generic async execution with shared worker pool
 * The externally visible workqueue. It relays the issued work items to
* the appropriate worker_pool through its pool_workqueues.
struct workqueue_struct {
           struct list head
                                                      /* WR: all pwqs of this wq */
                                pwqs;
           struct list head
                                                      /* PR: list of all workqueues */
                                list;
                                                                 /* protects this wq */
           struct mutex
                                           mutex:
                                                                 /* WQ: current work color */
                                           work_color;
          int
                                                                /* WQ: current flush color */
                                           flush_color;
          int
                                nr_pwqs_to_flush; /* flush in progress */
           atomic_t
           struct wq_flusher
                                *first_flusher;
                                                      /* WQ: first flusher */
           struct list_head
                                flusher_queue;
                                                      /* WQ: flush waiters */
           struct list_head
                                flusher_overflow; /* WQ: flush overflow list */
           struct list head
                                maydays; /* MD: pwqs requesting rescue */
           struct worker
                                           *rescuer; /* I: rescue worker */
                                                                 /* WQ: drain in progress */
                                           nr_drainers;
           int
                                           saved_max_active; /* WQ: saved pwq max_active */
          int
                                                                 /* PW: only for unbound wgs */
           struct workqueue_attrs
                                           *unbound_attrs;
           struct pool_workqueue
                                           *dfl_pwq; /* PW: only for unbound wqs */
#ifdef CONFIG_SYSFS
                                *wq_dev; /* I: for sysfs interface */
           struct wq_device
#endif
#ifdef CONFIG_LOCKDEP
           struct lockdep_map lockdep_map;
#endif
                                           name[WQ_NAME_LEN]; /* I: workqueue name */
           char
           * Destruction of workqueue struct is sched-RCU protected to allow
           * walking the workqueues list without grabbing wq pool mutex.
           * This is used to dump all workqueues from sysrq.
           struct rcu_head
                                           rcii:
          /* hot fields used during command issue, aligned to cacheline */
                                           flags ____cacheline_aligned; /* WQ: WQ_* flags */
           unsigned int
           struct pool_workqueue __percpu *cpu_pwqs; /* I: per-cpu pwqs */
           struct pool_workqueue __rcu *numa_pwq_tbl[]; /* PWR: unbound pwqs indexed by node */
};
struct work_struct {
           atomic_long_t data;
          struct list_head entry;
           work_func_t func;
#ifdef CONFIG_LOCKDEP
           struct lockdep_map lockdep_map;
#endif
};
typedef void (*work_func_t)(struct work_struct *work);
```

```
* initialize all of a work item in one go
* NOTE! No point in using "atomic long set()": using a direct
 * assignment of the work data initializer allows the compiler
 * to generate better code.
#ifdef CONFIG_LOCKDEP
#define __INIT_WORK(_work, _func, _onstack)
          do {
                     static struct lock_class_key __key;
                       _init_work((_work), _onstack);
                     (_work)->data = (atomic_long_t) WORK_DATA_INIT();
                     lockdep_init_map(&(_work)->lockdep_map, #_work, &__key, 0); \
                     INIT_LIST_HEAD(&(_work)->entry);
                     (\_work)->func = (\_func);
           } while (0)
#else
#define __INIT_WORK(_work, _func, _onstack)
          do {
                       _init_work((_work), _onstack);
                     (_work)->data = (atomic_long_t) WORK_DATA_INIT();
                     INIT LIST HEAD(&( work)->entry);
                     (\text{work})->func = (\text{func});
           } while (0)
#endif
#define INIT_WORK(_work, _func)
           __INIT_WORK((_work), (_func), 0)
* Workqueue flags and constants. For details, please refer to
* Documentation/workqueue.txt.
enum {
           WQ UNBOUND
                                          = 1 \ll 1, /* not bound to any cpu */
           WQ_FREEZABLE
                                          = 1 << 2, /* freeze during suspend */
                                                     = 1 << 3, /* may be used for memory reclaim */
           WQ_MEM_RECLAIM
                                          = 1 << 4, /* high priority */
           WQ_HIGHPRI
          WQ_CPU_INTENSIVE
                                          = 1 << 5, /* cpu intensive workqueue */
                                          = 1 << 6, /* visible in sysfs, see wq_sysfs_register() */
           WQ_SYSFS
           * Per-cpu workqueues are generally preferred because they tend to
           * show better performance thanks to cache locality. Per-cpu
           * workqueues exclude the scheduler from choosing the CPU to
           * execute the worker threads, which has an unfortunate side effect
           * of increasing power consumption.
           * The scheduler considers a CPU idle if it doesn't have any task
           * to execute and tries to keep idle cores idle to conserve power;
           * however, for example, a per-cpu work item scheduled from an
           * interrupt handler on an idle CPU will force the scheduler to
           * excute the work item on that CPU breaking the idleness, which in
           * turn may lead to more scheduling choices which are sub-optimal
           * in terms of power consumption.
           * Workqueues marked with WQ_POWER_EFFICIENT are per-cpu by default
           * but become unbound if workqueue.power_efficient kernel param is
```

```
* contribute significantly to power-consumption are identified and
          * marked with this flag and enabling the power_efficient mode
           * leads to noticeable power saving at the cost of small
           * performance disadvantage.
          * http://thread.gmane.org/gmane.linux.kernel/1480396
* Рабочие очереди для каждого процессора, как правило, предпочтительнее, поскольку они, как правило,
* демонстрируют более высокую производительность благодаря локальности кэша. Для каждого процессора
* рабочие очереди исключают возможность выбора планировщиком процессора для
* выполнение рабочих потоков, что имеет неприятный побочный эффект
* увеличения энергопотребления.
* Планировщик считает, что процессор простаивает, если у него нет какой-либо задачи
* для выполнения и пытается поддерживать простаивающие ядра в режиме ожидания для экономии
* однако, например, рабочий элемент для каждого процессора, запланированный из
* обработчика прерывания на неработающем процессоре заставит планировшик
* исключить рабочий элемент на этом процессоре, нарушая бездействие, которое наоборот может привести
к большему количеству вариантов планирования, которые являются неоптимальными с точки зрения
энергопотребления.
* Рабочие очереди, помеченные символом WQ_POWER_EFFICIENT, по умолчанию предназначены для
каждого процессора.
* но становится несвязанным, если рабочая очередь. параметр ядра power_efficient равен
* указано. Рабочие очереди для каждого процессора, которые идентифицируются для
* значительно увеличивают энергопотребление, идентифицируются и
* помечаются этим флагом и включают режим power_efficient.
* приводит к заметной экономии электроэнергии за счет небольших
* недостаток производительности.
          WQ_POWER_EFFICIENT
                                        = 1 << 7,
            WQ_DRAINING
                                        = 1 << 16, /* internal: workqueue is draining */
            WQ_ORDERED
                                       = 1 << 17, /* internal: workqueue is ordered */
           _WQ_LEGACY
                                        = 1 << 18, /* internal: create*_workqueue() */
          WQ_MAX_ACTIVE
                                                   /* I like 512, better ideas? */
                                       = 512,
          WQ MAX UNBOUND PER CPU
                                                             /* 4 * #cpus for unbound wa */
                                                  = 4.
          WQ DFL ACTIVE
                                        = WQ MAX ACTIVE / 2,
};
/* unbound wq's aren't per-cpu, scale max_active according to #cpus */
#define WQ_UNBOUND_MAX_ACTIVE \
          max\_t(int, WQ\_MAX\_ACTIVE, num\_possible\_cpus()*WQ\_MAX\_UNBOUND\_PER\_CPU)
* System-wide workqueues which are always present.
* system_wq is the one used by schedule[_delayed]_work[_on]().
* Multi-CPU multi-threaded. There are users which expect relatively
* short queue flush time. Don't queue works which can run for too
* long.
* system_highpri_wq is similar to system_wq but for work items which
* require WQ_HIGHPRI.
* system long wa is similar to system wa but may host long running
* works. Queue flushing might take relatively long.
* system unbound wg is unbound workqueue. Workers are not bound to
* any specific CPU, not concurrency managed, and all queued works are
* executed immediately as long as max_active limit is not reached and
```

* specified. Per-cpu workqueues which are identified to

- * resources are available.
- *
- * system_freezable_wq is equivalent to system_wq except that it's
- * freezable.
- *
- * *_power_efficient_wq are inclined towards saving power and converted
- * into WQ_UNBOUND variants if 'wq_power_efficient' is enabled; otherwise,
- * they are same as their non-power-efficient counterparts e.g.
- * system_power_efficient_wq is identical to system_wq if
- * 'wq_power_efficient' is disabled. See WQ_POWER_EFFICIENT for more info.
- */
- * Общесистемные рабочие очереди, которые всегда присутствуют.
- * system_wq это тот, который используется schedule[_delayed]_work[_on]().
- * Многопроцессорная многопоточность. Есть пользователи, которые ожидают относительно
- * короткое время промывки очереди *queue flush*. Не ставьте в очередь работы, которые могут выполняться слишком долго длинный.
- * system highpri wq аналогичен system wq, но для рабочих элементов, которые
- * требуется WQ HIGHPRI.
- * system long wq похож на system wq, но может содержать длительное время
- * работает. Очистка очереди может занять относительно много времени.
- * system_unbound_wq это несвязанная рабочая очередь. Работники не обязаны
- * любой конкретный процессор, не управляемый параллелизмом, и все работы в очереди выполняются
- * выполняется немедленно до тех пор, пока не будет достигнут предел max active и
- * ресурсы доступны.
- * system_freezable_wq эквивалентен system_wq, за исключением того, что он
- * возможность замораживания.
- * * power efficient wq склонны к экономии энергии и преобразованы
- * в варианты WQ UNBOUND, если включен параметр 'wq power efficient'; в противном случае
- * они такие же, как и их неэнергосберегающие аналоги например
- * system_power_efficient_wq идентичен system_wq, если
- * 'wq_power_efficient' отключен. Дополнительную информацию см. в разделе WQ POWER EFFICIENT.