# 6.3 HAProxy安装

### 版权说明

本"比特就业课"课程(以下简称"本课程")的所有内容,包括但不限于文字、图片、音频、视频、软件、程序、数据库、设计、布局、界面等,均由本课程的开发者或授权方拥有版权。 我们鼓励个人学习者使用本课程进行学习和研究。在遵守相关法律法规的前提下,个人学习者可以下载、浏览、学习本课程的内容,并为了个人学习、研究或教学目的而使用其中的材料。 但请注意,未经我们明确授权,个人学习者不得将本课程的内容用于任何商业目的,包括但不限于销售、转让、许可或以其他方式从中获利。此外,个人学习者也不得擅自修改、复制、传播、展示、表演或制作本课程内容的衍生作品。 任何未经授权的使用均属侵权行为,我们将依法追究法律责任。如果您希望以其他方式使用本课程的内容,包括但不限于引用、转载、摘录、改编等,请事先与我们取得联系,获取书面授权。感谢您对"比特就业课"课程的关注与支持,我们将持续努力,为您提供更好的学习体验。 特此说明。 比特就业课版权所有方。

对比特课程感兴趣,可以联系这个微信。



### 1. Ubuntu

### 安装HAProxy

- 1 #更新软件包
- 2 sudo apt-get update

```
4 #查找haproxy
5 sudo apt list|grep haproxy
6 
7 #安装haproxy
8 sudo apt-get install haproxy
9
```

### 验证安装

```
1 #查看服务状态
2 sudo systemctl status haproxy
3
4 #查看版本
5 haproxy -v
6
7 #如果要设置HAProxy服务开机自启,可以使用:
8 sudo systemctl enable haproxy
```

#### 执行结果:

```
1 root@hcss-ecs-2618:~# sudo systemctl status haproxy
 2 ● haproxy.service - HAProxy Load Balancer
        Loaded: loaded (/lib/systemd/system/haproxy.service; enabled; vendor
   preset: enabled)
        Active: active (running) since Wed 2024-05-15 16:57:34 CST; 10min ago
 5
          Docs: man:haproxy(1)
                file:/usr/share/doc/haproxy/configuration.txt.gz
 6
       Process: 45478 ExecStartPre=/usr/sbin/haproxy -Ws -f $CONFIG -c -q
 7
   $EXTRAOPTS (code=exited, status=0/SUCCESS)
 8
      Main PID: 45480 (haproxy)
         Tasks: 3 (limit: 2006)
 9
10
        Memory: 69.4M
           CPU: 92ms
11
        CGroup: /system.slice/haproxy.service
12
                ─45480 /usr/sbin/haproxy -Ws -f /etc/haproxy/haproxy.cfg -p
13
   /run/haproxy.pid -S /run/haproxy-master.sock
14
                └─45482 /usr/sbin/haproxy -Ws -f /etc/haproxy/haproxy.cfg -p
   /run/haproxy.pid -S /run/haproxy-master.sock
15
16 May 15 16:57:34 hcss-ecs-2618 systemd[1]: Starting HAProxy Load Balancer...
17 May 15 16:57:34 hcss-ecs-2618 haproxy[45480]: [NOTICE] (45480): New worker
   #1 (45482) forked
18 May 15 16:57:34 hcss-ecs-2618 systemd[1]: Started HAProxy Load Balancer.
```

```
19 root@hcss-ecs-2618:~# haproxy -v
20 HAProxy version 2.4.24-Oubuntu0.22.04.1 2023/10/31 - https://haproxy.org/
21 Status: long-term supported branch - will stop receiving fixes around Q2 2026.
22 Known bugs: http://www.haproxy.org/bugs/bugs-2.4.24.html
23 Running on: Linux 5.15.0-60-generic #66-Ubuntu SMP Fri Jan 20 14:29:49 UTC 2023 x86_64
24 root@hcss-ecs-2618:~#
```

# 修改haproxy.cfg

vim /etc/haproxy/haproxy.cfg

追加以下内容:

```
1 # haproxy web 管理界面
2 listen stats
       bind *:8100
       mode http
4
       stats enable
       stats realm Haproxy\ Statistics
7
       stats uri /
       stats auth admin:admin
8
9 # 配置负载均衡
10 listen rabbitmq
      bind *:5670
11
12
       mode tcp
13
       balance roundrobin
       server rabbitmq1 127.0.0.1:5672 check inter 5000 rise 2 fall 3
14
       server rabbitmq2 127.0.0.1:5673 check inter 5000 rise 2 fall 3
15
       server rabbitmg3 127.0.0.1:5674 check inter 5000 rise 2 fall 3
16
17
```

在HAProxy的配置文件中, listen stats 是用来设置一个监听器的指令,这个监听器专门用于 HAProxy的统计信息页面。这个页面提供了关于HAProxy运行状况的实时数据,包括当前的连接数、活动会话、以及流量等信息

#### 配置说明:

```
1 # haproxy web 管理界面
2 listen stats #设置一个监听器,统计HAProxy的统计信息
3 bind *:8100 #指定了监听器绑定到的IP地址和端口
4 mode http #监听器的工作模式为HTTP
5 stats enable #启用统计页面
6 stats realm Haproxy\ Statistics
```

```
stats uri /
      stats auth admin:admin #haproxy登录账号和密码
8
9 # 配置负载均衡
10 listen rabbitmq
                #设置监听器
      bind *:5670
                #监听器绑定到的IP地址和端口,也就是集群前端IP,供producer和consumer
11
  来进行选择,由于5672端口已经默认使用,这里选择5670端口
      mode tcp
                 #由于RabbitMQ使用AMQP协议,它是一个基于TCP的协议,所以这里使用TCP模
12
  尤
13
      balance roundrobin
                       #指定负载均衡策略为轮询
      #负载均衡中的集群节点配置,这里选择的rabbit节点
14
      server rabbitmq1 127.0.0.1:5672 check inter 5000 rise 2 fall 3
15
      server rabbitmq2 127.0.0.1:5673 check inter 5000 rise 2 fall 3
16
      server rabbitmq3 127.0.0.1:5674 check inter 5000 rise 2 fall 3
17
18
```

server rabbitmq1 127.0.0.1:5672 check inter 5000 rise 2 fall 3 定义后端RabbitMQ服务器的配置.

- server rabbitmq1: 定义RabbitMQ服务的内部标识, 这里的rabbitmq1 是指haproxy内部使用的, 不是指RabbitMQ的节点名称。
- 127.0.0.1:5672 : RabbitMQ真实的IP和端口
- check inter 5000:定义每隔多少毫秒检查RabbitMQ服务是否可用.
- ▶ rise 2: 定义RabbitMQ服务在发生故障之后,需要多少次健康检查才能被再次确认可用.
- fall 3: 定义需要经历多少次失败的健康检查之后,HAProxy才会停止使用此RabbitMQ服务。

#### 配置后整个文件如下:

不同的服务器,配置文件会略有不同,此处做参考


```
1 global
 2
           log /dev/log
                               local0
 3
           log /dev/log
                               local1 notice
           chroot /var/lib/haproxy
           stats socket /run/haproxy/admin.sock mode 660 level admin expose-fd
 5
   listeners
           stats timeout 30s
 6
 7
           user haproxy
           group haproxy
 8
           daemon
9
10
           # Default SSL material locations
11
12
           ca-base /etc/ssl/certs
           crt-base /etc/ssl/private
13
14
```

```
15
           # See: https://ssl-config.mozilla.org/#server=haproxy&server-
   version=2.0.3&config=intermediate
           ssl-default-bind-ciphers ECDHE-ECDSA-AES128-GCM-SHA256:ECDHE-RSA-
16
   AES128-GCM-SHA256: ECDHE-ECDSA-AES256-GCM-SHA384: ECDHE-RSA-AES256-GCM-
   SHA384: ECDHE-ECDSA-CHACHA20-POLY1305: ECDHE-RSA-CHACHA20-POLY1305: DHE-RSA-
   AES128-GCM-SHA256:DHE-RSA-AES256-GCM-SHA384
           ssl-default-bind-ciphersuites
17
   TLS_AES_128_GCM_SHA256:TLS_AES_256_GCM_SHA384:TLS_CHACHA20_POLY1305_SHA256
           ssl-default-bind-options ssl-min-ver TLSv1.2 no-tls-tickets
18
19
20
  defaults
21
           log
                      global
                       http
22
           mode
23
           option
                         httplog
                         dontlognull
           option
24
25
           timeout connect 5000
           timeout client 50000
26
27
           timeout server 50000
           errorfile 400 /etc/haproxy/errors/400.http
28
           errorfile 403 /etc/haproxy/errors/403.http
29
30
           errorfile 408 /etc/haproxy/errors/408.http
           errorfile 500 /etc/haproxy/errors/500.http
31
           errorfile 502 /etc/haproxy/errors/502.http
32
           errorfile 503 /etc/haproxy/errors/503.http
33
           errorfile 504 /etc/haproxy/errors/504.http
34
35
36
37 # haproxy web 管理界面
38 listen stats
       bind *:8100
39
40
       mode http
       stats enable
41
       stats realm Haproxy\ Statistics
42
       stats uri /
43
44
       stats auth admin:admin
45 # 配置负载均衡
46 listen rabbitmq
       bind *:5670
47
       mode tcp
48
       balance roundrobin
49
50
       server rabbitmq1 127.0.0.1:5672 check inter 5000 rise 2 fall 3
       server rabbitmq2 127.0.0.1:5673 check inter 5000 rise 2 fall 3
51
       server rabbitmq3 127.0.0.1:5674 check inter 5000 rise 2 fall 3
52
53
```

1 sudo systemctl restart haproxy

# 查看HAProxy

访问:http://124.71.229.73:8100/



可以看到咱们的集群节点已经出来了

## 2. CentOS

## 下载并安装

1 yum -y install haproxy

#### 运行结果

```
1 [root@VM-24-3-centos rabbitmq]# yum -y install haproxy
2 Loaded plugins: fastestmirror, langpacks
3 Loading mirror speeds from cached hostfile
4 epel
4.7 kB 00:00:00
5 extras
2.9 kB 00:00:00
6 os
3.6 kB 00:00:00
```

```
7 updates
 2.9 kB 00:00:00
8 updates/7/x86_64/primary_db
 18 MB 00:00:00
9 Resolving Dependencies
10 --> Running transaction check
11 ---> Package haproxy.x86_64 0:1.5.18-9.el7_9.1 will be installed
12 --> Finished Dependency Resolution
13
14 Dependencies Resolved
15
______
  17 Package
                          Arch
  Version
                                Repository
         Size
_______
 ============
19 Installing:
20 haproxy
                          x86 64
  1.5.18-9.el7_9.1
                                updates
         835 k
21
22 Transaction Summary
______
 24 Install 1 Package
25
26 Total download size: 835 k
27 Installed size: 2.6 M
28 Downloading packages:
29 haproxy-1.5.18-9.el7_9.1.x86_64.rpm
 835 kB 00:00:00
30 Running transaction check
31 Running transaction test
32 Transaction test succeeded
33 Running transaction
   Installing : haproxy-1.5.18-9.el7_9.1.x86_64
34
```

```
35 Verifying : haproxy-1.5.18-9.el7_9.1.x86_64

1/1

36

37 Installed:
38 haproxy.x86_64 0:1.5.18-9.el7_9.1

39

40 Complete!
41 [root@VM-24-3-centos rabbitmq]#
42
```

# 修改haproxy.cfg

vim /etc/haproxy/haproxy.cfg

```
1 listen rabbitmq_local_cluster 0.0.0.0:5670
 2
           mode tcp
           balance roundrobin
 3
           server rabbit1 43.143.223.50:5672 check inter 5000 rise 2 fall 3
 4
 5
           server rabbit3 43.143.223.50:5673 check inter 5000 rise 2 fall 3
           server rabbit4 43.143.223.50:5674 check inter 5000 rise 2 fall 3
 6
 7 listen private_monitoring :8100
           mode http
 8
           option httplog
           stats enable
10
           stats uri
11
                            /stats
           stats refresh 5s
12
13
```

#### 配置说明:

```
listen rabbitmq_local_cluster 0.0.0.0:5670 #集群前端IP,供producter和consumer来进行选择,由于5672端口已经默认使用,这里选择5670端口 mode tcp #负载均衡选项 balance roundrobin #轮询算法将负载发给后台服务器 server rabbit1 43.143.223.50:5672 check inter 5000 rise 2 fall 3 #负载均衡中的集群节点配置,这里选择的rabbit节点 server rabbit3 43.143.223.50:5673 check inter 5000 rise 2 fall 3 server rabbit4 43.143.223.50:5674 check inter 5000 rise 2 fall 3 listen private_monitoring :8100
```


```
9 mode http
10 option httplog
11 stats enable
12 stats uri /stats #haproxy 前端页面
13 stats refresh 60s # 60s刷新一次页面
```

# 启动HAProxy

1 systemctl start haproxy

# 查看HAProxy

访问:http://43.143.223.50:8100/stats





可以看到咱们的集群节点已经出来了