Part 1 操作系统概述 凭借 resort oounded concurrency 为束 constraint 2.3.2 短程调度的时机 先请求资源,再管 mutex。 (1) 用户内存中的进程 **非抢占**∶阻塞;运行完毕。**抢占∶<mark>管程 monitor</mark> 原语 primitive** 1.1 Operating System 先 signal,再 wait。不然会死锁 原子操作 atomic operation 宏内核 Monolithic Kernel *栈 stack*:从上往下坨,局部变量 +时间片用尽; 所需资源到达。 (2) 读者写者问题 2.4.1 同步的概念 *堆 heap*:从下往上堆,malloc() 单任务 uniprogramming *2.3.3 短程调度算法* ① 读者优先算法 批处理 batch system data: 全局变量 text: 代码区 (1) FCFS / FIFO 非抢占 互斥:数据一致性 多任务 multiprogramming 数据、栈和属性(即 PCB (2) Round Robin 抢占(时间片) 条件同步: 执行顺序 readcount = 0; rmutex = 1; mutex 分时系统 time-sharing 2.4.2 正确互斥四条件 的集合被称为**进程映像**。每个进程<mark>●时间片结束了才会再找下-</mark> = 1 调用函数 invoke a function 映像都由进程控制块、用户栈、进个,时间片中间来一个进程鸟都 忙则等待、空闲让进、有限等待 Writer Process 程专用地址空间以及和其它进程<mark>不鸟一下</mark>。 111 历史 让权等待。 While(ture) /hile(ture) Performance ●串行处理 Serial 的共享地址空间组成。 2.4.3.1 软件实现互斥 mWait(mutex) • q large ⇒ FCFS
 • q small ⇒ Interleaved 2) Process Control Block ●批处理: 吞吐量优先 Test then set: 无法保证互斥 *q must be large with respect to context switch, otherwise overhead is too high (all overhead) **Set then test**: 互斥是能互斥了, semSignal(进行读操作 ○监控程序 Monitor Process identifier ●多任务处理: 并发度优先 倒是经常死锁/活锁了。 CPU state information ■ How do you choose time slice? What if too big? Response time suffers
What if infinite? Get back FIFO
What if time slice too small? Throughput
suffers! > user-visible, control & status ●分时系统:周转时间优先、响应 Dekker: 有阶级的 Set then test; 时间优先 两个预定锁,互相谦让,客场让主 > stack pointers 用户可改 1.1.3 System Call vs API 场,主客场轮流当。 ② 公平情况算法 Comparisons between FCFS and RR Process control infomation Assuming zero-cost context-switching time, is RR alway better than FCFS? System calls Analysis of Peterson's algorithm readcount = 0; rmutex = 1; mutex ·scheduling:状态,优~级,事件 boolean P1WantIn = false; //must be in shared memory boolean P2WantIn = false; //must be in shared memory int turn = 1; //must be in shared memory P1: Simple example: 10 jobs, each takes 100s of CPU time
RR scheduler quantum of 1s
All jobs start at the same time □ Request OS services = 1; *wmutex = 1* used memory and I/O, opened * Process control: abort, create, terminate process Reader process: Completion Times: Job # FIFO RR 1 100 991 2 200 992 allocate/free memory while(ture){ ♦ File management: create, delete, open, close file le (true) {
PI WantIn = true;
turn = 2;
while (P2WantIn && turn == 2) do {nothing}; //检测是否有写者存在, 无空 pointer to next PCB ❖ Device management: read, write, reposition device //申请使用readcount //读者数量加1 2.2 线程与进程间通信 readcount++; If the order is reversed and a process is preempted after setting the turn variable but before setting the Wantin variable, then both processe can get into the critical section. *Information maintenance: get time or date C.S.1; if (readcount=1) semWait(mutex); //如果此为第 2.2.1 线程 Both RR and FCFS finish at the same time Signal(rmutex); //释放readcount的使用权, ; Signal(wmutex); //恢复wmutex *Communications: send/receive message remainder section; 独立拥有: Program Counter、寄 Average turnaround time is much worse under RR!
 Bad when all jobs have same length 1.1.4 实时系统 进行读操作; 存器组、栈空间 utex): //申请readcount的使用权。 与兄弟线程共享:代码区、数据(3) SPN / SJF 非抢占 ● 硬实时:保证准时完成。 readcount—; //读者数量減1 if(readcount—0) semSignal(mutex); //如果没有读 semSignal(mutex); //郑荣放readcount的使用权, 2.4.4 信号量 ●选定了就让它运行完! 软实时: 重要任务优先级高而区、操作系统资源 lacktriangleShortest Path Next 已, 未必能准时。 Semaphore structure (1) TCB: 见 PCB 红色字 Shortest Job First A new data structure called semaphore

An integer with a nonnegative initial value : s.count

An initially empty queue: s.queue 1.2 计算机硬件 semInit(s) Multithreading requires changes in the prodescription model Writer process: (4) SRTF 抢占(到达) 特权指~ privileged instruction each thread of execution receives its own control block and stack P1: semWait(s while {true} ●一有新进程到,立刻重新选 轮询 poll struct semaphore {
 int count;
 queueType queue 人。老渣男了! -1 P2: semWait(s //检测是否 own execution state
 ("Running", "Blocked", etc.)
 own copy of CPU registers ●指令是通过数据总线传输的 semWait(mutex); //申请对数 Shortest Remaining Time F~ 1.2.1 中断 -2 P3: semWait(s 进行写操作 data > own execution history (stack) Three atomic operations on semaphore
• Initialize s: semInit(s) ●硬中断 Interrupt □ SPN/SRTF are the best you can do at minimizing avera semSignal(mutex); //释放数基 turnaround time //恢复wm the process keeps a global control block listing resources 由硬件发起、异步的 Increase s: semSignal(s)Decrease s: semWait(s) progran code Provably optimal (SPN among non-preemptive, SRTF among preemptive) Since SRTF is always at least as good as SPN, focus or SRTF ●软中断 Exception 由软件发起、同步的 (2) U-to-K 模型 SRTF
Comparison of SRTF with FCFS and RR

What if all jobs the same length?

SRTF becomes the same as FCFS (i.e., FCFS is best car
do if all jobs the same length)

What if jobs have varying length?

SRTF (and RR): short jobs not stuck behind long ones 2.4.5 管程 Semaphores: A special data structure, includin an integer variable and a queue. ○陷阱 Trap: System Call ● 共享、安全、互斥 2.2.2 Inter-Process Communi~ · Integer is used for signaling Queue is used to hold processes waiting on the semaphore (1) P 唤醒 Q ○错误 Fault (1) 分类 〇中止 Abort ●共享内存 shared memory ● P 等待 O 执行: Hoare semWait(P) primitive is used to receive signal 1.2.3 硬件级保护 Q 等 P 继续执行: MESA ●消息传递 MsgPass (SysCall) semSignal(V) primitive is used to send signal Starvation

SRTF can lead to starvation if many small jobs!

Large jobs never get to run
Somehow need to predict future

How can we do this? semWait and semSignal cannot be interrupted (2) Hoare Socket Privileged instructions O Remote Procedure Call ● 不可用于通信: condition 链 ● 强信号量: FIFO Examples How can we do this?
Some systems ask the user
When you submit a job, have to say how long it will take
To stop cheating, system shills job if takes too long
But: even non-malicious users have trouble predicting runtil
Bottom line, can't really know how long job will take
However, can use SRTE as a yardstick for measuring other j (2) 信息传递 ● 入口等待队列、条件变量队列、 • Change mode bit in processor status register 信号量三大用途 . Change which memory locations a user program can ●阻塞式发送:发送方阻塞到消息 紧急等待队列。 *互斥*:初始化为1 被接收方接收完毕。 ●非阻塞式发送:发送方后台发送 (3) 管程与生产消费者问题 Send commands to I/O devices • 有限并发: 初始化为 n producer put(item) //放数据 Jump into kernel code 通信 signaling: 初始化为 0 SRTF Pros & Cons { item nextp; 信息,前台继续干别的事情。 -、*会合 Rendezvous* //所有缓冲区为满缓冲区 Non-privileged ("safe") instructions if (count==n) ●阻塞式接收: 等~ Guarantee that a1 happens before cwait(notfull); //等待空缓冲区 5) Priority 抢占或非抢占 Examples 非阻塞式接收:收到之后再调个 buffer(in)=nextp; b2 and b1 happens before a2. . Load, store ● 低优先级进程饥饿 starve in=(in+1)mod n: Add, subtract, 回调。 Create two semaphores, named aArrived and bArriv * aArrived indicates whether Thread A has arrived at the rendezvous, and bArrived likewise ● 优先级反转 priority inversion: count=count+1; Conditional branch, jump to subroutine, . (3) RPC if(full队列不为空) csignal(notempty); H 被 M 抢跑了。H/L 共享资源 and initialize them both to zero. 客户端 stub;服务端 skeleton Even better approaches //唤醒等待满缓冲 区队列中的进程 R、M 不需要 R。L 先把 R 锁了。 2.3 进程调度 ■ SPN/SJF is an example of priority scheduling Problems with the additive base and bounds? statement b1; statement a1: rocedure get(item)//取数据 { item nexte; if (count==o) //所有缓冲区为空缓冲区 cwait(notempty); //等特一个装满数据的缓冲区 nexte=buffer(out); semSignal(bArrived); Memory sharing between processes? (e.g., how to share one copy of same machine instructions) . In SPN, the shortest job has the highest priorit semSignal(aArrived); semWait(bArrived); Can also assign processes fixed priorities
 Process priority is usually represented as a number
 Varies whether higher or lower numbers correspond to priority semWait(aArrived); nedium-term scheduling statement a2; statement b2; Memory fragmentation as processes come and go 周转时间 Turnaround Time Paging and segmentation 多人会合在同一点: ♦ Translation done in hardware, using a table for each 服务时间 Service Time process Priority scheduling can be preemptive or non-preempti out=(out+1)mod n; If non-preemptive, a new higher-priority process added to ready queue won't take the CPU from a lower-priority running process
If preemptive, a new higher-priority process added to ready queue immediately takes the CPU from a lower-priority out-(out-)mouth, count-count-1; if (empty队列不为空) csignal(notfull)} //唤醒等待空缓冲区队列中的进程 总等待时间 Waiting Time · Table is set up and managed by kernel 首次应答时间 Response Time tex = 1; //mutex provides exclusive access to count so tha
//threads can increment it safely
rier = 0; //barrier is locked (zero) until all threads arrive ●所有 I/O 操作都是特权指令 季吐量 Throughput ←RAID running proces {in=0; out=0; count=0; } //管程变量初始化 (3) 内存保护 2.3.1 长中短调度 (6) Multilevel Queue Sche~ Base register & limit register 长: 从磁盘进入内存 (新建→就绪) (7) M~ Feedback Queue S~ Producer while(true){ while(true) { Memory protection degree of multiprogrami~、合理搭●反馈即:可在队列间移动 生产item pc.get(item); 配计算-I/O 密集进程 ●队列间 RR, 队列内 FIFO。 pc.put(item): 消费item: . Interrupt vector and the interrupt service routines 中:是否挂起 suspend(内存移到●优先级越高的队列,时间片就 • Data access and over-write from other programs 例题 □ HW support: two registers for legal address 磁盘), swap out: 滚出内存。 越短。 2.5 死锁与饥饿 determination (1) 生产者-消费者问题 短: 下一个给 CPU 的是谁? Base register – holds the smallest legal physical memory address
 Limit register – contains the size of the range ●一旦某个进程被系统抢占一 死锁检测 Deadlock detection Unbounded buffer, 1 producer, 1 consumer 决策者 scheduler 次,那么它就会被移到低一个优 花锁恢复 Deadlock Recovery ✓ in modified only by producer and out only by consume 执行者 dispatcher: 上下文切换 no race condition; no need for mutexes, just a while loop 先级的队列的队尾。 花锁预防 Deadlock Prevention ☐ Memory outside the defined range is protected item[] b; wn wn wn wn wn int in, out; 跳转到程序的对应位置 ●新进程会直接进入最高优先级 死锁避免 Deadlock Avoidance OS Service Hardware Support 队列的队尾。 while (true) {
 item = produce(); Dispatch latency – time it takes for the dispatcher stop one process and start another running: Kernel/User Mode 死锁、活锁与饥饿 while (out == //忙等待, 不能从 item = b[out] (8) HRRN 非抢占 Protected Instructions 「日 次一 がしが、 が譲、当多・进程間の計申清果英流源計、のお採用一定的分配策略(領度策略)分配景應・分配策略可能是公平的、能格正请求 者在有限的间内获得所需资源。也可能是不公平的、銀不能保 工等特時间的上半、当等特時间的成項問題等時半、生进程 環、以至于进程无法按要求完成が、称为成死。 学様、た故学統合修理下出来が相称を生ませ b[in] = item; in++; Base & Limit Registers Scheduling time ●最短相应比 w+s/s Interrupt re-enabling time
 Context switch time Interrupts Interrupt Vectors 2.4 互斥与同步 System Calls Trap Instructions Synchronization 2) 有限 buffer, 多产多消 I/O Interrupts, Memory-Mapping 互斥 Mutual Exclusion Scheduling criteria Synchronization Atomic Instructions 条件同步 Condition Synchro~ Producer: Consumer: (特死与死師的差別: □ CPU utilization: keep the CPU as busy as possible Virtual Memory Translation Lookaside Buffers while (true) while (true) ☐ Throughput: # of processes that complete their execution per time unit 6界区 critical section Scheduling Produce an item Timer 死锁一定发生循环等待,饿死则不一定; 死锁一定涉及多个进程,饿死的进程则可能是一个 竞争条件 race condition semWait(empty); semWait(full); ☐ Turnaround time: amount of time to execute a semWait(mutex) Part 2 进程管理 particular process 有限等待 bounded waiting Buffer(in)=item; item=Buffer(out); 2.5.1 死锁四条件 ■ Waiting time: amount of time a process has been waiting in the ready queue 2.1 进程 值信号量 binary semaphore in=(in+1)%n; out=(out+1)%n; ● 资源互斥、持有等待、不可抢占 Response time: amount of time it takes from when a request was submitted until the first response is produced, not output (for time-sharing environment)

有限并发 semSignal(mutex); 抢占 preemption semSignal(empty); ● 循环等待 semSignal(full);} 级联的 cascading consume the item

2.5.2 数学建模 While performance depends on the exact sequence of process requests and sizes, statistical conclusions can 读 链式 Basic Functions of I/O Subsystem (1) 联合进程图示 process r reached: Presents a logical or abstract view of communication ar storage devices to the users and to other high-level subsystems by hiding the details of the physical devices 区大小是固定还是可变 可变 固定块 固定块 可 Joint Progress Diagram Best-fit placement 低到高 (2) 资源分配图 First-fit placement the best and fastest Resource Allocation Graph 通过汉明码实 现冗余 Contiguous Allocation Next-fit placement ext-fit placement the runner-up: slightly worse than first-fit, because it sprea fragmentation more evenly (whereas first-fit has a tendence preserve big blocks at the end of memory) ◇ 後の原忠党CPU→順へ報商収合升行 Supports the convenient sharing of communication and storage devices. ◆ 共享设备的使用,设备保护、分配和调度 ●显式 Chained:文件名,起始,长度 00 ●隐式(Implicit) Chained: FAT □ Resource Type with 4 instances 2N●Indexed Allocation 路板 Buddy System: 二分与融合 Each I/O device consists of two parts: \square P_i requests instance of R_i the controller or module, containing most of the the device proper, such as a disk drive 把 block 表也存进 block 里 *求兄弟*: 找到对应的位,翻-○改1: var-length portion 3.1.4 内存不够怎么办 \square P_i is holding an instance of R_i The job of the controller is: RAID2, to control the I/O and handle bus access for i 节流:overlay (固定区、覆盖区) ○改2: Multilevel Indexing(inode 2.5.3 检测并恢复 6.1.4 Free-space Management 开源: compact、swap ● 所有资源、当前可用资源 Why I/O controllers? Why not connecting the deviced directly to the bus? * wide variety of peripherals with various operation methods: don't want to incorporate heterogeneous logic into CPU * controllers offer a more unified hardware command interface data transfer rate slower or faster than memory or CPU * different data and word lengths * multiplexing one module serving several devices (ex: SCSI) * Functions of an I/O device controller * interface to CPII and memory, six sastem bus 把所有空闲空间连一起看作swap 文件内类似动态分区。 ● 总资源请求、当前已分配资源 大文件。●Bitmap ●Linked list 3.2 虚拟内存 还要多少资源 ●Grouping:记 index 的 block 成链 esident set 驻留集 ●检测时机:某进程开始等待、定 ●Counting:类似 IndexAlloc 的改 2 ranslation Lookaside Buffer 时检测 ●页号从0开始 6.2 inode 资源分配图化简 ●文件名不存在文件的 inode 中 □连续模式:给一个进程分配一个连续的内存空间 ● 先看 只有入边 的进程 interface to CPU and memory via system bus ◆单一连续分配: 只适用于单道程序系统 而是存在目录的 inode 中。 interface to one or more peripherals by custom data links ▼ 上头方配: 欠运用了平运在户系统 ● 固定分区: 分区大小固定 — ⇒ 动态分区: 分区大小依程序大小变化 — ◆ 伙伴系统: 固定分区与动态分区的综合 :当时 ● 只要这些进程赶紧走掉就能释 ●12 个一级指针(直接指针) 放资源了 读时最快为单个磁盘的两 倍:写时与单个磁盘相近 接口寄存器(可寻址的,即 系统为其分配了地址),可 分成: 2.5.4 死锁预防 {<u>=</u> = 于单个磁盘 ●静态 个磁盘 ◆段页式:分段与分页的综合 Remove one of the design or scheduling conditions? File b 相似 ◆ 地址接口寄存器 (CPU写, 主 制器法) 相似 3.2.1 内存分页 remove "mutual exclusion": 用瓦 写时 当时 ●小页面:减少页内碎片,提高内 File b → not possible: must always be supported by the OS: 但可增力 存利用率,但进程页表变长、且会 remove "hold & wait"? require that a process gets all its res 降低页面换进换出的效率。 → inefficient and impractical: defeats interleaving, cre-waits, cannot predict all resource needs ●LA 转 PA remove "no preemption" = allow preemption ● は 森 , . . ● 缺页中断的处理 I/O地址空间: I/O功能的地址集合称为I/O空间,包括: □ remove "circular wait"? 内存中用以映射设备的数据缓冲区 ex: impose an ordering of resources →inefficient, again 1/O地址空间在系统中配置的三种模式 ※ 独立于内存的I/O地址空间模式。I/O地址空间与内存 互独立、对I/O地址空间的访问需要用特殊的I/O指令 • 发起缺页中断: MMU 查询页表失败,即目标内存页已被 sw 1100 2.5.5 死锁避免 OS 将讲程置为 Blocked 映射到內存空间的I/O地址空间模式,I/O寄存器映射成內存的一部分,可以用內存访问语句来读写I/O设备寄存器。Monay Apped 混合模式 ~ bufer 内映 ,控制考查器。 独 谕 • OS 发起 I/O 请求,将页面从磁盘中 swap 入内存 在 I/O 操作在后台运行的时候, CPU 将让位给下一个进程 I/O 完成。硬件发起 I/O 中断。OS 返回 Programmed I/O (or "polling" or "busy waiting"): 修改页表 • 将上述进程重新置为 Ready the CPU must repeatedly poll the device to check if the I/O request completed 小结:银行家算法中的数据结构 ●哈希页表: 把「进程号+页号」拿 Interrupt-driven I/O: 中断I/O

●动态 (1) 介入时机: 有新资源请求

(2) 银行家算法: 死锁检测扩展

□ 资源向量 Resource: 是一个含有m个元素。其中的每一个元素代表类资源全部数目。

央资和Courter 是一个含有m个元素,其中的每一个元素代表 类资和企物设计。 可利用资源的高水和lable: 是一个含有m个元素,其中的每一个元素 代表一类可利用的资源就用。其物量是系统中两能置约的类杂金原可用 酸聚量且,如果在malable[j]。本、表示像中域有集实资源外, 最大市果地所代am,是一个含有m×m的矩阵。它定义了系统中中 可能的每一个运程和两类强的线流流来,如果Camid)。由。 不进行调度和两类强的线流流来,如果Camid)。由。 分能即用Gamid 是一合有m×m的矩阵。它定义了系统中每一 类资温高高之分流的每一进程的资源效。如果Allocation(i,j)。k。表 定程行由它分离,及解除一位。 需求矩阵 Request 是一个含有m×m的矩阵,即以表示每一个进程的 前分类资源或,如果Reed(i,j)。k。表示逻程证言是来类资源体个 方能论成从任务。 Request(i,j)。Claim(i,j)-Allocated(i)

Part 3 内存管理 3.1 实内存管理

●存储管理: 掉电后信息丢失


●设备管理: 掉电后信息仍在

●主存的作用: CPU 取指令与数据

CPU 与外设通讯。 ●时间局部性:循环 ●空间局部性:顺序执行

3.1.2 程序的装入

□ 符号名地址→独立的逻辑地址→统一的逻辑地址→物理地址



●绝对装入: 仅适用于单道

●静态重定位: 装入已是 PA

●动态重定位:装入仍装 LA

3.1.3 内存分配方案

Fixed Partitioning:分书架、可以页面变成两条命 equal-size 也可以 unequal。涉及分>蓝色是收回 "免死金牌" 的机制 区表、进程表。

Dynamic~: 堆箱子。涉及分配分

区表、空闲分区表(链) First-Fit: 每次都从全局开头找

Next~: 从上次分配位置开始找 Best-Fit: 恰恰好

Worst-Fit: 找最大空格、土豪 从搜索空闲区速度及主存利用率来看,最先适应分配算法、适应分配算法和最佳适应算法性能好。 如果空闲区较从小到土排列、则最先适应算法性能好。 分配算法。反之、如果空间区按从大到小排列。则最先适应

空闲区按从小到大排列时,最先适应分配算法能尽可能使用低

由于最先适应算法简单、快速,在实际的操作系统中用得较多; 其次是最佳适应算法和下次适应算法

Direct Memory Access (DMA): 直接存储器访问

the CPU is involved only at the start and the end of the
transfer; it delegates control to the I/O controller that
accesses memory directly without bothering the CPU 3.2.3 段页式 段内页号P 页内地址W 页偏移量W 段内地址d (段偏移量) 3.2.4 Replacement Policy **Local Replacement** 主导权在置换算法
 先为每个进程分配一定量的页框。OS有一个空闲页框队列,有进程缺页时从空闲队列取页框板 框,直至缺页率减少到 适当值为止。 • 主导权在驻留集管理

3.2.2 内存分段 ●分段在编译时由编译程序完成

3.2.5 开算 注意,性能曲线中 OPT 无论如何都 无法与其它相交, 它是界。

●最优置换策略 OPTimal

淘汰掉在未来最晚用掉的 ●最近最久不使用 LRU

约定最顶上的一个最安全

只要一有内存访问,就要把访问指文件内部的结构安排 的页面提前。

可行的最优策略, 但开销大

●免死金牌 Clock/NRU

>新页面起手两条命、刚被访问的

坡蓝色指到的页面,扣一条命;扣 到没命的就寄、被换出、蓝标给下 -个人——先杀人,再移动。

初始置页的时候,蓝标是卡在第空间管理、目录结构、文件 ·格不变的。<mark>别做快,记得扣命</mark> 若加多一个 M 位,则扫第—遍找<mark>挂载分区信息</mark>

A/M 均为 0 的、第二遍扫 A=0 的、 并按照 NRU 扣金牌,必要时重复

上述两步。 FIFO

Part 5 I/O Management ●Block devices 块设备

可寻址、块式存储、互独访问

e.g. 磁盘、磁带 Character/Stream devices

字符流、不可寻址。键鼠/网络

提而CFOAI/O设备之间的开行在 冲的实现方法 采用专用的硬件缓冲器(如Cache,I/O设备和控制器内部的 用缓冲区) 在内存中划出一个具有n个存储单元的缓冲区,称"软件缓冲"。 也称"内存缓冲区"。

the CPU can switch to other tasks and is (frequinterrupted by the I/O device

缓冲技术实现的有效性前提 作为的块是按性包括突发性与间歇性)的快,而不是持续性 快,例:各种I/O缓冲区)。 访问局部性,即局部的数据被连续多次访问(例:Cache)。

(TEU37)へ 緩和CPU与I/O设备之间速度不匹配的矛盾 减少对CPU的中断频率,放宽对CPU对中断响应时间的限制。 提高CPU和I/O设备之间的并行性

为解决什么问 趣而引入 直观的解决方案 简单、公平 未对寻消进行 FIFO 先进先出 SSTE 与了解决FIFO

最短服务时 遊时间要短 会导致"饥饿 现象 兼顾了较小的寻 偏向于两端(这时间和防止饥 内、最外)的 | 取短服务时 | 算法平均寻垣时 | 同姓长的问题 | SCAN | 为了解決SSTF | 扫描(电梯) | 导致的"饥饿"

Part 6 File

少条记录。

● File Logical Structure

0 字节流

o Record Sequence

♦ Pile

♦ Sequential File

♦ Indexed File

♦ Indexed Sequential File o Tree

6.1 File System Implementation ●盘上信息:启动扇区、已用未用Bootloader 进入保护模式

●内存中信息: 两张 FCB、"DCB"、

> 进程的 FCB: 文件描述符(指针 6.1.1 Directory Implementation

Linear list

●Hash table: 基于链表的改进 6.1.2 Record blocking

洁构化文件的组块、I/O 基本单位 Fixed blocking

Variable blocking unspanned

o spanned 6.1.3 File Block Allocation

Word Bank ocality 局部性 integrity 完整性

拉斯斯斯

程的

运行时间短的进 (简称短进程) 利;对 I/O 密集

对长进程不利

非抢占

(时间片用完

非抢占 min(s)

お占へ

非抢占

min[s

x + W

一春吐

按 按 数

ierarchy 等级制度 LRU,cache,TLE imultaneously 同时地

confidentiality 机密性 chronological 按时间顺序的 imeliness 及时性 temporal loca

ewind 倒带 propensity 倾向

langling pointer 悬挂 icyclic-graph 无环图 ransient 短暂的 malicious 恶意的

analogous 相似的 explicit 显式的、明确的

mplicit 隐式的 concatenate 连挂 detach 分离;派遣 <mark>spatial local</mark>

●组块因子 F: 一个组块里面有多<mark>integrated 综合的、融合的</mark> edundant Array of Independen

Disks 冗余磁盘阵列 ognitive ability 认知能力

propensity 倾向;习性 nacroscopic 宏观的; 肉眼可见的

<mark>nypothetical 假设的</mark>sufficient足够 dedicate 致力; 献身

duplicate *n./adj.* 完全一样的 provably 可证明地 nudge 推动

nheritance n. 继承物 Lab 1 系统软件启动过程

Bootloader 加载 ELF 格式的 OS 的过程; 函数调用堆栈跟踪函数; 中断初始化和处理 Lab 2 物理内存管理

实现 first-fit 连续物理内存分配 算法;寻找虚拟地址对应的页表项 释放某虚地址所在的页并取消对 应二级页表项的映射 Lab 3 虚拟内存管理

给未被映射的地址映射上物理页**奖** 基于 FIFO 的页面替换算法 Lab 5 用户进程管理

自己的内存空间给子进程

映射、保护

加载应用程序并执行;父进程复制 by @Jonbgua, https://icourse.club/user/6436