



© 2008 Emprise Corporation. All Rights Reserved. For more information on this and other products visit: www.emprisecorporation.com

Table of Contents

	Foreword	(
Part I	Getting Started	30
1	Overview	31
2	Implementation Instructions	33
3	Creating Your First Chart	35
4	Customizing Your Chart	40
5	Anatomy of a Chat	41
	Y Axis	
	X Axis Hint	
	Chart Body	
•	Legend	
6	Version 1.x Compatability Deprecated Properties, Methods and Events	
7	Deployment	
Part II	Changes	48
1	Changes in version 2.3	48
2	Changes in version 2.1	49
3	Changes in version 2.0.1	49
4	Changes in version 2.0	50
5	Changes in version 1.3.1	5
6	Changes in version 1.3	51
7	Changes in version 1.2.1	52
8	Changes in version 1.2	52
9	Changes in version 1.1	54
10	Changes in version 1.0.1	55
11	Changes in version 1.0	56
Part III	Data Formats	57
1	XML - Full	58
2	XML - Short	59
3	XML - Compact	59
Part IV	API Reference	60
1	EJSC	60
	Properties	-
	DefaultImagePath DefaultColors	
	Delauliculuis	60

	DefaultBarColors	61
	DefaultPieColors	61
	STRINGS	62
2	EJSC.Chart	62
	Properties	63
	allow interactivity	63
	allow_mouse_wheel_zoom	63
	allow_move	64
	allow_zoom	64
	allow_hide_error	64
	auto_find_point_by_x	65
	auto_mic_by_x	65
	auto_rosize	65
	axis_bottom	66
	axis_left	67
	axis_right	67
	axis_top	68
	background	69
	building_message	69
	drawing_message	69
	legend_state	69
	legend_title	70
	max_zoom_message	70
	message_timeouts	70
	proximity_snap	70
	show_hints	71
	show_legend	71
	show_messages	71
	show_titlebar	72
	title	72
	Methods	72
	acquireSeries	72
	addSeries	73
	clearSelectedPoint	73
	exportSVG	74
	exportSVGLegend	75
	findClosestPoint	76
	getLegendState	77
	getMinMaxYInXRange	77
	getSeries	77
	getZoomBoxPixelCoordinates	77
	hideTitlebar	78
	hideZoomBox	78
	legendMinimize	78
	legendRestore	78
	redraw	78
	remove	79
	removeSeries	79
	selectPoint	79
	setAutoResize	79
	setLegendTitle	79
	setShowLegend	80
	setTitle	80
	showTitlebar	80

showZoomBox	80
Events	81
onAfterBuild	81
onAfterDraw	81
onAfterDrawSeries	81
onAfterMove	
onAfterSelectPoint	82
onAfterUnselectPoint	
onAfterZoom	
onBeforeBuild	
onBeforeDblClick	
onBeforeDraw	
onBeforeDrawSeries	
onBeforeSelectPoint	
onBeforeUnselectPoint	
onContextMenu	
onDblClickPoint	
onShowHint	
onShowMessage	
onUserBeginZoom	
onUserEndZoom	
Deprecated	
Properties	
force_static_points	
force_static_points_x	
force_static_points_y	
legendTitle	
show_crosshairs	86
show_grid	86
show_mouse_position	86
show_x_axis	86
show_y_axis	86
x_axis_caption	86
x_axis_className	86
x_axis_extremes_ticks	86
x_axis_formatter	86
x_axis_max_tick_interval	86
x_axis_min_tick_interval	86
x_axis_minor_ticks	86
x_axis_size	86
x_axis_stagger_ticks	87
x_axis_tick_className	87
x_axis_tick_count	87
x_cursor_position_caption	87
x_cursor_position_formatter	
x_max	87
x_min	87
x_value_hint_caption	87
x_zero_plane	
y_axis_caption	
y_axis_className	
y_axis_extremes_ticks	
y_axis_formatter	
y_axis_max_tick_interval	
<u></u>	

	y_axis_min_tick_interval	87
	y_axis_minor_ticks	87
	y_axis_size	88
	y_axis_tick_className	88
	y_axis_tick_count	88
	y_cursor_position_caption	88
	y_cursor_position_formatter	88
	y_max	88
	y_min	88
	y_value_hint_caption	88
	y_zero_plane	88
	Methods	88
	addXAxisBin	88
	addYAxisBin	88
	convertPixelToPoint	88
	convertPointToPixel	88
	findClosestPointInSeries	88
	hideGrid	88
	hideXAxis	89
	hideYAxis	89
	getXExtremes	89
	getYExtremes	89
	getZoom	89
	removeXAxisBin	89
	removeYAxisBin	89
	selectClosestPoint	89
	setCrosshairs	89
	setXAxisCaption	89
	setXExtremes	89
	setYAxisCaption	89
	setYExtremes	89
	setZoom	89
	showGrid	89
	showXAxis	89
	showYAxis	90
	Events	90
	onAfterShowCrosshairs	90
	onBeforeBeginZoom	90
	onBeforeEndZoom	90
	onShowCrosshairs	90
	onXAxisNeedsTicks	90
	onYAxisNeedsTicks	90
3	Axis Types	
	•	
	LinearAxis	90
	Properties	91
	background (inherited)	
	border (inherited)	
	caption (inherited)	
	caption_class (inherited)	
	color (inherited)	
	crosshair (inherited)	
	cursor_position (inherited)	93
	extremes_ticks (inherited)	94
	force_static_points (inherited)	94

formatter (inherited)	94
grid (inherited)	95
hint_caption (inherited)	95
label_class (inherited)	
major_ticks (inherited)	
max_extreme (inherited)	
min_extreme (inherited)	
minor_ticks (inherited)	98
size (inherited)	98
stagger_ticks (inherited)	
visible (inherited)	
zero_plane (inherited)	
Methods	100
addBin (inherited)	
getExtremes (inherited)	
getZoom (inherited)	
getZoomBoxCoordinates (inherited)	
hide (inherited)	
hideGrid (inherited)	
pixelToPoint (inherited)	
pointToPixel (inherited)	
removeBin (inherited)	
resetZoom (inherited)	
setCaption (inherited)	
setCrosshair (inherited)	
setExtremes (inherited)	
setZoom (inherited)	
show (inherited)	
· · · · ·	
showGrid (inherited)	
Events	104
onHideCrosshair (inherited)	
onHideCursorPosition (inherited)	
onNeedsTicks (inherited)	
onShowCrosshair (inherited)	
onShowCursorPosition (inherited)	
LogarithmicAxis	106
Properties	107
background (inherited)	107
base	
border (inherited)	
caption (inherited)	
caption_class (inherited)	
color (inherited)	
crosshair (inherited)	
cursor_position (inherited)	
extremes_ticks (inherited)	
force_static_points (inherited)	
formatter (inherited)	
grid (inherited)	
hint_caption	
label_class (inherited)	
major_ticks (inherited)	
max_extreme (inherited)	
min_extreme (inherited)	113

minor_ticks (inherited)	11
size (inherited)	11
stagger_ticks (inherited)	11
visible (inherited)	11
zero_plane (inherited)	11
Methods	11
addBin (inherited)	11
getExtremes (inherited)	11
getZoom (inherited)	11
getZoomBoxCoordinates (inherited)	11
hide (inherited)	11
hideGrid (inherited)	11
pixelToPoint (inherited)	11
pointToPixel (inherited)	11
removeBin (inherited)	11
resetZoom (inherited)	
setCaption (inherited)	
setCrosshair (inherited)	
setExtremes (inherited)	
setZoom (inherited)	
show (inherited)	
showGrid (inherited)	
Events	
onHideCrosshair (inherited)	
onHideCursorPosition (inherited)	
onNeedsTicks (inherited)	
onShowCrosshair (inherited)	
onShowCursorPosition (inherited)	
ateAxis	
Properties	
background (inherited)	
border (inherited)	
caption (inherited)	
caption_class (inherited)	
color (inherited)	
crosshair (inherited)	
cursor_position (inherited)	
extreme_ticks (inherited)	
force_static_points (inherited)	
formatters (inherited)	
grid (inherited)	
label_class (inherited)	
max_extreme (inherited)	
,	
major_ticks (inherited) min_extreme (inherited)	
minor_ticks (inherited)	
size (inherited)stagger ticks (inherited)	
stagger_ticks (inherited)	
visible (inherited)	
zero_plane (inherited)	
Methods	
addBin (inherited)	
getExtremes (inherited)	
getZoom (inherited)	

	getZoomBoxCoordinates (inherited)	13
	hide (inherited)	
	hideGrid (inherited)	
	pixelToPoint (inherited)	
	pointToPixel (inherited)	
	removeBin (inherited)	
	resetZoom (inherited)	
	setCaption (inherited)	
	setCrosshair (inherited)	
	setExtremes (inherited)	
	setZoom (inherited)	
	show (inherited)	
	showGrid (inherited)	
	Events	
	onHideCrosshair (inherited)	
	onHideCursorPosition (inherited)	
	onNeedsTicks (inherited)	
	onShowCrosshair (inherited)	
	onShowCursorPosition (inherited)	
1		
4		
	EJSC.AlarmSeries	
	Properties	
	autosort (inherited)	13
	axis	13
	color (inherited)	13
	coloredLegend (inherited)	14
	delayLoad (inherited)	14
	fill	14
	fillTo	14
	flag	14
	hint_string (inherited)	14
	legendlsVisible (inherited)	14
	lineOpacity (inherited)	14
	lineWidth (inherited)	14
	opacity (inherited)	14
	padding (inherited)	14
	title (inherited)	14
	visible (inherited)	
	Methods	
	findClosestByPixel (inherited)	
	findClosestByPoint (inherited)	14
	getDataHandler (inherited)	14
	getPadding (inherited)	14
	getVisibility (inherited)	14
	hide (inherited)	14
	hideLegend (inherited)	14
	reload (inherited)	14
	setColor (inherited)	14
	setColoredLegend (inherited)	14
	setDataHandler (inherited)	14
	setLineOpacity (inherited)	14
	setLineWidth (inherited)	14
	setOpacity (inherited)	14
	setPadding (inherited)	14

set	tTitle (inherited)	147
	ow (inherited)	147
	owLegend (inherited)	147
	3	148
	AfterDataAvailable (inherited)	148
	AfterVisibilityChange (inherited)	148
	BeforeVisibilityChange (inherited)	148
		148
	ShowHint (inherited)	
	ogGaugeSeries	149
•	rties	150
	chor	150
axi		150
	layLoad (inherited)	151
	Color	151
fillC	Opacity	151
hei	ight	151
lab	pel	152
leg	gendIsVisible (inherited)	152
loc	k	152
ma	arker_position	153
ma	ax	153
mir	n	153
mir	norTick	154
	edle	154
	sition	155
•	nge	155
	nge_degrees	156
		156
	nges	
	ırt_degree	156
tick		156
	kCount	157
	e (inherited)	157
vis	ible (inherited)	157
wic	dth	157
X_8	axis_formatter (inherited)	158
Method	ds	158
get	tDataHandler (inherited)	158
get	tVisibility (inherited)	158
hid	de (inherited)	158
hid	leLegend (inherited)	159
	oad (inherited)	159
	tDataHandler (inherited)	159
	tTitle (inherited)	159
	ow (inherited)	159
	owLegend (inherited)	160
_	S	160
	AfterDataAvailable (inherited)	160
	AfterVisibilityChange (inherited)	160
		160
	BeforeVisibilityChange (inherited)	
	Formats	161
_	Series	162
•	rties	163
	tosort (inherited)	163
clo	seLine	163

color (inherited)	163
coloredLegend (inherited)	164
delayLoad (inherited)	164
drawPoints (inherited)	164
hint_string (inherited)	
legendlsVisible (inherited)	
lineOpacity (inherited)	
lineWidth (inherited)	
opacity (inherited)	
padding (inherited)	
pointBorderColor (inherited)	
pointBorderSize (inherited)	
pointColor (inherited)	
pointSize (inherited)	
title (inherited)	
visible (inherited)	
x_axis (inherited)	
x_axis_formatter (inherited)	
y_axis (inherited)	
y_axis_formatter (inherited)	
Methods	
findClosestByPixel (inherited)	
findClosestByPoint (inherited)	
getDataHandler (inherited)	
getPadding (inherited)	
getVisibility (inherited)	170
hide (inherited)	170
hideLegend (inherited)	170
reload (inherited)	170
setColor (inherited)	171
setColoredLegend (inherited)	171
setDataHandler (inherited)	171
setLineOpacity (inherited)	171
setLineWidth (inherited)	171
setOpacity (inherited)	172
setPadding (inherited)	
setTitle (inherited)	
show (inherited)	
showLegend (inherited)	
Events	
onAfterDataAvailable (inherited)	
onAfterVisibilityChange (inherited)	
onBeforeVisibilityChange (inherited)	
onShowHint (inherited)	
Data Formats	
Text Replacement Options	
EJSC.BarSeries	
Properties	
autosort (inherited)	
color (inherited)	
coloredLegend (inherited)	
defaultColors	
delayLoad (inherited)	
groupedBars	178

hint_string (inherited)	
intervalOffset	
legendlsVisible (inherited)	
lineOpacity (inherited)	
lineWidth (inherited)	
opacity (inherited)	
padding (inherited)	
orientation	
ranges	
title (inherited)	
treeLegend	
useColorArray	
visible (inherited)	
x_axis (inherited)	
x_axis_formatter (inherited)	
y_axis (inherited)	
y_axis_formatter (inherited)	
Methods	
addRange	
5	
clearRanges	
deleteRange	
findClosestByPixel (inherited)	
findClosestByPoint (inherited)	
getBarSize	
getBarSizeInPoints	
getDataHandler (inherited)	
getPadding (inherited)	
getPoints	
getVisibility (inherited)	
hide (inherited)	
hideLegend (inherited)	
reload (inherited)	
setColor (inherited)	
setColoredLegend (inherited)	
setDataHandler (inherited)	
setDefaultColors	
setGroupedBars	
setIntervalOffset	
setLineWidth (inherited)	
setOpacity (inherited)	
setPadding (inherited)	
setTitle (inherited)	
show (inherited)	
showLegend (inherited)	
Events	
onAfterDataAvailable (inherited)	
onAfterVisibilityChange (inherited)	
onBarNeedsColor	
onBeforeVisibilityChange (inherited)	
onShowHint (inherited)	
Data Formats	
Text Replacement Options	
SC.CandlestickSeries	
Properties	10

	autosort (inherited)	. 194
	color (inherited)	. 194
	coloredLegend (inherited)	
	delayLoad (inherited)	
	gain	
	hint_string (inherited)	
	intervalOffset	
	legendIsVisible (inherited)	
	lineOpacity (inherited)	
	lineWidth (inherited)	
	loss	
	opacity (inherited)	
	padding (inherited)	
	title (inherited)	
	visible (inherited)	
	x_axis (inherited)	
	x_axis_formatter (inherited)	
	y_axis (inherited)	
	y_axis_formatter (inherited)	. 199
	Methods	200
	findClosestByPixel (inherited)	. 200
	findClosestByPoint (inherited)	. 200
	getDataHandler (inherited)	. 200
	getPadding (inherited)	. 200
	getVisibility (inherited)	. 201
	hide (inherited)	. 201
	hideLegend (inherited)	. 201
	reload (inherited)	. 201
	setColor (inherited)	. 202
	setColoredLegend (inherited)	. 202
	setDataHandler (inherited)	. 202
	setLineOpacity (inherited)	
	setLineWidth (inherited)	202
	setOpacity (inherited)	
	setPadding (inherited)	
	setTitle (inherited)	
	show (inherited)	
	showLegend (inherited)	
	Events	204
	onAfterDataAvailable (inherited)	
	onAfterVisibilityChange (inherited)	
	onBeforeVisibilityChange (inherited)	
	onShowHint (inherited)	
	Data Formats	205
	Text Replacement Options	
E IS	·	206
EJS	C.DoughnutSeries	207
	Properties	208
	defaultColors (inherited)	
	delayLoad (inherited)	
	doughnutOffset	
	height (inherited)	
	hint_string (inherited)	
	legendlsVisible (inherited)	
	lineOpacity (inherited)	. 209

lineWidth (inherited)	209
opacity (inherited)	210
position (inherited)	210
title (inherited)	
total_value (inherited)	
treeLegend (inherited)	
visible (inherited)	
width (inherited)	
x_axis_formatter (inherited)	
Methods	
findCenter (inherited)	
findCenterOfCurve (inherited)	
getDataHandler (inherited)	
getPoints (inherited)	
getTotalValue (inherited)	
getVisibility (inherited)	
hide (inherited)	
hideLegend (inherited)	
reload (inherited)	
resetTotalValue (inherited)	
setDataHandler (inherited)	
setDefaultColors (inherited)	
setLineOpacity (inherited)	
setLineWidth (inherited)	
setOpacity (inherited)	
setTitle (inherited)	
setTotalValue (inherited)	
show (inherited)	
showLegend (inherited)	
Events	
onAfterDataAvailable (inherited)	
onAfterVisibilityChange (inherited)	
onBeforeVisibilityChange (inherited)	
onPieceNeedsColor (inherited)	
onShowHint (inherited)	
Data Formats	
Text Replacement Options	
EJSC.ErrorSeries	219
Properties	
avgSize	
autosort (inherited)	
capSize capDist	
color (inherited)	
coloredLegend (inherited)	
delayLoad (inherited)hint_string (inherited)	
legendlsVisible (inherited)	
lineOpacity (inherited)	
lineWidth (inherited)	
orientation	
opacity (inherited)	
padding (inherited)	
title (inherited)	224

	visible (inherited)	224
	x_axis (inherited)	224
	x_axis_formatter (inherited)	225
	y_axis (inherited)	225
	y_axis_formatter (inherited)	225
	Methods	225
•	findClosestByPixel (inherited)	225
	findClosestByPoint (inherited)	226
	getDataHandler (inherited)	226
	getPadding (inherited)getPadding (inherited)	226
	getVisibility (inherited)	227
	hide (inherited)	227
	hideLegend (inherited)	227
		227
	reload (inherited)	
	setColor (inherited)	227
	setColoredLegend (inherited)	228
	setDataHandler (inherited)	228
	setLineOpacity (inherited)	228
	setLineWidth (inherited)	228
	setOpacity (inherited)	228
	setPadding (inherited)	229
	setTitle (inherited)	229
	show (inherited)	229
	showLegend (inherited)	229
I	Events	230
	onAfterDataAvailable (inherited)	230
	onAfterVisibilityChange (inherited)	230
	onBeforeVisibilityChange (inherited)	230
	onShowHint (inherited)	230
EJSC	FloatingBarSeries	231
1	Properties	232
	autosort (inherited)	232
	color (inherited)	232
	coloredLegend (inherited)	232
	defaultColors (inherited)	232
	delayLoad (inherited)	233
	groupedBars (inherited)	233
	hint_string (inherited)	233
	intervalOffset (inherited)	234
	legendlsVisible (inherited)	234
	lineOpacity (inherited)	234
	lineWidth (inherited)	234
	opacity (inherited)	235
	orientation (inherited)	235
	padding (inherited)	235
	ranges (inherited)	236
	title (inherited)	236
	treeLegend (inherited)	237
	useColorArray (inherited)	237
	visible (inherited)	237
	Y AYIS (INDERITED)	ンスな
	x_axis (inherited)	238
	x_axis_formatter (inherited)	238
	·	

Methods	239
addRange (inherited)	239
clearRanges (inherited)	239
deleteRange (inherited)	239
findClosestByPixel (inherited)	239
findClosestByPoint (inherited)	240
getBarSize (inherited)	240
getBarSizeInPoints (inherited)	
getDataHandler (inherited)	
getPadding (inherited)	
getPoints (inherited)	
getVisibility (inherited)	
hide (inherited)	
hideLegend (inherited)	
reload (inherited)	
setColor (inherited)	
setColoredLegend (inherited)	
setDataHandler (inherited)	
setDefaultColors (inherited)	
setIntervalOffset (inherited)	
setLineWidth (inherited)	
setOpacity (inherited)	
setPadding (inherited)	
setTitle (inherited)	
show (inherited)	
showLegend (inherited)	
Events	
onAfterDataAvailable (inherited)	
onAfterVisibilityChange (inherited)	
onBarNeedsColor (inherited)	
onBeforeVisibilityChange (inherited)	
onShowHint (inherited)	
Data Formats	
Text Replacement Options	
ISC.FunctionSeries	
Properties	
•	
color (inherited)	
coloredLegend (inherited)	
hint_string (inherited)	
legendlsVisible (inherited)	
lineOpacity (inherited)	
lineWidth (inherited)	
padding (inherited)	
title (inherited)	
visible (inherited)	
x_axis (inherited)	
x_axis_formatter (inherited)	
y_axis (inherited)	
y_axis_formatter (inherited)	
Methods	
findClosestByPixel (inherited)	
findClosestByPoint (inherited)	
getPadding (inherited)	
getVisibility (inherited)	

hide (inherited)	254
hideLegend (inherited)	254
reload (inherited)	255
setColor (inherited)	255
setColoredLegend (inherited)	255
setLineWidth (inherited)	255
setPadding (inherited)	
setTitle (inherited)	
show (inherited)	
showLegend (inherited)	
Events	
onAfterVisibilityChange (inherited)	
onBeforeVisibilityChange (inherited)	
onShowHint (inherited)	
Text Replacement Options	
EJSC.LineSeries	
Properties	
autosort (inherited)	
color (inherited)	
coloredLegend (inherited)	
delayLoad (inherited)	
drawPoints	
hint_string (inherited)	
legendlsVisible (inherited)	
lineOpacity (inherited)	
lineWidth (inherited)	
padding (inherited)	
pointBorderColor	
pointBorderSize	
pointColor	
pointSize	
title (inherited)	
visible (inherited)	
x_axis (inherited)	
x_axis_(inherited)x	
y_axis (inherited)	
y_axis_formatter (inherited)	
Methods	
findClosestByPixel (inherited)	
findClosestByPoint (inherited)	
getDataHandler (inherited)	
getPadding (inherited)	
getVisibility (inherited)	
hide (inherited)	
hideLegend (inherited)	
reload (inherited)	
setColor (inherited)	
setColoredLegend (inherited)	
setDataHandler (inherited)	
setLineOpacity (inherited)	
setLineWidth (inherited)	
setPadding (inherited)	
setTitle (inherited)	
show (inherited)	267

showLegend (inherited)	
Events	
onAfterDataAvailable (inherited)	
onAfterVisibilityChange (inherited)	
onBeforeVisibilityChange (inherited)	
onShowHint (inherited)	
Text Replacement Options	
Data Formats	
SC.OpenHighLowCloseSeries	
Properties	
autosort (inherited)	
,	
color (inherited)	
coloredLegend (inherited)	
delayLoad (inherited)	
gain	
hint_string (inherited)	
intervalOffset	
legendIsVisible (inherited)	
lineOpacity (inherited)	
lineWidth (inherited)	
loss	
opacity (inherited)	
padding (inherited)	
title (inherited)	
visible (inherited)	
x_axis (inherited)	
x_axis_formatter (inherited)	
y_axis (inherited)	
y_axis_formatter (inherited)	
Methods	
findClosestByPixel (inherited)	
findClosestByPoint (inherited)	
getDataHandler (inherited)	
getPadding (inherited)	
getVisibility (inherited)	
hide (inherited)	
hideLegend (inherited)	
reload (inherited)	
setColor (inherited)	
setColoredLegend (inherited)	
setDataHandler (inherited)	
setLineOpacity (inherited)	
setLineWidth (inherited)	
setOpacity (inherited)	
setOpacity (inherited)setPadding (inherited)	
setTitle (inherited)	
•	
show (inherited)	
showLegend (inherited)	
Events	
onAfterDataAvailable (inherited)	
onAfterVisibilityChange (inherited)	
onBeforeVisibilityChange (inherited)	
onShowHint (inherited)	

Text Replacement Options	284
EJSC.OverUnderSeries	284
Properties	285
autosort (inherited)	285
color (inherited)	285
coloredLegend (inherited)	285
exceed	286
delayLoad (inherited)	286
hint_string (inherited)	286
legendlsVisible (inherited)	287
lineOpacity (inherited)	287
lineWidth (inherited)	287
opacity (inherited)	287
padding (inherited)	288
subsede	288
title (inherited)	289
visible (inherited)	289
x_axis (inherited)	289
x_axis_formatter (inherited)	289
y_axis (inherited)	289
y_axis_formatter (inherited)	290
Methods	290
findClosestByPixel (inherited)	290
findClosestByPoint (inherited)	290
getDataHandler (inherited)	291
getPadding (inherited)	291
getVisibility (inherited)	291
hide (inherited)	291
hideLegend (inherited)	292
reload (inherited)	292
setColor (inherited)	292
setColoredLegend (inherited)	292
setDataHandler (inherited)	
setLineOpacity (inherited)	
setLineWidth (inherited)	
setOpacity (inherited)	
setPadding (inherited)	
setTitle (inherited)	293
show (inherited)	
showLegend (inherited)	294
Events	
onAfterDataAvailable (inherited)	294
onAfterVisibilityChange (inherited)	294
onBeforeVisibilityChange (inherited)	
onShowHint (inherited)	295
EJSC.PieSeries	295
Properties	296
defaultColors	296
delayLoad (inherited)	296
height	
hint_string (inherited)	297
legendlsVisible (inherited)	
lineOpacity (inherited)	
lineWidth (inherited)	298

	opacity (inherited)	298
	position	298
	title (inherited)	298
	total_value	299
	treeLegend	299
	visible (inherited)	299
	width	299
	x_axis_formatter (inherited)	300
	Methods	300
	findCenter	300
	findCenterOfCurve	300
	getDataHandler (inherited)	300
	getPoints	301
	getTotalValue	301
	getVisibility (inherited)	301
	hide (inherited)	301
	hideLegend (inherited)	302
	reload (inherited)	302
	resetTotalValue	302
	setDataHandler (inherited)	302
	setDefaultColors	302
	setLineWidth (inherited)	303
	setOpacity (inherited)	303
	setTitle (inherited)	303
	setTotalValue	304
	show (inherited)	304
	showLegend (inherited)	304
	Events	304
	onAfterDataAvailable (inherited)	304
	onAfterVisibilityChange (inherited)	304
	onBeforeVisibilityChange (inherited)	305
	onPieceNeedsColor	305
	onShowHint (inherited)	305
	Data Formats	305
	Text Replacement Options	307
EJS	SC.ScatterSeries	307
	Properties	308
	autosort (inherited)	308
	color (inherited)	308
	coloredLegend (inherited)	309
	delayLoad (inherited)	309
	hint_string (inherited)	309
	legendIsVisible (inherited)	309
	lineOpacity (inherited)	310
	lineWidth (inherited)	310
	opacity (inherited)	310
	padding (inherited)	310
	pointSize	311
	pointStyle	311
	title (inherited)	311
	visible (inherited)	312
	x_axis (inherited)	312
	x_axis_formatter (inherited)	312
	y_axis (inherited)	312

y_axis_formatter (inherited)	
findClosestByPixel (inherited)	
findClosestByPoint (inherited)	
getDataHandler (inherited)	
getPadding (inherited)	
getVisibility (inherited)	
hide (inherited)	
hideLegend (inherited)	
reload (inherited)	
setColor (inherited)	
setColoredLegend (inherited)	
setDataHandler (inherited)	
setLineOpacity (inherited)	
setLineWidth (inherited)	
setOpacity (inherited)	
setPadding (inherited)	
setPointStyle	
setTitle (inherited)	
show (inherited)	
showLegend (inherited)	
Events	
onAfterDataAvailable (inherited)	
onAfterVisibilityChange (inherited)	
onBeforeVisibilityChange (inherited)	
onShowHint (inherited)	
Data Formats	
Text Replacement Options	
C.StepSeries	
Properties	
autosort (inherited)	
color (inherited)	
coloredLegend (inherited)	
drawPoints (inherited)	
hint_string (inherited)	
legendlsVisible (inherited)	
lineOpacity (inherited)	
lineWidth (inherited)	
padding (inherited)	
pointBorderColor (inherited)	
pointBorderSize (inherited)	
pointColor (inherited)	
pointSize (inherited)	
title (inherited)	
visible (inherited)	
v avia (inharitad)	
x_axis (inherited)	
x_axis_formatter (inherited)	
x_axis_formatter (inherited) y_axis (inherited)	
x_axis_formatter (inherited) y_axis (inherited) y_axis_formatter (inherited)	
x_axis_formatter (inherited) y_axis (inherited) y_axis_formatter (inherited) Methods	
x_axis_formatter (inherited) y_axis (inherited) y_axis_formatter (inherited) Methods findClosestByPoint (inherited)	
x_axis_formatter (inherited) y_axis (inherited) y_axis_formatter (inherited) Methods	

getVisibility (inherited)	327
hide (inherited)	327
hideLegend (inherited)	328
reload (inherited)	328
setColor (inherited)	328
setColoredLegend (inherited)	328
setDataHandler (inherited)	
setLineOpacity (inherited)	
setLineWidth (inherited)	
setPadding (inherited)	
setTitle (inherited)	
show (inherited)	
showLegend (inherited)	
Events	
onAfterDataAvailable (inherited)	
onAfterVisibilityChange (inherited)	
onBeforeVisibilityChange (inherited)	
onShowHint (inherited)	
Text Replacement Options	
Data Formats	
EJSC.StackedBarSeries	
Properties	
autosort (inherited)	
color (inherited)	
coloredLegend (inherited)	
defaultColors (inherited)	
delayLoad (inherited)	
groupedBars (inherited)	
hint_string (inherited)	
intervalOffset (inherited)	
legendlsVisible (inherited)	336
lineOpacity (inherited)	
lineWidth (inherited)	337
opacity (inherited)	
orientation (inherited)	337
padding (inherited)	337
ranges (inherited)	338
title (inherited)	339
treeLegend (inherited)	339
treeLegendRoot	339
useColorArray (inherited)	339
visible (inherited)	340
x_axis (inherited)	340
x_axis_formatter (inherited)	340
y_axis (inherited)	340
y_axis_formatter (inherited)	340
Methods	
addRange (inherited)	
addSeries	
clearRanges (inherited)	
deleteRange (inherited)	
findClosestByPixel (inherited)	
findClosestByPoint (inherited)	
getBarSize (inherited)	

getBarSizeInPoints (inherited)	
getDataHandler (inherited)	343
getPadding (inherited)	343
getPoints (inherited)	
getVisibility (inherited)	
hide (inherited)	
hideLegend (inherited)	344
reload (inherited)	344
removeSeries	
setColor (inherited)	
setColoredLegend (inherited)	
setDataHandler (inherited)	
setDefaultColors (inherited)	
setGroupedBars (inherited)	
setIntervalOffset (inherited)	
setLineOpacity (inherited)	
setLineWidth (inherited)	
setOpacity (inherited)	
setPadding (inherited)	
setTitle (inherited)	
show (inherited)	
showLegend (inherited)	
Events	
onAfterDataAvailable (inherited)	
onAfterVisibilityChange (inherited)	
onBarNeedsColor (inherited)	
onBeforeVisibilityChange (inherited)	
onShowHint (inherited)	
Text Replacement Options	
EJSC.TrendSeries	
Properties	
color (inherited)	
coloredLegend (inherited)	
hint_string (inherited)	
legendlsVisible (inherited)	
lineOpacity (inherited)	
lineWidth (inherited)	
padding (inherited)	
title (inherited)	
visible (inherited)	
x_axis (inherited)	
x_axis_formatter (inherited)	353
y_axis (inherited)	354
y_axis_formatter (inherited)	
Methods	
findClosestByPixel (inherited)	
findClosestByPoint (inherited)	
getPadding (inherited)	
getVisibility (inherited)	
hide (inherited)	355
hideLegend (inherited)	356
reload (inherited)	356
setColor (inherited)	356
setColoredLegend (inherited)	356

	setLineWidth (inherited)	356
	setPadding (inherited)	357
	setTitle (inherited)	357
	show (inherited)	357
	showLegend (inherited)	357
	Events	358
	onAfterVisibilityChange (inherited)	
	onBeforeVisibilityChange (inherited)	
	onShowHint (inherited)	
	Text Replacement Options	
5	Data Handlers	
9		
	EJSC.ArrayDataHandler	
	Methods	
	getArray	
	loadData (inherited)	
	setArray	359
	Events	
	onDataAvailable (inherited)	
	EJSC.CSVFileDataHandler	360
	Properties	360
	requestType (inherited)	360
	url (inherited)	360
	urlData (inherited)	361
	Methods	361
	getUrl (inherited)	361
	loadData (inherited)	361
	setRequestType (inherited)	362
	setUrl (inherited)	362
	setUrlData (inherited)	362
	setXMLData (inherited)	362
	Events	
	onDataAvailable (inherited)	363
	onDataReady (inherited)	
	onNeedsData (inherited)	
	EJSC.CSVStringDataHandler	
	Methods	
	getCSV	
	loadData (inherited)	
	setCSV	
	Events	
	onDataAvailable (inherited)	
	EJSC.JSONFileDataHandler	
	Properties	
	requestType (inherited)	
	url (inherited)	
	urlData (inherited)	
	Methods	
	getUrl (inherited)	
	loadData (inherited)	
	setRequestType (inherited)	
	setUrl (inherited)	
	setUrlData (inherited)	
	setXMLData (inherited)	
	Events	368

	onDataAvailable (inherited)	368
	onDataReady (inherited)	368
	onNeedsData (inherited)	
	EJSC.JSONStringDataHandler	
	Methods	
	getJSON	369
	loadData (inherited)	369
	setJSON	
	Events	
	onDataAvailable (inherited)	
	EJSC.XMLDataHandler	
	Properties	
	requestType (inherited)	
	url (inherited)	
	urlData (inherited)	
	Methods	
	getUrl (inherited)	
	loadData (inherited)	
	setRequestType (inherited)	
	setUrl (inherited)	
	setUrlData (inherited)	
	setXMLData (inherited)	
	Events	
	onDataAvailable (inherited)	
	onDataReady (inherited)	
	onNeedsData (inherited)	
	EJSC.XMLStringDataHandler	374
	Methods	374
	getXML	374
	loadData (inherited)	375
	setXML	375
	Events	375
	onDataAvailable (inherited)	375
6	Label Formatters	375
	EJSC.DateFormatter	
	Properties	
	format_string	
	timezoneOffset	
	useUTC	_
	Methods	
	format (inherited)	
	EJSC.NumberFormatter	
	Properties	
	currency_align	
	currency_position	378
	currency_symbol	378
	decimal_separator	
	forced_decimals	379
	negative_symbol	379
	thousand_separator	379
	variable_decimals	379
	Methods	379
	format (inherited)	
	EJSC.StringFormatter	

	Properties		380
	append		380
	prefix		380
	•		381
		ed)	381
	_		381
		at	381
7			381
•			
			381
	EJSC.AjaxDataHandle	r	382
	•		382
	requestType		382
	url		382
	urlData		382
	Methods		383
	getUrl		383
	loadData (inhe	rited)	383
	setRequestTy	oe	383
	setUrl		383
	setUrlData		384
	setXMLData		384
	Events		384
		ole (inherited)	384
			384
	•		385
			385
			385
	background		385
	border		386
	caption		386
	•		387
	color		387
	crosshair		387
		n	388
	cursor_position		
extremes_ticks			388
		oints	389
	formatter		389
	grid		390
	hint_caption		390
	label_class		390
	max_extreme		391
	major_ticks		391
	minor_ticks		392
	min_extreme		393
	size		393
	stagger_ticks		393
	visible		394
	zero_plane		394
	Methods		395
	addBin		395
	getExtremes		395
	getZoom		395
	getZoomBoxC	oordinates	396
	hide		396

hideGrid	
resetZoom	
pixelToPoint	
pointToPixel	
removeBin	
setCaption	398
setCrosshair	
setExtremes	
setZoom	
show	399
showGrid	
Events	
onHideCrosshair	
onHideCursorPosition	
onNeedsTicks	
onShowCrosshair	
onShowCursorPosition	
EJSC.DataHandler	
Methods	
loadData	
Events	
onDataAvailable	
EJSC.GaugeSeries	
Properties	
color (inherited)	
coloredLegend (inherited)	
delayLoad (inherited)	
legendIsVisible (inherited)	
lineOpacity (inherited)	
lineWidth (inherited)	
opacity (inherited)	
title (inherited)	
visible (inherited)	
,	
x_axis_formatter (inherited)	
Methods	
getDataHandler (inherited)	
getVisibility (inherited)	
hide (inherited)	
hideLegend (inherited)	
reload (inherited)	
setColor (inherited)	
setColoredLegend (inherited)	
setDataHandler (inherited)	
setLineOpacity (inherited)	
setLineWidth (inherited)	
setOpacity (inherited)	
setTitle (inherited)	
show (inherited)	
showLegend (inherited)	
Events	
onAfterDataAvailable (inherited)	
onAfterVisibilityChange (inherited)	
onBeforeVisibilityChange (inherited)	
EJSC.Formatter	408

Properties		••••
format_string		
Methods		
format		
EJSC.Point		
label		
userdata		
X		
у		
autosort		
color		
	1	
delayLoad		
hint_string		
=	e	••••
lineOpacity		
lineWidth		••••
opacity		
• •		
padding title		•••••
visible		••••
x_axis		
	ter	
y_axis		
·	ter	••••
		••••
•	Pixel	••••
•	Point	
· ·	er	
getPadding		
getVisibility		
hide		
hideLegend		
reload		
setColor		
setColoredLeg	gend	
setDataHandle	er	
setLineOpacity	у	
setLineWidth		
setOpacity		
setPadding		
setTitle		
show		
showLegend		
Events		
onAfterDataAv	/ailable	
	yChange	
	ilityChange	
OLIDAIDIA AISIDI	,	

	Index	0
Part V	Getting Support	428
12	Using Colors	428
11	Text Replacement Options	
10	META Tag Configuration	
_	Exporting To SVG	
9	y (inherited)	426
	x (inherited)	
	userdata (inherited)	
	label (inherited)	425
	Properties	425
	EJSC.XYPoint	425
	x (inherited)	
	userdata (inherited)	
	open	
	label (inherited)low	40
	high	
	close	
	Properties	
	EJSC.StockPoint	
	x (inherited)	423
	userdata (inherited)	423
	label (inherited)	
	Properties	
	x (inherited) EJSC.PiePoint	
	userdata (inherited)	
	label (inherited)	
	Properties	
	EJSC.GaugePoint	
	y (inherited)	421
	x (inherited)	
	userdata (inherited)	
	min	40.
	label (inherited) max	
	Properties	
	EJSC.FloatingBarPoint	
	y (inherited)	
	x (inherited)	
	userdata (inherited)	420
	label (inherited)	419
	Properties	419

1 Getting Started

Welcome to Emprise JavaScript Charts. Constructed entirely in JavaScript the days of annoying plugin downloads and browser security warnings are gone. With genuine ease of use and complete customization Emprise JavaScript Charts provides you with the tools you need to publish your data quickly and in a variety of formats. With its wide range of interactive features, simple and straightforward implementation, and unparalleled functionality, Emprise JavaScript Charts is the clear first choice for all your charting needs.

Here's a quick sampling of just some of the features included:

• Interactive:

Features such as Hints, Mouse Tracking, Mouse Events, Key Tracking and Events, Zooming, Scrolling, and Crosshairs raise interactivity and user experience in web charting to a new level.

• Axis Scaling:

There's no need to determine your data range before hand. EJSChart will calculate and scale automatically to fit whatever data it is presented with.

• Auto Zooming, Scrolling:

Too much data and not enough screen real estate? Show it all. Let your end users zoom in on the pieces they're most interested in. Axis locking for single axis zoom, scrolling and automatic axis scaling are all included.

• Stackable Series:

Multiple chart series can be stacked and combined to fit many charting needs.

Multiple Series Types:

Line, Area, Scatter, Pie, Bar and Function series are just the beginning. New series are just a few lines of JavaScript code away.

• Ajax-Driven Data:

EJSChart supports XML-formatted data and loads data on the fly. New series can be added and data updated in real time without page reloads.

• Compatible:

Built with compatibility in mind and tested on all major browsers, you can be assured your charts will function consistently for the broadest range of end users. See the full list of compatible browsers on our System Requirements page.

• Plugin Free:

100% Pure JavaScript Charting Solution. No more worries of incompatible plugin versions or confusing security warnings. EJSChart is pure JavaScript and requires no client installation.

Customizable:

Every aspect of the charting display can be configured and customized through well-documented properties and methods. Want to do more than just change the color of the background? Need a series type which doesn't already exist? EJSChart is fully customizable and extendable to provide the greatest flexibility and integration for existing site designs and needs.

1.1 Overview

Welcome to Emprise JavaScript Charts. Constructed entirely in JavaScript the days of annoying plugin downloads and browser security warnings are gone. With genuine ease of use and complete customization Emprise JavaScript Charts provides you with the tools you need to publish your data quickly and in a variety of formats. With its wide range of interactive features, simple and straightforward implementation, and unparalleled functionality, Emprise JavaScript Charts is the clear first choice for all your charting needs.

Here's a quick sampling of just some of the features included:

- Interactive: Features such as Hints, Mouse Tracking, Mouse Events, Key Tracking and Events, Zooming, Scrolling, and Crosshairs raise interactivity and user experience in web charting to a new level.
- Axis Scaling: There's no need to determine your data range before hand. EJSChart will calculate and scale automatically to fit whatever data it is presented with.
- Auto Zooming, Scrolling: Too much data and not enough screen real estate? Show it all. Let your end users zoom in on the pieces they're most interested in. Axis locking for single axis zoom, scrolling and automatic axis scaling are all included.
- **Stackable Series:** Multiple chart series can be stacked and combined to fit many charting needs.
- **Multiple Series Types:** Line, Area, Scatter, Pie, Bar and Function series are just the beginning. New series are just a few lines of JavaScript code away.
- Ajax-Driven Data: EJSChart supports XML-formatted data and loads data on the fly.

 New series can be added and data updated in real time without page reloads.
- Compatible: Built with compatibility in mind and tested on all major browsers, you can be assured your charts will function consistently for the broadest range of end users. See the full list of compatible browsers on our System Requirements page.
- Plugin Free: 100% Pure JavaScript Charting Solution. No more worries of incompatible plugin versions or confusing security warnings. EJSChart is pure JavaScript and requires no client installation.
- **Customizable:** Every aspect of the charting display can be configured and customized through well-documented properties and methods. Want to do more than just change the

color of the background? Need a series type which doesn't already exist? EJSChart is fully customizable and extendable to provide the greatest flexibility and integration for existing site designs and needs.

1.2 Implementation Instructions

Ease of implementation was an important factor considered in the development of EJSChart. The process from purchase to user "wow" takes just a matter of minutes and can be completed following the few easy to follow steps detailed below. Designed for all users, no previous JavaScript knowledge is required to implement EJSChart or take advantage of its many features. The steps below will guide you through the installation and testing of the EJSChart library.

- 1. Create a new directory in the home directory of your webpage and name it EJSChart.
- Copy the contents (all files and directories) of the /dist/ folder provided in your EJSChart download package into your newly created EJSChart folder on your web server.
- 3. Open the webpage that you wish to place an example chart on. If you do not currently have one or wish to use a test page for this purpose one has been provided for you in the How To directory included with your download. This file is named mydemochart.html and can be edited in your preferred html editor or even notepad.
- 4. Copy <script type="text/javascript" src="/EJSChart/EJSChart.js"></script> into the head section of your webpage. *This path can be modified as necessary to correctly point to EJSChart.js.

5. Create a div on your page where you would like the chart to be displayed. The size of the chart can be specified within the div properties if desired. The div is created by

pasting <div id="myChart" style="width:450px; height:330px;"></div> where desired in the body of your webpage. The style width and height properties can be adjusted as desired.

```
<!doctype html public "-//W3C//DTD HTML 4.0</pre>
Transitional//EN">
<html>
  <head>
    <title>My Demo Chart</title>
    <meta name="Author" content="Emprise Corporation">
    <meta name="Description" content="EJSChart Demo</pre>
Chart HTML Page">
   <script type="text/javascript"</pre>
src="/EJSChart/EJSChart.js"> </script>
  </head>
  <body>
           This is a sample page that is used to
copy and paste a demo chart into.
    <div id="myChart" style="width:450px;</pre>
height:330px;"></div>
  </body>
</html>
```

6. To turn the div into a chart paste the following sample code at the end of your webpage.

```
<script type="text/javascript">
         var chart = new EJSC.Chart("myChart");
               chart.addSeries(new EJSC.AreaSeries(
                 new EJSC.ArrayDataHandler([[1,1],[2,2],[3,3],[4,2],[5,3]]))
               );
       </script>
<!doctype html public "-//W3C//DTD HTML 4.0</pre>
Transitional//EN">
<html>
  <head>
    <title>My Demo Chart</title>
    <meta name="Author" content="Emprise Corporation">
    <meta name="Description" content="EJSChart Demo</pre>
Chart HTML Page">
   <script type="text/javascript"</pre>
src="/EJSChart/EJSChart.js"> </script>
  </head>
  <body>
          This is a sample page that is used to
copy and paste a demo chart into.
    <div id="myChart" style="width:450px;</pre>
height:330px;"></div>
    <script type="text/javascript">
     var chart = new EJSC.Chart("myChart");
         chart.addSeries(new EJSC.AreaSeries(
           new
EJSC.ArrayDataHandler([[1,1],[2,2],[3,3],[4,2],[5,3]]))
    </script>
  </body>
</html>
```

7. Upload your edited webpage to your web server. Visit your webpage and view the demo chart located on the page where the div was placed.

1.3 Creating Your First Chart

Now that you have created and tested your first demonstration chart on your web server it is time to create your own chart. This demonstration will guide you through creating your first chart and introduce you to some of the many available features and methods of customization available to you in Emprise JavaScript Charts. If you have not yet completed the Implementation Instructions it is recommended that you do so before continuing with this section as they guide you through uploading the necessary files to your web server.

- Open the webpage that you wish to place your first custom chart on. If you do
 not currently have one or wish to use a test page for this purpose one has been
 provided for you in the How To directory included with your download. This file is
 named myfirstchart.html and can be edited in your preferred html editor or even
 notepad.
- 2. Copy <script type="text/javascript" src="/EJSChart/EJSChart.js"></script> into the head section of your webpage. *This path can be modified as necessary to correctly point to EJSChart.js.

3. Create a div on your page where you would like the chart to be displayed by pasting <div id="myFirstChart" style="width:600px; height:400px;"></div> where desired in the body of your webpage.

```
<!doctype html public "-//W3C//DTD HTML 4.0
Transitional//EN">
<html>
    <head>
        <title>My Demo Chart</title>
        <meta name="Author" content="Emprise Corporation">
        <meta name="Description" content="Emprise
JavaScript Charts :: Customization Example">
        <script type="text/javascript"
src="/EJSChart/EJSChart.js"> </script></script>
```

4. The next step is to create the chart object. This is done at the end of your html file, directly before the closing body tag; </body>. To begin define the text as JavaScript with <script type="text/javascript"> and create a chart object on the next line using var chart = new EJSC.Chart("myFirstChart"); Be sure that the div id as identified within the body of your webpage matches the title you place within the parenthesis when creating your chart. In this example it is 'myFirstChart'. Failure to create the appropriate div's for the chart to be placed in will result in errors and prevent your chart from being displayed.

The properties of your chart including its visual appearance and interactivity are highly customizable by adjusting its properties. Instructions on how to accomplish this can be found on the Customizing Your Chart page of this guide.

In this example code the chart has been customized to remove the legend and set a custom title by adding:

```
<script type="text/javascript">
         var chart = new EJSC.Chart(
            "myFirstChart",
              show_legend: false,
              title: "My First Custom Chart"
          );
<!doctype html public "-//W3C//DTD HTML 4.0
Transitional//EN">
<html>
  <head>
    <title>My Demo Chart</title>
    <meta name="Author" content="Emprise Corporation">
   <meta name="Description" content="Emprise</pre>
JavaScript Charts :: Customization Example">
    <script type="text/javascript"</pre>
src="/EJSChart/EJSChart.js"> </script>
  </head>
          This is a sample page that is used to
  <body>
       copy and paste a demo chart into.
    <div id="myFirstChart" style="width:600px;</pre>
       height:400px;"></div>
   <script type="text/javascript">
```

```
var chart = new EJSC.Chart(
    "myFirstChart",
    {
        show_legend: false,
        title: "My First Custom Chart"
     }
    );
    </body>
</html>
```

5. Now that the chart has been created the series must be created. The series defines how your data will be displayed in the chart you are creating. The types of series that are available may vary by license; more details on this can be found on the LICENSE.txt file.

When creating the chart you can also choose which format you will be providing the data in. This is accomplished with the use of different Data Handlers. The formats currently supported by EJSChart are XML file, JavaScript Array, CSV file, and CSV string data. Details on the implementation of each of these data handlers as well as sample code can be found on their respective pages in the Developer Guide help file.

The properties of your series, including its visual appearance and interactivity, are customized by adjusting its properties. Instructions on how to accomplish this can be found on the Customizing Your Chart page.

In this example code a bar chart was created using the Bar Series, the color was set to green, and the bar border width was set to five pixels. The data to be graphed was specified using the EJSC.ArrayDataHandler. To accomplish this the following code was added:

```
Transitional//EN">
<html>
  <head>
    <title>My Demo Chart</title>
    <meta name="Author" content="Emprise Corporation">
    <meta name="Description" content="Emprise</pre>
JavaScript Charts :: Customization Example">
    <script type="text/javascript"</pre>
src="/EJSChart/EJSChart.js"> </script>
  </head>
  <body>
           This is a sample page that is used to
       copy and paste a demo chart into.
    <div id="myFirstChart" style="width:600px;</pre>
       height:400px;"></div>
   <script type="text/javascript">
      var chart = new EJSC.Chart(
        "myFirstChart",
          show_legend: false,
          title: "My First Custom Chart"
      );
      var myChartSeries = new EJSC.BarSeries(
            new EJSC.ArrayDataHandler(
              [
                 ["Month 1",1],
["Month 2",2],
                 ["Month 3",3],
                 ["Month 4",4],
                ["Month 5",5]
              ]
          );
        myChartSeries.color = 'rgb(50,210,50)';
        myChartSeries.lineWidth = 5;
  </body>
</html>
```

 Once created the series must then be added to the chart using the addSeries method in the chart class.

```
<!doctype html public "-//W3C//DTD HTML 4.0
Transitional//EN">
<html>
  <head>
    <title>My Demo Chart</title>
    <meta name="Author" content="Emprise Corporation">
    <meta name="Description" content="Emprise</pre>
JavaScript Charts :: Customization Example">
   <script type="text/javascript"</pre>
src="/EJSChart/EJSChart.js"> </script>
  </head>
           This is a sample page that is used to
       copy and paste a demo chart into.
    <div id="myFirstChart" style="width:600px;</pre>
       height:400px;"></div>
   <script type="text/javascript">
      var chart = new EJSC.Chart(
        "myFirstChart",
          show_legend: false,
          title: "My First Custom Chart"
      );
```

7. Close the JavaScript by inserting </script> at the end.

```
<!doctype html public "-//W3C//DTD HTML 4.0
Transitional//EN">
<html>
  <head>
    <title>My Demo Chart</title>
    <meta name="Author" content="Emprise Corporation">
    <meta name="Description" content="Emprise</pre>
JavaScript Charts :: Customization Example">
    <script type="text/javascript"</pre>
src="/EJSChart/EJSChart.js"> </script>
  </head>
  <body>
          This is a sample page that is used to
       copy and paste a demo chart into.
    <div id="myFirstChart" style="width:600px;</pre>
       height:400px;"></div>
   <script type="text/javascript">
      var chart = new EJSC.Chart(
        "myFirstChart",
          show_legend: false,
          title: "My First Custom Chart"
      );
      var myChartSeries = new EJSC.BarSeries(
            new EJSC.ArrayDataHandler(
                ["Month 1",1],
                ["Month 2",2],
                ["Month 3",3],
                ["Month 4",4],
                ["Month 5",5]
              ]
          );
        myChartSeries.color = 'rgb(50,210,50)';
        myChartSeries.lineWidth = 5;
      chart.addSeries(myChartSeries);
    </script>
  </body>
</html>
```

8. That's it! Upload the webpage to your web server and you're done.

1.4 Customizing Your Chart

With Emprise JavaScript Charts, the customization options of your chart are endless. This includes visual appearance, which can be modified to integrate fully with any theme or design, as well as chart interactivity, which can range from including user capabilities such as auto zooming and custom hint captions to hidden-axis view only chart displays. Your chart can be customized on the chart and series level via the modification of the chart and series properties.

The first customization options available to you are at the chart level. They can be specified when creating the chart or alternatively after the chart object has been established. The properties available for editing and their syntax can be found in the Chart Properties section of the help documentation. In addition, examples of their implementation with sample code and the resulting effect on chart display or interactivity are available on the in the /examples/ directory of the distribution package. There are also additional examples available online at http://www.ejschart.com/examples/

The following are a few quick examples of modifying commonly used properties both at and after chart creation:

• Modification of the bottom x and left y axis labels during chart creation:

• Modification of the bottom x and left y axis labels after chart creation:

```
var chart = new EJSC.Chart("myChart");
    chart.axis_bottom.setCaption("Month");
    chart.axis_left.setCaption("Temperature");
```

The properties of each series on a chart may also be customized. This is accomplished with the editing of properties in the same way as was done to customize chart properties; either at the time of series creation or following creation. The properties available for editing and their syntax can be found on the Properties page of each of the different series help sections. In addition, examples of their implementation with sample code and the resulting effect on chart display or interactivity are available on the in the /examples/ directory of the distribution package. There are also additional examples available online at http://www.ejschart.com/examples/

The following are a few quick examples of modifying commonly used properties both at and after chart creation:

• Modification of the series lineWidth property during creation:

```
var myChartSeries = new EJSC.FunctionSeries(Math.sin, {lineWidth:
4});
```

• Modification of the lineWidth property after creation:


```
var myChartSeries = new EJSC.FunctionSeries(Math.sin);
myChartSeries.setLineWidth(4);
```

1.5 Anatomy of a Chat


In order to fully understand the power of the properties available for customizing charts is important to become familiar with the various components of the chart.

The following diagram identify many of these components:


1.5.1 Y Axis




1.5.2 X Axis




1.5.3 Hint



1.5.4 Chart Body



1.5.5 Legend



1.6 Version 1.x Compatability

We have moved a significant number of properties and methods into separate classes to support multiple axes and new series types. You may find that properties used in charts you have already developed no longer have the effect expected on your charts. To help with the transition to the new code base we have included a version 1 compatibility JavaScript file.

To have this code included automatically into your page, simply put the following tag in the page header BEFORE you include EJSChart.js:

This utility script will automatically convert the deprecated properties to their version 2 counterparts.

In addition, if you are using a browser, browser extension, or other JavaScript package which implements window.console, the script will log the deprecated properties being converted in order to aide you in upgrading your code.

Additional META tag options are described here.

1.6.1 Deprecated Properties, Methods and Events

The following lists all properties, methods and events which have been deprecated in version 2.0 and are no longer available unless the v1 Compatibility Script is included.

Properties

force_static_points force_static_points_x force_static_points_y legendTitle show_crosshairs show grid show_mouse_position show_x_axis show_y_axis x_axis_caption x_axis_className x_axis_extremes_ticks x_axis_formatter x_axis_max_tick_interval x_axis_min_tick_interval x_axis_minor_ticks x_axis_size x_axis_stagger_ticks x_axis_tick_className x_axis_tick_count x_cursor_position_caption x_cursor_position_formatter x max x min x_value_hint_caption x_zero_plane y_axis_caption y_axis_className y_axis_extremes_ticks y_axis_formatter y_axis_max_tick_interval y_axis_min_tick_interval y_axis_minor_ticks y_axis_size y_axis_tick_className y_axis_tick_count y_cursor_position_caption y_cursor_position_formatter y_max y_min y_value_hint_caption y_zero_plane

Methods

addXAxisBin addYAxisBin convertPixelToPoint convertPointToPixel findClosestPointInSeries hideGrid hideXAxis hideYAxis getXExtremes getYExtremes getZoom removeXAxisBin removeYAxisBin selectClosestPoint setCrosshairs setXAxisCaption setXExtremes setYAxisCaption setYExtremes setZoom showGrid showXAxis showYAxis

Events

onAfterShowCrosshairs onBeforeBeginZoom onBeforeEndZoom onShowCrosshairs onXAxisNeedsTicks onYAxisNeedsTicks

1.7 Deployment

The Emprise JavaScript Charts distribution package includes a compressed and obfuscated version of the source code for easy deployment. The entire /dist/ directory is meant to be placed on a web site, as is, with no modification necessary.

If you have access to the source code (Developer and Enterprise editions) and have made modifications, there is a utility web page located in the /packer/ directory which hosts a compression script powered by Dean Edward's Packer (original source: http://dean.edwards.name/packer/)

This utility must be used to compress and obfuscate the JavaScript source code before making it live or distributing it within your own application.

2 Changes

2.1 Changes in version 2.3

Version 2.3

New Features

- Added pointStyle property to LineSeries and AreaSeries
- Added even shading and odd shading properties to LinearAxis
- Added onUserEndZoom event to Chart
- Vertical Axis Captions (check cross-browser)
- Added legend_position, legend_height, and legend_width to Chart
- Added setAxis method to Chart
- New Series: ErrorSeries
- New Series: AlarmSeries
- New Series: OverUnderSeries
- New Series: StepSeries
- New Series: DoughnutSeries (DonutSeries)

New Axis: DateAxis

Bug Fixes

Fixed issues with displaying charts in IE9

2.2 Changes in version 2.1

Version 2.1

New Features

- Added treeLegendRoot property to StackedBarSeries
- Added left and right as valid property values for PieSeries.position and AnalogGaugeSeries.position
- Added defaultColors, useColorArray and onBarNeedsColor to StackedBarSeries
- Added the ability for StackedBarSeries to share a single color array among all owned series
- Added support for IE8 RC1 (and most previous betas) in all modes
- Added chart.setShowLegend method
- Performance increases in IE when drawing multiple series and/or series with large numbers of points
- Added support for gaps in LineSeries (use a blank string as Y)
- Added getBarSizeInPoints to BarSeries and descendant classes

Bug Fixes

- Corrected several IE related memory leaks
- Corrected memory leaks related to Ajax requests (affected all browsers)
- Corrected memory leaks when removing charts from a page repeatedly without refreshing
- Corrected parameter name for CSVStringDataHandler.setCSV
- Fixed AreaSeries draw when series contains more than 5000 points in IE
- Fixed incorrect parsing of numeric Y values in Stock Series
- Updated chart.onBeforeSelectPoint, onAfterSelectPoint, onShowHint to send the correct value for the HoverOrSelect parameter
- Corrected error when trying to get/set axis captions
- Corrected issues with certain data handlers corrupting data when Object.prototype has been modified
- Fixed issues with legend movement when the chart was inside a scrollable container
- Corrected Axis.pointToPixel so that it returns the proper value when given a string (bin)
- Corrected double loading of data when using JSONStringDataHandler
- Removed the ability for closeLine to affect drawing in LineSeries
- Corrected issues with AreaSeries drawing when closeLine was false in Safari
- Corrected AreaSeries drawing in IE when more than 5000 points exist
- Corrected issues with extremes calculations in StackedBarSeries

2.3 Changes in version 2.0.1

Version 2.0.1

New Features

- Added Series.getPadding, Series.setPadding methods
- Added Series.padding property
- Added Chart.legend_state (normal, minimized)
- Added Chart.legendMinimize, Chart.legendRestore, Chart.getLegendState methods
- Added ignoreBounds parameter to Axis.pointToPixel

Bug Fixes

- BarSeries / FloatingBarSeries Fixed dimension calculation which caused bars to be missed if the mouse was close to an axis
- BarSeries / FloatingBarSeries Updated point location / distance to return exact matches when the mouse is within a bar
- Fixed issue with chart files when in a directory named ejschart_
- Corrected issue with axis.force static points and cursor position
- Corrected issue with legend icons causing non-secure warning in https session
- Added catch to all try/finally statements to account for IE bug
- Corrected adjustment to so that crosshairs position exactly under the cursor
- Renamed variable int to interval to correct Safari 2 parse issue
- Updated default series padding to account for axis assignment
- Corrected issue with horizontal bars not drawing when rendered 1 pixel wide

Documentation Updates

- Added documentation for META tag options
- Added documentation for Series.findClosestByPoint and Series.findClosestByPixel

2.4 Changes in version 2.0

Additions

- Multiple X and Y Axes
- Logarithmic Axis
- JSON String and File Data Handlers
- Stacked Bar Series
- Floating Bar Series
- String Formatter for prefixing and appending to labels
- OpenHighLowClose Series
- Candlestick Series
- Filled Scatter Series Points in IE
- Much optimized rendering of axis labels and ticks
- Cleaner and smaller HTML generation of chart objects
- Faster chart rendering and much better support for many charts in a single page
- Removed the need for EJSChartIE.css and EJSChartIE6.css
- Better control over styling of major tick marks
- More styling options for grid lines and axis borders
- Easier customization of cursor position elements
- · Background coloring with opacity of the chart area and axes

2.5 Changes in version 1.3.1

Additions

- Added Chart.y_axis_min_tick_interval, y_axis_max_tick_interval, x_axis_min_tick_interval and x_axis_max_tick_interval for finer tick control
- Added tick enhancements when using date values so that the tick interval cannot be less than one millisecond
- Added support for point specific labels in Line/Area/Scatter/Bar series

Bug Fixes

- Fixes issues with onXAxisNeedsTicks and onYAxisNeedsTicks not positioning correctly
- Added check to ensure the selected point is valid before firing onDblClickPoint event
- Updated CSV data handlers to account for pie/gauge series and correctly map labels
- Fixed issues with text bins for Y when using XML data handlers
- Updated array data handler to account for pie/gauge series and correctly map labels
- Fixed issue with gauge border default value
- Fixed issues with gauge drawing when added to a chart but not immediately drawn

2.6 Changes in version 1.3

Additions

- Added AreaSeries.closeLine property which determines if the line should return to the zero plane and draw as a closed shape.
- Added PieSeries.findCenterOfCurve(point) method
- Added support for SVG exporting

Modifications

- Modified axis to write out ticks and labels less often
- Line and scatter series are now split into smaller draws in order to support larger data sets in IE
- BarSeries point selection now accounts for proximity snap setting and the bar's line width
- Added support for text labels (bins) to TrendSeries

Bug Fixes

- Updated color conversion routine to fix issues in IE
- Added additional logic to ajax data handlers to prevent double loading
- Corrected resize issue in IE which could cause an 'Invalid Argument' error
- Updated extremes calculations to correct issues with negative numbers
- getYExtremes() now correctly returns the y axis extremes
- Added additional offset checks in point location routines to account for quirks mode in various browsers
- Fixed issues with xml data handler and processing string values
- PieSeries data points now correctly save and display their labels if defined
- Corrected drawing issues in BarSeries with negative numbers
- Fixed BarSeries drawing in IE with a large number of points

- Corrected BarSeries draw in IE to close the bar line
- Updated PieSeries to reset its available colors correctly when reloading

2.7 Changes in version 1.2.1

Additions

Added selectPoint and clearSelectedPoint methods to the chart.

Modifications

- Enhanced support for chart with large numbers of series.
- Enabled initial implementation of Series.delayLoad (default true) which controls when a series triggers its data handler to begin data retrieval
- Updated PiePoint and PieSeries to correctly render float values for pie pieces
- Updated PieSeries to handle more 100% piece drawing cases

Bug Fixes

- Fixed issues with series reloading where auto calculated extremes were not reset with new data (affected all series)
- Fixed print rendering issues in all browsers except Opera. The chart now renders as show on screen when printing.
- Fixed XYPoint class to properly recognize the Y value as a number as opposed to a string.
- Fixed inheritance issue with ArrayDataHandler
- Fixed issues with clearing the chart when all loaded series are set invisible
- Fixed PieSeries reload method to reset available colors
- Fixed BarSeries treeLegend property to function properly when useColorArray is false
- Fixed BarSeries reload method to reset available colors
- Fixed range drawing in AnalogGaugeSeries to correctly connect arcs before filling
- Fixed issue with x axis labels not aligning correctly when allow interactivity was false

2.8 Changes in version 1.2

Additions

- Added classes to better control and track axis bins (text labels)
- Added support for y axis bins
- Added support for shared bins between series (unused bins)
- Added coordinate property to Chart.y_zero_plane and Chart.x_zero_plane to allow zero plane to fall somewhere other than 0
- Added Chart.force_static_points_x and Chart.force_static_points_y (force_static_points works as before, for x only) to force bins when data is numeric
- Implemented Chart.y_axis_extremes_ticks
- Added support for drawing minor tick marks on the Y axis and Y axis
- Added Chart.onXAxisNeedsTicks and onYAxisNeedsTicks to allow for custom tick configurations
- Added support for auto sort in all applicable series / data handlers. This is now set by default and may be turned off if data is correctly sorted prior to being handed to the data handler.
- Added support for color specifications as rgb(0,0,0), rgba(0,0,0,100) and hex (#000000) everywhere colors may be specified
- Added support for mouse wheel to zoom (controlled by allow_interactivity, allow_zoom, allow_mouse_wheel_zoom)

- Added Chart.addYAxisBin, Chart.addXAxisBin, Chart.removeYAxisBin, Chart.removeXAxisBin methods to support manual definition (and order) of axis bins
- Added EJSC.XMLStringDataHandler class
- Added drawPoints, pointSize, pointColor, pointBorderSize, pointBorderColor properties to EJSC.LineSeries and EJSC.AreaSeries
- Added support for new zero plane coordinate property to AreaSeries and BarSeries
- Added tree-style legend for PieSeries
- Added tree-style legend option for BarSeries (default true when useColorArray is true and treeLegend is left undefined)
- Added position and height/width properties to PieSeries to support multiple pie series per chart
- Added findCenter method to PieSeries to find the center point of a given piece
- Added getPoints method to PieSeries (to allow findCenter calls to provide a valid piece object)
- Added orientation property to BarSeries and support for horizontal bar charts
- Added total_value property and getTotalValue, setTotalValue, resetTotalValue methods to PieSeries
- Added [total] and [percent] as hint text replacement options for PieSeries
- Added x_cursor_position_formatter and y_cursor_position_formatter properties to chart to allow for a different formatter for mouse position display

Modifications

- Consolidated and cleaned up xml parsing routines
- Consolidated and cleaned up csv parsing routines
- Cached many often used math methods for performance
- Modified extremes to account for manually added bins with no associated data in series
- Rewrote data handlers to better support text labels (bins)
- Modified pie series to correctly use lineOpacity
- Updated pie piece drawing to one path creation per piece
- Added check in AnalogGaugeSeries to avoid resetting innerHTML unless the label has actually changed.
- Added check of show_hints before triggering onShowHint event

Bug Fixes

- Added media attribute to link tag to fix printing issues in firefox/netscape
- Added correct headers when sending an xml request as POST
- Fixed case when last tick is missing while using x axis tick count
- Fixed spelling getZoomBoxCoordinates
- Updated lineOpacity to 100 (from 1) in PieSeries so lines draw correctly
- Added check for single 100% piece to remove line when drawn (fixed full circle drawing)
- Reversed intercept/ slope properties in TrendSeries so they represent the correct values
- Updated number formatter to check for -0 as final output and remove sign
- onDblClickPoint and onAfterSelectPoint both now function correctly when show_hints is false
- Fixed unterminated string error in TrendSeries
- Updated style to remove border when axes are not visible (ie, pie or gauge only charts)
- Fixed constant resize issue with pie charts (and anything with x axis hidden) in IE6/opera
- Fixed issue with series drawing multiple times when added and redraw is false

2.9 Changes in version 1.1

Additions

- Added new series type AnalogGaugeSeries
- Added onBeforeBeginZoom, onBeforeEndZoom and onAfterShowCrosshairs events to Chart
- Added support for local loading of chart code in IE 7 and IE6 with certain versions of the XMLHttpRequest ActiveX control.
- Added new axis styling properties to Chart: x_axis_size, x_axis_className, x_axis_tick_className, x_axis_stagger_ticks, x_axis_tick_count, y_axis_size, y_axis_className, y_axis_tick_className, y_axis_tick_count.
- Added Chart.setZoom and getZoom methods to in order to get the current zoom and set zoom to a particular range
- Added Chart.getMinMaxYInXRange method to programatically find the min and max Y values in a given X range
- Added Chart.findClosestPointInSeries method to programatically find the closest point to the coordinates (x,y) in a particular series
- Added Chart.getZoomBoxCoordinates method to get the current zoom box coordinates
- Added Chart.displayZoomBox method to programatically display the zoom box
- Added BarPoint class to support additional BarSeries functionality
- Added the ability to draw bars with different colors based on ranges
- Added the ability to adjust the spacing between bars using the new intervalOffset property.
- Added the ability to switch between grouped and overlayed bars with BarSeries
- Added a color pool to BarSeries for individually colored bars (similar to PieSeries)
- Added onBarNeedsColor to BarSeries for more advanced bar coloring options
- Added setDefaultColors, addRange, deleteRange, clearRanges, setIntervalOffset and setGroupedBars methods to BarSeries
- Added support for 'exponential' and 'logarithmic' types in TrendSeries
- Added showGrid/hideGrid methods with an optional redraw parameter to prevent immediate redrawing
- Optimized trend series calculation routines
- Blank X or Y axis captions now trigger the axis to be resized giving the chart additional space
- Added the ability to specify only changed members of child objects via the options property
- Added Chart.convertPointToPixel method to calculate document pixel top/left of a point in chart units
- Added Chart.convertPixelToPoint method to calculate chart point from a document pixels
- Added base AjaxDataHandler class, XMLDataHandler and CSVFileData handler now descend from this class.
- Added requestType property and setRequestType method to AjaxDataHandler for changing between GET and POST.
- Added urlData property and setUrlData method to AjaxDataHandler to allow assignment of POST data and GET url parameters
- Added onNeedsData event and setXMLData method to AjaxDataHandler to support 3rd party Ajax libraries for data retrieval
- Added reload flag to setUrl method (default = false) in AjaxDataHandler to allow for immediate data retrieval / series reload.
- Added Chart.allow_hide_error property (default = false) which allows error messages to be hidden and overwritten with non-error messages
- Added additional error checking and reporting into xmlrequestpool, errors occuring during series data retrieval via XML or CSVFile data handlers will be displayed on the chart.
- Added EJSC.utility.XMLRequestPool.fatalErrors property to define which HTTP codes cause a XMLHttpRequest to fail.
- Added redraw flag to Chart.addSeries in order to postpone full redraw until all series have been added.

Added Chart.remove() method which completely deletes a chart from the page.

Modifications

- Moved a number of private properties into the EJSC namespace for easier patching.
- Modified load/unload events to use utility.attachEvent method so that the methods are detached automatically
- Changed non-IE browser load of stylesheet to insert link tag instead of force load stylesheet via ajax
- Reduced minimum height to 60 px
- Tick container now positioned absolute in order to support additional styling options.
- Added chart parameter to onShowCrosshairs event
- Removed case sensitivity requirement for locating support files.

Bug Fixes

- Consolidate references to html and head tags, clear references on unload to fix IE leak
- Fixed issue with attachEvent in Opera causing errors
- Added cleanup routine to series in order to remove references to legend items and fix IE leaks
- Fixed canvas cover positioning
- x_axis container left coordinate is now set to fix issues with table/float layouts causing odd shifts in IE
- doRecalcExtremes now called in resize method in order to re-adjust padding appropriately to the new chart size
- Fixed issues with drawing first series added when extreme values are static
- Fixed issues in recalculation of extreme values when no series data is available
- Fixed offset issues with hints and point selection
- Fixed issues with point selection routine when no point is selected
- Fixed onBeforeDblClick event to send correct reference to chart
- Fixed issue with array data handler loading when array is empty
- Fixed scatter series to not draw line through center of circle
- Fixed and optimized several issues with drawing and point selection within BarSeries with many bars
- Fixed issues with calculating spacing and widths with multiple bar series in a single chart
- Fixed issues with drawing and point selection in bar series when bar is only partially in view
- Fixed style issues with legend header and legend captions in IE

2.10 Changes in version 1.0.1

Additions

- Added series.opacity property
- Added series.setOpacity method
- Added series.lineOpacity property
- Added series.setLineOpacity property
- Added useUTC property to DateFormatter (default value == true)
- Added timezoneOffset property to DateFormatter (default value == undefined) Only applicable when useUTC is true
- Added series.legendlsVisible property (default value == true)
- Added series.showLegend and series.hideLegend methods
- Added chart.legendTitle property and chart.setLegendTitle method

Modifications

- Modified to remove all code inside target div
- Attach events to chart container to prevent selection
- Moved lineWidth property and setLineWidth method into base Series class
- Modified LineSeries to use lineOpacity properties
- Modified AreaSeries to use opacity and lineOpacity properties
- Modified ScatterSeries to use lineWidth, opacity and lineOpacity properties
- Modified PieSeries to use lineWidth, opacity and lineOpacity properties
- Modified BarSeries to use opacity and lineOpacity properties
- Modified FunctionSeries and TrendSeries to use lineOpacity property
- Text selection is now cancelled when drag/selection originates in the chart (except Opera)

Bug Fixes

- Fixed hint and point selection issues when the chart is inside a scrollable container
- Added check and alert if attachEvent fails
- Setting y min/max, x min/max during chart creation now correctly assign extremes
- Fixed scaling errors when only a single Y or X value has been specified
- Added call to onBeforeZoom when double clicking to allow canceling of zoom out
- Added call to onAfterZoom when double clicking to zoom out
- Fixed BarSeries line drawing on Internet Explorer
- Fixed automatic resizing of y axis caption in IE when using setYAxisCaption()
- Fixed style sheets to completely hide axis when turned off
- Fixed style sheets to hide key grabber element and remove border and background from cursor position elements.
- Fixed issues with long series titles wrapping legend items
- Added additional exception handling to unload methods and storage and clearing of auto-resize interval
- Fixed errors when attempting to load empty data sets (applicable to all data handlers)
- Fixed error when loading BarSeries with a single point

2.11 Changes in version 1.0

Additions

- Added an optional redraw flag into Chart.removeSeries in order to allow for multiple removes between chart redraws.
- Added support for user-defined data associated with a point
- Added support for reading user-defined data from full and short xml formats
- Added the setTitle method to the base Series class.
- Added getDataHandler method to base Series class.
- Added getUrl and setUrl methods to XMLDataHandler and CSVFileDataHandler classes.
- Added getArray and setArray methods to ArrayDataHandler class.
- Added getCSV and setCSV methods to CSVStringDataHandler class.
- Added coloredLegend property to Series to specify whether the series legend text should inherit the series color
- Added setColoredLegend method to Series in order to update the coloredLegend property after series creation

Modifications

- Updated chart resize methods to monitor the chart container and update whenever necessary, this adds greater compatibility with other 3rd party packages such as Dojo when the chart is placed inside a window class.
- Chart.removeSeries() now deletes the series object which was removed.
- Modified series legend items to have their text color match the series color.
- Modified series legend captions to not wrap and display full text with a hint.

Bug Fixes

- Fixed event attachments to global objects such as document.onmouseup to use attachEvent / addEventListener
- Chart.removeSeries() now correctly removes the legend objects without error.
- Fixed an issue where tall charts could lose interactivity.

3 **Data Formats**

The following is a brief summary of the data formats supported by Emprise JavaScript Charts. For additional information please see the individual class help files and example code available at http://www.ejschart.com/help/

XML

The EJSC.XMLDataHandler class will load an XML file containing chart data using AJAX. The following XML formats are supported:

Full:

```
<graph>
    <plot>
     <point x="" y="" />
    </plot>
  </graph>
Short:
```

```
<G>
  <L>
    <P x="" y="" />
  </L>
</G>
```

Compact:

```
<L values="X|Y,X|Y,X|Y" />
</G>
```

Array

The EJSC.ArrayDataHandler class will load chart data from a JavaScript array. The basic format of the array is as follows:

```
[X Value, Y Value],
[X Value, Y Value]
```

CSV (Comma Separated Values)

The EJSC.CSVFileDataHandler and EJSC.CSVStringDataHandler classes support a comma separated list of data points. EJSC.CSVFileDataHandler will load the data points list from a file on the server using AJAX. EJSC.CSVStringDataHandler takes a string in its constructor specifying the CSV text.

X | Y, X | Y, X | Y

JSON (JavaScript Object Notation)

The EJSC.JSONFileDataHandler and EJSC.JSONStringDataHandler classes support JSON formatted data points. EJSC.JSONFileDataHandler will load the data points list from a file on the server using AJAX. EJSC.JSONStringDataHandlertakes a string in its constructor specifying the JSON text.

3.1 XML - Full

The full xml format is the most verbose and the most human readable of the supported formats. This format is ideal for experimenting with chart configuration and charts with smaller datasets.

General Usage:

Series Data Formats:

The above example is used for the majority of currently supported data series types. There are exceptions such as the EJSC.PieSeries, EJSC.AnalogGaugeSeries and others. For a full description of the data format for a given series, see the Data Formats topic below each series section.

Text Labels:

At times, numeric labels and the auto scaling options in the chart are not necessary, not available or not desired for display data. A EJSC.BarSeries for instance, which is used to compare number of widgets sold by color. The chart supports providing text as the X value, rather than a number:

User-Defined Data:

When displaying custom hints and implementing drill down style reports it is often necessary to have an additional piece of data associated with each data point such as a database id value. The full and short xml formats support the **userdata** property which is read in and assigned to the associated EJSC.Point descendant. The value specified is entirely up to the developer. It could be a set of integers representing a database primary key value, a url which points to drill-down data or even a javascript function. The **userdata** property of a point is available during point-related events in the chart such as EJSC.Chart.onDblClickPoint, EJSC.Chart.onAfterSelectPoint, etc.

3.2 XML - Short

The short XML format provides the same functionality as the full format but with less transfer overhead (there is no reduction in the processing overhead of extracting the point data, see the Array and CSV formats for more concise options).

The general format is as follows:

The <G> tag relates to the <graph> tag in the full format, the <L> tag relates to the <plot> tag and <P> is equivalent to <point>.

Support for pie charts is provided in the same manner as with the full format, i.e.

```
<P x="" label="" />
```

3.3 XML - Compact

The compact xml format is geared towards larger data sets which need to reduce the overhead associated with transfer and extraction of chart data via a more verbose xml format.

The data is provided in csv-like format and stored in the "values" attribute of the <L> tag:

For the majority of series, the above example would be used to provide X,Y coordinates.

4 API Reference

4.1 EJSC

Top level namespace for all classes and variables used by the Emprise JavaScript Charts package. Use of this namespace prevents variable name collisions with other available JavaScript packages.

4.1.1 Properties

Public Properties

DefaultImagePath DefaultColors DefaultBarColors DefaultPieColors STRINGS

Inherited Properties

none

4.1.1.1 DefaultImagePath

Definition

string **DefaultImagePath** = "images/"

Description

Relative path defining the path to all images used by EJSC classes.

4.1.1.2 DefaultColors

Definition

```
array defaultColors = [
                "rgb(120,90,59)",
                "rgb(53,115,53)",
                "rgb(178,87,56)",
                "rgb(203,143,71)",
                "rgb(55,106,155)",
                "rgb(205,197,51)",
                "rgb(209,130,139)",
                "rgb(159,153,57)",
                "rgb(206,173,136)",
                "rgb(191,132,72)",
                "rgb(151,135,169)",
                "rgb(140,48,51)",
                "rgb(59,144,187)",
                "rgb(197,190,104)",
                "rgb(109,136,79)",
                "rgb(144,100,144)",
                "rgb(181,94,94)",
                "rgb(59,144,144)"
                "rgb(204,136,92)",
```

```
"rgb(139,167,55)",
"rgb(205,171,66)",
"rgb(150,184,211)"
]
```

Description

This array is used in each chart to specify available series colors. Add to or modify this array in order to define a single set of default colors used by all charts on a page.

4.1.1.3 DefaultBarColors

Definition

```
array defaultBarColors = [
      "rgb(120,90,59)",
      "rgb(53,115,53)",
      "rgb(178,87,56)",
      "rgb(203,143,71)",
      "rgb(55,106,155)",
      "rgb(205,197,51)",
      "rgb(209,130,139)",
      "rgb(159,153,57)",
      "rgb(206,173,136)",
      "rgb(191,132,72)",
      "rgb(151,135,169)",
      "rgb(140,48,51)",
      "rgb(59,144,187)"
      "rgb(197,190,104)",
      "rgb(109,136,79)",
      "rgb(144,100,144)",
      "rgb(181,94,94)",
      "rgb(59,144,144)",
      "rgb(204,136,92)",
      "rgb(139,167,55)",
      "rgb(205,171,66)",
      "rgb(150,184,211)"
```

Description

Defines the pool of default colors available for bar series bars.

4.1.1.4 DefaultPieColors

Definition

```
array defaultPieColors = [
    "rgb(120,90,59)",
    "rgb(53,115,53)",
    "rgb(178,87,56)",
    "rgb(203,143,71)",
    "rgb(55,106,155)",
    "rgb(205,197,51)",
    "rgb(209,130,139)",
    "rgb(159,153,57)",
    "rgb(206,173,136)",
    "rgb(191,132,72)",
```

```
"rgb(151,135,169)",
"rgb(140,48,51)",
"rgb(59,144,187)",
"rgb(197,190,104)",
"rgb(109,136,79)",
"rgb(144,100,144)",
"rgb(181,94,94)",
"rgb(59,144,144)",
"rgb(204,136,92)",
"rgb(139,167,55)",
"rgb(205,171,66)",
"rgb(150,184,211)"
```

Description

Defines the pool of default colors available for pie pieces.

4.1.1.5 **STRINGS**

Definition

Description

Defines the default strings used by the chart.

4.2 EJSC.Chart

Chart class that holds all the generic information for each chart that is being created.

The constructor expects the id or reference for a DOM object (preferrably a div) and an optional set of object properties. **NOTE**: The contents of the DOM object will be cleared before rendering the chart.

Constructor

Defining Chart Properties and Events

Chart properties may be set individually after the chart has been created or in batch using the options parameter during instantiation.

Setting properties individually

Setting properties in batch

4.2.1 Properties

4.2.1.1 allow_interactivity

Definition

boolean allow_interactivity = true

Description

Defines if the chart can be interacted with (ie zooming, moving, point selection, etc.).

Example

>> Turn off all interactivity for the chart

4.2.1.2 allow_mouse_wheel_zoom

Definition

boolean allow_mouse_wheel_zoom = true

Description

Defines if the chart can be zoomed via the scroll wheel on the mouse. This is automatically disabled if allow_interactivity or allow_zoom is set to false.

Example

>> Turn off wheel zooming for the chart.

4.2.1.3 allow_move

Definition

boolean allow_move = true

Description

Defines if the chart can be moved once it has been zoomed in. This is automatically disabled if allow interactivity is set to false.

Example

>> Turn off moving for the chart.

4.2.1.4 allow_zoom

Definition

boolean allow_zoom = true

Description

Defines if the chart can be zoomed. This is automatically disabled if allow_interactivity is set to false.

Example

>> Turn off zooming for the chart.

4.2.1.5 allow_hide_error

Definition

boolean allow_hide_error = false

Description

Defines whether the chart can overwrite an error message with a non-error message or hide the error message after a brief period of time.

Example

>> Allow all messages, including errors, to be hidden after a brief period of time

4.2.1.6 auto_find_point_by_x

Definition

boolean auto_find_point_by_x = false

Description

Defines if the select point routine should select points based only on the X position of the cursor.

Example

>> Allow point selection to occur on click anywhere within the Y axis, find the closest point based solely on X.

4.2.1.7 auto_resize

Definition

boolean auto_resize = true

Description

Defines if the chart will start a timer to check for size changes in order to automatically redraw. If you are controlling the display, size and position of the chart div container manually, it may be beneficial to turn this option off in order to eliminate the timer overhead.

Example

>> Turn off the chart's auto resize functionality

4.2.1.8 auto zoom

Definition

string auto_zoom = undefined


Valid property values:



Description

Defines if the chart should auto-select the zoom area based on the X or Y coordinates selected by the user. The other coordinates are automatically selected based on best fit for the data defined in the range selected.

Example



>> Allow user to select beginning and ending X values to zoom, then auto-scale the Y axis according to the data.

4.2.1.9 axis_bottom

Definition

EJSC.Axis axis_bottom = EJSC.LinearAxis

Description

Defines the axis that will at the bottom of the chart. All four axes are defined as EJSC.LinearAxis by default when the chart is created and do not need to be manually created unless a different type of axis is needed. These properties automatically allow the setting of axis properties during chart creation as shown in the example below.

```
Types:
EJSC.LinearAxis
EJSC.LogarithmicAxis
```

Example

>> Hide the bottom axis

>> Display a base 10 logarithmic axis at the bottom of the chart.

4.2.1.10 axis_left

Definition

EJSC.Axis axis_left = EJSC.LinearAxis

Description

Defines the axis that will at the left side of the chart. All four axes are defined as EJSC.LinearAxis by default when the chart is created and do not need to be manually created unless a different type of axis is needed. These properties automatically allow the setting of axis properties during chart creation as shown in the example below.

```
Types:
EJSC.LinearAxis
EJSC.LogarithmicAxis
```

Example

>> Hide the left axis

>> Display a base 10 logarithmic axis at the left side of the chart.

4.2.1.11 axis_right

Definition

EJSC.Axis axis_right = EJSC.LinearAxis

Description

Defines the axis that will at the right side of the chart. All four axes are defined as EJSC.LinearAxis by

default when the chart is created and do not need to be manually created unless a different type of axis is needed. These properties automatically allow the setting of axis properties during chart creation as shown in the example below.

```
Types:
EJSC.LinearAxis
EJSC.LogarithmicAxis
```

Example

>> Show the right axis

>> Display a base 10 logarithmic axis at the right side of the chart.

4.2.1.12 axis_top

Definition

EJSC.Axis axis_top = EJSC.LinearAxis

Description

Defines the axis that will at the top of the chart. All four axes are defined as EJSC.LinearAxis by default when the chart is created and do not need to be manually created unless a different type of axis is needed. These properties automatically allow the setting of axis properties during chart creation as shown in the example below.

```
Types:
EJSC.LinearAxis
EJSC.LogarithmicAxis
```

Example

>> Show the top axis

>> Display a base 10 logarithmic axis at the top of the chart.

```
axis_top: new EJSC.LogarithmicAxis({ base: 10 })
}
);
```

4.2.1.13 background

Definition

```
object background = {
          color: "#FFF",
          opacity: 0,
          includeTitle: false
};
```

Description

Defines the color and opacity of the chart area background. If the include Title property is set to true, the title bar area will be filled as well. If opacity is 0, no fill will occur.

NOTE: To set the color of then entire chart area (all axes, chart, titlebar, etc.), set the background-color style for the chart DOM object.

```
<div id="chart" style="width: 400px; height: 400px; background-color: #ffff00;"></div>
```

4.2.1.14 building_message

Definition

string **building_message** = EJSC.STRINGS["building_message"]

Description

Defines if text to display while the chart is being initially assembled. The default string used for all charts in the page is drawn from the EJSC.Strings property.

4.2.1.15 drawing_message

Definition

```
string drawing_message = EJSC.STRINGS["drawing_message"]
```

Description

Defines if text to display while the chart is being drawn. The default string used for all charts in the page is drawn from the EJSC.Strings property.

4.2.1.16 legend state

Definition

```
string legend_state = "normal"
```

Valid options are "normal" or "minimized".

Description

Defines the initial state of the legend. This property is only applicable during chart creation. To modify the state of the legend after the chart has been created, see Chart.legendMinimize() and Chart.legendRestore(). To check the current state of the legend during chart execution, see Chart.getLegendState().

4.2.1.17 legend_title

Definition

```
string <a href="legend_title">legend_title</a> = EJSC.STRINGS["chart_legend_title"]
```

Description

Defines the caption displayed in the chart legend title bar. To modify this caption after chart creation, use Chart.setLegendTitle()

4.2.1.18 max_zoom_message

Definition

```
string max_zoom_message = EJSC.STRINGS["max zoom message"]
```

Description

Defines if text to display when the maximum zoom has been reached. The default string used for all charts in the page is drawn from the EJSC.Strings property.

4.2.1.19 message_timeouts

Definition

```
object message_timeouts = {
    progress: 500,
    nodata: 500,
    info: 500,
    error: 2000
};
```

Description

Defines the amount of time in milliseconds to display a particular message type.

4.2.1.20 proximity_snap

Definition

```
integer proximity_snap = 5
```

Description

Determines the maximum number of pixels away from a point the cursor can be for point selection and hints.

Example

>> Allow clicks to trigger point selection up to 9 pixels away from the actual point.

4.2.1.21 show hints

Definition

boolean **show_hints** = true

Description

Defines whether hints should be selected when a point is hovered over or selected. This is automatically disabled if allow_interactivity is set to false.

Example

>> Turn off hints and point selection.

4.2.1.22 show_legend

Definition

boolean **show_legend** = true

Description

Defines if the chart legend should be displayed.

Example

>> Turn off legend display

4.2.1.23 show_messages

Definition

boolean **show_messages** = true

Description

Defines if progress messages should be displayed above the chart or not.

Example

>> Turn off progress messages.

4.2.1.24 show titlebar

Definition

boolean show_titlebar = true

Description

Defines if the titlebar (containing chart title and mouse position indicators) should be displayed above the chart.

Example

>> Display the chart without a titlebar

4.2.1.25 title

Definition

string title = "Emprise JavaScript Chart"

Description

Defines the title of the chart. It is displayed at the top left of the chart.

Example

>> Give the chart a name.

4.2.2 Methods

4.2.2.1 acquireSeries

Definition

void acquireSeries (EJSC.Series series, boolean redraw)

Description

Moves a series from one chart to another. This method will remove the series from the chart which

currently owns it and add it to the chart making the acquireSeries call.

Sends:

series - The series to be moved redraw - Boolean flag telling the old and new charts if they should redraw immediately. Specifying **false** here will require that both charts redraw() methods are called in order to display the results of the acquisition.

4.2.2.2 addSeries

Definition

EJSC.Series addSeries (EJSC.Series series, boolean redraw)

Description

Adds a new series to the chart and returns the newly added series (this is useful when creating series inline as shown in the example below). The series must descend from EJSC.Series.

If redraw is false, drawing will not occur immediately but will not be entirely prevented. Certain actions such as adding an additional series with redraw = true, or chart dimensions changing may still trigger the series to draw. The default, if redraw is omitted is **true**.

Note: If the series has not defined a title (i.e. Series.title = "") at the time addSeries is called, a default title of "Series <index>" will be assigned (where <index> is the current series index in internal series storage).

```
Types:
```

EJSC.AlarmSeries

EJSC.AnalogGaugeSeries

EJSC.AreaSeries

EJSC.BarSeries

EJSC.CandlestickSeries

EJSC.DoughnutSeries

EJSC.ErrorSeries

EJSC.FloatingBarSeries

EJSC.FunctionSeries

EJSC.LineSeries

EJSC.OpenHighLowCloseSeries

EJSC.OverUnderSeries

EJSC.PieSeries

EJSC.ScatterSeries

EJSC.StepSeries

EJSC.StackedBarSeries

EJSC.TrendSeries

Example

>> Add a line series to the chart.

```
var myChart = new EJSC.Chart("chart");
var mySeries = myChart.addSeries(new EJSC.LineSeries(...));
```

4.2.2.3 clearSelectedPoint

Definition

void clearSelectedPoint()

Description

Clears the current point selection and hides the hint if necessary.

4.2.2.4 exportSVG

Definition

string exportSVG(object Options)

Options Described (parameter {default value})

includeHeader {true}

The includeHeader property defines whether the result should include the xml declaration (<?xml version="1.0"?>) and the SVG doctype tags.

height {chart height in pixels}

The height property defines the height attribute of the viewbox attribute in the output svg tag (see viewbox). By default this is the pixel height of the chart but may be set to an arbitrary number or percentage such as "100%"

width {chart width in pixels}

The width property defines the width attribute of the viewbox attribute in the output svg tag (see viewbox). By default this is the pixel width of the chart but may be set to an arbitrary number or percentage such as "100%"

namespace {none}

The namespace property defines the prefix namespace to use for the svg tags. This is useful when used with includeHeader=false if including the resulting svg inside another document type. By default, this left undefined and the resulting svg will look something like <svg ... >...</svg>. If defined, for example as namespace = mysvg, the resulting svg will look like <mysvg:svg ...>...</mysvg:svg>.

Description

This method will export the chart as it is currently rendered as SVG. This string can be returned to the server for processing into many different forms such as png or pdf. The server-side processing of this data is beyond the scope of this help document.

Example:

4.2.2.5 exportSVGLegend

Definition

string exportSVGLegend(object Options)

Options Described (parameter {default value})

orientation {"horizontal"}

The orientation property defines how the legend dimensions will be calculated. Valid options are "horizontal" and "vertical". When using horizontal, the legend's width will match the chart's width and the legend items will be displayed left to right, top to bottom. The height will expand as needed to accomidate all legend items. Specifying vertical for orientation will cause the legend to match the charts height and display the legend items top to bottom, left to right, expanding the width of the legend as necessary.

includeHeader {true}

The includeHeader property defines whether the result should include the xml declaration (<?xml version="1.0"?>) and the SVG doctype tags.

height {chart height in pixels}

The height property defines the height attribute of the viewbox attribute in the output svg tag (see viewbox). By default this is the pixel height of the chart but may be set to an arbitrary number or percentage such as "100%"

width {chart width in pixels}

The width property defines the width attribute of the viewbox attribute in the output svg tag (see <u>viewbox</u>). By default this is the pixel width of the chart but may be set to an arbitrary number or percentage such as "100%"

namespace {none}

The namespace property defines the prefix namespace to use for the svg tags. This is useful when used with includeHeader=false if including the resulting svg inside another document type. By default, this left undefined and the resulting svg will look something like <svg ... >...</svg>. If defined, for example as namespace = mysvg, the resulting svg will look like <mysvg:svg ... >... </mysvg:svg>.

border {}

show {true}

The show property determines whether or not to draw a border around the entire

legend area.

color {"#000"}

The color property specifies the color of the border, only applicable if show is true.

size {1}

The size specifies the size (thickness) of the border drawn, only applicable if show is true.

show_title {true}

The show_title property determines whether to draw the title area of the legend. If false or if the chart's title property is blank, the legend title area will not be drawn.

Description

This method will export the chart legend as it relates to the currently rendered chart. The legend is exported in a more print friendly manner and may be customized using the options described above. The exported SVG string can be returned to the server for processing into many different forms such as png or pdf. The server-side processing of this data is beyond the scope of this help document.

Example:

```
<script type="text/javascript">
               var chart = new EJSC.Chart("myChart", {});
               var series = new EJSC.LineSeries(
                               new EJSC.ArrayDataHandler([[1,1],[2,2],[3,3],[4,2],[5,1]]),
               chart.addSeries(series);
               function buttonClick() {
                               alert(chart.exportSVG({
                                               height: "50%",
width: "50%",
                                               border: {
                                                                show: true,
                                                               color: "#F00",
                                                                size: 4
                                                show_title: false
                               }));
               }
<button onclick="buttonClick();">Export SVG</button>
```

4.2.2.6 findClosestPoint

Definition

EJSC.Point findClosestPoint(interger x, integer y, boolean select, boolean sticky)

Description

Given X and Y as screen pixel coordinates (not chart coordinates), this method will find and return the closest point in any of its series. Optionally, the point may be selected by sending true for the select parameter and displayed as either as a popup hint (i.e. when a user hovers over a point) by sending false for the sticky parameter or a sticky hint (i.e. a user clicks on a point) by sending true.

4.2.2.7 getLegendState

Definition

```
string getLegendState()
```

Possible return values:

```
"normal"
"minimized"
```

Description

Returns the string which represents the current state of the legend window.

4.2.2.8 getMinMaxYInXRange

DEPRECATED - Will be replaced in a future version

Definition

```
object getMinMaxYInXRange( float x_min, float x_max )

RETURNS:
{ y_min: float, y_max: float }
```

Description

Returns the min and max Y values for the provided X range.

4.2.2.9 getSeries

Definition

```
void getSeries( )
```

Description

Returns an array of EJSC. Series object currently assigned to the chart.

4.2.2.10 getZoomBoxPixelCoordinates

Definition

```
object getZoomBoxPixelCoordinates( string ScreenOrChart )

RETURNS:
{ left: integer, top: integer, right: integer, bottom: integer, width: integer, height: integer }

ScreenOrChart Values:
    "screen"
    "chart"
```

Description

Returns the current pixel coordinates of the zoom box (whether visible or not). The ScreenOrChart

parameter may be used to specify if the coordinates returned are based off the top left of the chart ("chart"), or the top left of the page ("screen").

4.2.2.11 hideTitlebar

Definition

void hideTitlebar()

Description

Hides the titlebar, resizes and chart area and redraws all visible series.

No effect if the titlebar is already hidden.

4.2.2.12 hideZoomBox

Definition

void hideZoomBox()

Description

Hides the zoom box. No effect if the zoom box is already hidden.

4.2.2.13 legendMinimize

Definition

void legendMinimize()

Description

Minimizes the legend window. This has no effect if the legend window is already in a minimized state.

4.2.2.14 legendRestore

Definition

void legendRestore()

Description

This method restores the legend window from its minimized state to its previous height.

4.2.2.15 redraw

Definition

void redraw(boolean reselectPoint)

Description

Resizes chart elements (if necessary) and redraws the entire chart and all series contained within. the

reselectPoint parameter determines whether to retain point selection (if any) between redraws.

4.2.2.16 remove

Definition

void remove()

Description

Removes the chart from the page, cleans up all attached events, references, timeouts and intervals and clears the contents of the parent element (specified during creation).

4.2.2.17 removeSeries

Definition

void removeSeries (EJSC.Series series, boolean redraw)

Description

Removes the specified series from the chart and triggers an immediate rescaling and redraw. Send in redraw = false if performing multiple removes and want to delay redrawing until complete.

4.2.2.18 selectPoint

Definition

void selectPoint(EJSC.Point point, boolean sticky)

Description

Selects the point provided. The sticky property specifies whether the hint window will close when the mouse moves over another point in the chart.

The point object can be retrieved using the Chart.findClosestPoint() or Series.findClosestByPoint() methods.

4.2.2.19 setAutoResize

Definition

void setAutoResize(boolean auto_resize)

Description

Enables or disables the auto_resize functionality once the chart has been created.

4.2.2.20 setLegendTitle

Definition

void setLegendTitle(string title)

Description

Updates the caption in the legend window title bar.

4.2.2.21 setShowLegend

Definition

void setShowLegend(boolean show)

Description

Shows or hides the chart legend and updates the value of Chart.show_legend

4.2.2.22 setTitle

Definition

void setTitle(string title)

Description

Updates the chart title shown in the title area of the chart. This method must be used to change the title once the chart has been rendered.

To set a default chart title on creation, see EJSC.Chart.title.

4.2.2.23 showTitlebar

Definition

void showTitlebar()

Description

Shows the titlebar, resizes and chart area and redraws all visible series.

No effect if the titlebar is already visible.

4.2.2.24 showZoomBox

Definition

void **showZoomBox**(coordinate x_min, coordinate x_max, string x_axis, coordinate y_min, coordinate y max, string y axis)

Description

Shows the zoom box at the specified chart coordinates using the axes specified.

Example

```
>> Show the zoom box at x=10,y=10, x=100, y=100
```

```
var chart = new EJSC.Chart("chart",
```

4.2.3 Events

4.2.3.1 onAfterBuild

Definition

void onAfterBuild(EJSC.Chart chart)

Description

Called immediately after the chart has finished writing itself to the page. Sends the chart object which triggered the event.

4.2.3.2 onAfterDraw

Definition

void onAfterDraw(EJSC.Chart chart)

Description

Called after a drawing option has completed. Sends the chart object which triggered the event.

4.2.3.3 onAfterDrawSeries

Definition

void onAfterDrawSeries (EJSC.Chart chart, CanvasContext ctx)

Description

Called after the series are drawn.

Sends:

chart - The chart object which finished drawing its series ctx - The canvas context which was just drawn to

4.2.3.4 onAfterMove

Definition

void onAfterMove(EJSC.Chart chart)

Description

Called after the chart has been dragged/moved while zoomed in. Sends the chart object which triggered the event.

4.2.3.5 onAfterSelectPoint

Definition

void **onAfterSelectPoint**(EJSC.Point point, EJSC.Series series, EJSC.Chart chart, DOMObject hint_element, string HoverOrSelect)

Description

Called after a point has been selected due to mouse over (hover) or physical selection (click, keyboard).

Sends:

```
point - The point object selected.
series - The series object in which the point exists.
chart - The chart object which triggered the event (owns the series/point).
hint_element - The DOM object which contains the hint text/markup
HoverOrSelect - String "hover" or "select" to indicate what triggered the event.
```

4.2.3.6 onAfterUnselectPoint

Definition

void onAfterUnselectPoint()

Description

Called after a point has lost selection.

4.2.3.7 onAfterZoom

Definition

void onAfterZoom(EJSC.Chart chart)

Description

Called after the chart has been zoomed. Sends the chart object which triggered the event.

4.2.3.8 onBeforeBuild

Definition

void onBeforeBuild(EJSC.Chart chart)

Description

Called immediately before the chart begins writing itself to the page. Sends the chart object which triggered the event.

4.2.3.9 onBeforeDblClick

Definition

boolean onBeforeDblClick(EJSC.Chart chart)

Description

Called before the chart does any processing related to a double click. Return **false** may be used to cancel all additional processing.

4.2.3.10 onBeforeDraw

Definition

boolean onBeforeDraw()

Description

Called before the chart is drawn. If return is false, draw is canceled.

4.2.3.11 onBeforeDrawSeries

Definition

void onBeforeDrawSeries(EJSC.Chart chart, CanvasContext ctx)

Description

Called before the series are drawn.

Sends:

chart - The chart object about to draw its series

ctx - The canvas context about to be drawn to

4.2.3.12 onBeforeSelectPoint

Definition

boolean **onBeforeSelectPoint**(EJSC.Point point, EJSC.Series series, EJSC.Chart chart, DOMObject hint element, string HoverOrSelect)

Description

Called after a point has been selected due to mouse over (hover) or physical selection (click, keyboard).

Sends:

```
point - The point object about to be selected.
series - The series object in which the point exists.
chart - The chart object which triggered the event (owns the series/point).
hint_element - The DOM object which contains the hint text/markup
HoverOrSelect - String "hover" or "select" to indicate what triggered the event.
```

4.2.3.13 onBeforeUnselectPoint

Definition

void onBeforeUnselectPoint(EJSC.Point point, EJSC.Series series, EJSC.Chart chart)

Description

Called before a point has been unselected. If return is false, current point selection is not lost.

Sends:

point - The point object about to lose selected.

4.2.3.14 onContextMenu

Definition

void onBeforeUnselectPoint(EJSC.Point point, Event event)

Description

Called when the context menu event is fired on the chart object.

Sends:

chart - The chart object that triggered the event

event - The JavaScript event object

4.2.3.15 onDblClickPoint

Definition

boolean onDblClickPoint(EJSC.Point point, EJSC.Series series, EJSC.Chart chart)

Description

Called when a point is double clicked or the ENTER key is pressed and a point is selected. If return is false, cancels zoom-out (if axis are shown).

4.2.3.16 onShowHint

Definition

string **onShowHint**(EJSC.Point point, EJSC.Series series, EJSC.Chart chart, DOMObject hint_element, string HoverOrSelect)

Description

Called after a point has been selected due to mouse over (hover) or physical selection (click, keyboard).

A custom string may be returned in order to specify the contents of the hint window. See Text Replacement Options for more details.

Sends:

point - The point object selected.
series - The series object in which the point exists.
chart - The chart object which triggered the event (owns the series/point).
hint_element - The DOM object which contains the hint text/markup
HoverOrSelect - String "hover" or "select" to indicate what triggered the event.

4.2.3.17 onShowMessage

Definition

void onShowMessage(string message, string type)

Description

Called when the status message is displayed (in the top right corner of the chart).

Sends:

message - The text to be displayed type - A string identifying the type of message window. This may be "error" or "info"

4.2.3.18 onUserBeginZoom

Definition

boolean onUserBeginZoom(EJSC.Chart chart)

Description

Called when the user begins to draw the zoom box by clicking in the chart area and dragging down and to the right.

Returning false will cancel the zoom operation and hide the zoom box.

4.2.3.19 onUserEndZoom

Definition

boolean onUserEndZoom(EJSC.Chart chart)

Description

Called when the user finishes drawing the zoom box but before the zoom takes place.

Returning false will cancel the zoom operation and hide the zoom box.

4.2.4 Deprecated

4.2.4.1 Properties

4.2.4.1.1 force_static_points

DEPRECATED See EJSC.Axis.force_static_points

4.2.4.1.2 force_static_points_x

DEPRECATED See EJSC.Axis.force static points

4.2.4.1.3 force_static_points_y

DEPRECATED See EJSC.Axis.force_static_points

4.2.4.1.4 legendTitle

DEPRECATED See EJSC.Chart.legend_title

4.2.4.1.5 show_crosshairs

DEPRECATED See EJSC.Axis.crosshair

4.2.4.1.6 show_grid

DEPRECATED See EJSC.Axis.grid

4.2.4.1.7 show_mouse_position

DEPRECATED See EJSC.Axis.cursor_position

4.2.4.1.8 show_x_axis

DEPRECATED See EJSC.Axis.visible

4.2.4.1.9 show_y_axis

DEPRECATED See EJSC.Axis.visible

4.2.4.1.10 x_axis_caption

DEPRECATED See EJSC.Axis.caption

4.2.4.1.11 x_axis_className

DEPRECATED See EJSC.Axis.caption_class

4.2.4.1.12 x_axis_extremes_ticks

DEPRECATED See EJSC.Axis.extremes_ticks

4.2.4.1.13 x_axis_formatter

DEPRECATED See EJSC.Axis.formatter

4.2.4.1.14 x_axis_max_tick_interval

DEPRECATED See EJSC.Axis.major_ticks

4.2.4.1.15 x_axis_min_tick_interval

DEPRECATED See EJSC.Axis.major_ticks

4.2.4.1.16 x_axis_minor_ticks

DEPRECATED See EJSC.Axis.minor_ticks

4.2.4.1.17 x_axis_size

DEPRECATED See EJSC.Axis.size

4.2.4.1.18 x_axis_stagger_ticks

DEPRECATED See EJSC.Axis.stagger ticks

4.2.4.1.19 x_axis_tick_className

DEPRECATED See EJSC.Axis.label_class

4.2.4.1.20 x_axis_tick_count

DEPRECATED See EJSC.Axis.major_ticks

4.2.4.1.21 x_cursor_position_caption

DEPRECATED See EJSC.Axis.cursor_position

4.2.4.1.22 x_cursor_position_formatter

DEPRECATED See EJSC.Axis.cursor_position

4.2.4.1.23 x_max

DEPRECATED See EJSC.Axis.max_extreme

4.2.4.1.24 x_min

DEPRECATED See EJSC.Axis.min_extreme

4.2.4.1.25 x_value_hint_caption

DEPRECATED See EJSC.Axis.hint_caption

4.2.4.1.26 x_zero_plane

DEPRECATED See EJSC.Axis.zero plane

4.2.4.1.27 y_axis_caption

DEPRECATED See EJSC.Axis.caption

4.2.4.1.28 y_axis_className

DEPRECATED See EJSC.Axis.caption_class

4.2.4.1.29 y_axis_extremes_ticks

DEPRECATED See EJSC.Axis.extremes_ticks

4.2.4.1.30 y_axis_formatter

DEPRECATED See EJSC.Axis.formatter

4.2.4.1.31 y_axis_max_tick_interval

DEPRECATED See EJSC.Axis.major_ticks

4.2.4.1.32 y_axis_min_tick_interval

DEPRECATED See EJSC.Axis.major_ticks

4.2.4.1.33 y_axis_minor_ticks

DEPRECATED See EJSC.Axis.minor_ticks

4.2.4.1.34 y_axis_size

DEPRECATED See EJSC.Axis.size

4.2.4.1.35 y_axis_tick_className

DEPRECATED See EJSC.Axis.label_class

4.2.4.1.36 y_axis_tick_count

DEPRECATED See EJSC.Axis.major_ticks

4.2.4.1.37 y_cursor_position_caption

DEPRECATED See EJSC.Axis.cursor_position

4.2.4.1.38 y_cursor_position_formatter

DEPRECATED See EJSC.Axis.cursor_position

4.2.4.1.39 y_max

DEPRECATED See EJSC.Axis.max_extreme

4.2.4.1.40 y_min

DEPRECATED See EJSC.Axis.min_extreme

4.2.4.1.41 y_value_hint_caption

DEPRECATED See EJSC.Axis.hint_caption

4.2.4.1.42 y_zero_plane

DEPRECATED See EJSC.Axis.zero_plane

4.2.4.2 Methods

4.2.4.2.1 addXAxisBin

DEPRECATED See EJSC.Axis.addBin

4.2.4.2.2 addYAxisBin

DEPRECATED See EJSC.Axis.addBin

4.2.4.2.3 convertPixelToPoint

DEPRECATED See EJSC.Axis.pixelToPoint

4.2.4.2.4 convertPointToPixel

DEPRECATED See EJSC.Axis.pointToPixel

4.2.4.2.5 findClosestPointInSeries

DEPRECATED See EJSC.Series.findClosestByPoint

4.2.4.2.6 hideGrid

DEPRECATED See EJSC.Axis.hideGrid

4.2.4.2.7 hideXAxis

DEPRECATED See EJSC.Axis.hide

4.2.4.2.8 hideYAxis

DEPRECATED See EJSC.Axis.hide

4.2.4.2.9 getXExtremes

DEPRECATED See EJSC.Axis.getExtremes

4.2.4.2.10 getYExtremes

DEPRECATED See EJSC.Axis.getExtremes

4.2.4.2.11 getZoom

DEPRECATED See EJSC.Axis.getZoom

4.2.4.2.12 removeXAxisBin

DEPRECATED See EJSC.Axis.removeBin

4.2.4.2.13 removeYAxisBin

DEPRECATED See EJSC.Axis.removeBin

4.2.4.2.14 selectClosestPoint

DEPRECATED See EJSC.Chart.findClosestPoint

4.2.4.2.15 setCrosshairs

DEPRECATED See EJSC.Axis.setCrosshair

4.2.4.2.16 setXAxisCaption

DEPRECATED See EJSC.Axis.setCaption

4.2.4.2.17 setXExtremes

DEPRECATED See EJSC.Axis.setExtremes

4.2.4.2.18 setYAxisCaption

DEPRECATED See EJSC.Axis.setCaption

4.2.4.2.19 setYExtremes

DEPRECATED See EJSC.Axis.setExtremes

4.2.4.2.20 setZoom

DEPRECATED See EJSC.Axis.setZoom

4.2.4.2.21 showGrid

DEPRECATED See EJSC.Axis.showGrid

4.2.4.2.22 showXAxis

DEPRECATED See EJSC.Axis.show

4.2.4.2.23 showYAxis

DEPRECATED See EJSC.Axis.show

4.2.4.3 Events

4.2.4.3.1 onAfterShowCrosshairs

DEPRECATED

There is no direct replacement for this event. See EJSC.Axis.onShowCrosshair

4.2.4.3.2 onBeforeBeginZoom

DEPRECATED See EJSC.Chart.onUserBeginZoom

4.2.4.3.3 onBeforeEndZoom

DEPRECATED See EJSC.Chart.onUserEndZoom

4.2.4.3.4 onShowCrosshairs

DEPRECATED

There is no direct replacement for this event. See EJSC.Axis.onShowCrosshair

4.2.4.3.5 onXAxisNeedsTicks

DEPRECATED See EJSC.Axis.onNeedsTicks

4.2.4.3.6 onYAxisNeedsTicks

DEPRECATED See EJSC.Axis.onNeedsTicks

4.3 Axis Types

4.3.1 LinearAxis

LinearAxis is the default axis type for all four chart axes.

The constructor takes an optional set of object properties used to perform initial configuration.

Constructor

Defining Properties and Events

LinearAxis properties may be set individually after the chart has been initialized and/or the axis has been created or in batch using the options parameter during instantiation.

Setting properties individually

Setting properties in batch

4.3.1.1 Properties

4.3.1.1.1 background (inherited)

Definition

```
object background = {
      color: "#fff",
      opacity: 0,
      includeTitle: false
};
```

Description

Defines the color and opacity of the axis area background. Setting the includeTitle property to true will fill the axis caption area as well as the ticks. If opacity is set to 0, no fill will occur.

4.3.1.1.2 border (inherited)

Definition

Description

Defines the appearance of the axis side bordering the chart area. By default the border color inherits the axis color property (EJSC.Axis.color)

Example

>> Provide a 2 pixel tall green border on the bottom axis.

```
var chart = new EJSC.Chart( "chart", {
          axis_bottom: {
          border: { thickness: 2, color: "#0F0" }
```

```
} );
```

4.3.1.1.3 caption (inherited)

Definition

```
string caption = "Axis"
```

Description

Defines the text to be displayed below or beside the axis.

For styling the caption, see EJSC.Axis.caption_class

Example

>> Customize the bottom axis caption.

```
var chart = new EJSC.Chart( "chart", {
                axis_bottom: { caption: "Year" }
} );
```

4.3.1.1.4 caption_class (inherited)

Definition

```
string caption_class = ""
```

Description

Defines the CSS className to assign to the axis caption.

For styling the tick labels, see EJSC.Axis.label_class

Example

>> Style the axis caption bold.

4.3.1.1.5 color (inherited)

Definition

```
string color = "#FFF"
```

Description

Defines the default color of the axis border and tick marks. If the sub properties such as minor_ticks.color, major_ticks.color, border.color are left undefined, they inherit the value set here.

Example

>> Color the axis border and tick marks red

```
var chart = new EJSC.Chart( "chart", {
                axis_bottom: { color: "#F00" }
} );
```

4.3.1.1.6 crosshair (inherited)

Definition

```
object crosshair = {
            show: false,
            color: "#F00"
}
```

Description

Defines if crosshair should be shown on the chart at the current mouse coordinates as they relate to the given axis. May be enabled and disabled for each axis independently. This is automatically disabled for all axes if EJSC.Chart.allow_interactivity is set to false.

Example

>> Show crosshair based on the bottom axis mouse position.

4.3.1.1.7 cursor_position (inherited)

Definition

```
object cursor_position = {
    show: false,
    color: "#F00",
    textColor: "#FFF",
    formatter: undefined,
    caption: undefined,
    className: undefined}
```

Description

Defines the display properties of the cursor position feature for an axis. These properties may be used to turn the cursor position indicator on and off as well as configure the styling and color.

show: determines whether or not to display the cursor position while the mouse is within the chart area

color: sets the background and line color

textColor: sets the text color

formatter: defines a formatter to use when displaying coordinates, if left undefined it will use the axis formatter

caption: defines text to use as a prefix to the current coordinate

className: a CSS class name to be used for additional styling

Example

>> Turn on cursor position for the bottom axis and configure to display a related label

4.3.1.1.8 extremes_ticks (inherited)

Definition

boolean extremes_ticks = false

Description

Defines if the min and max values should be forced to land on the next tick mark.

Example

>> Force tick marks at the min and max coordinates of the bottom axis (left and right sides of the chart)

```
var chart = new EJSC.Chart( "chart", {
          axis_bottom: { extremes_ticks: true }
} );
```

4.3.1.1.9 force_static_points (inherited)

Definition

boolean force_static_points = false

Description

Defines if the chart should force ticks to match up to every point by converting the data to strings.

Example

>> Display every bottom axis data point, essentially disable auto axis scaling.

```
var chart = new EJSC.Chart( "chart", {
          axis_bottom: { force_static_points: true }
} );
```

4.3.1.1.10 formatter (inherited)

Definition

EJSC.Formatter formatter = EJSC.Formatter

Description

Defines the formatter that will be used to format the tick marks on the axis before displaying them.

```
Types:
EJSC.DateFormatter
EJSC.NumberFormatter
EJSC.StringFormatter
```

Example

>> Display bottom axis tick labels as \$0.00

Definition

```
object grid = {
        thickness: 1,
        color: "rgb(230,230,230)",
        opacity: 100,
        show: true
}
```

Description

Defines the appearance and visibility of the grid drawn in the background.

Example

>> Do not draw the background grid for the top and right axes.

4.3.1.1.12 hint_caption (inherited)

Definition

```
string hint_caption = "Value:"
```

Description

Defines the text to display in front of the axis-related value in the hint (leave blank to hide the value when displaying the hint).

Example

>> Customize the value label in the hint window

4.3.1.1.13 label_class (inherited)

Definition

```
string label_class = ""
```

Description

Defines the CSS className to assign to the axis tick labels. Used in conjunction with EJSC.Axis.stagger_ticks and EJSC.Axis.size, this property allows for greater control over the size and staggering of tick labels on the top and bottom axes.

For styling the caption, see EJSC.Axis.caption class

Example

>> Style the axis tick labels grey, make them 24 pixels high to enable text wrapping and enable two levels of tick staggering.

4.3.1.1.14 major_ticks (inherited)

Definition

```
object major_ticks = {
    thickness: 1,
    size: 4,
    color: undefined,
    opacity: 100,
    show: true,
    count: undefined,
    offset: 0,
    min_interval: undefined,
    max_interval: undefined
}
```

Description

This set of properties defines the characteristics of the major ticks for a given axis.

thickness: the height or width (depending on axis orientation) of the tick mark

size: the amount the tick mark extends from the axis border, may be specified as a number or a string containing % for a percentage

color: the color of the tick marks, if left undefined this property inherits its value from EJSC.Axis.color

opacity: the opacity of the tick marks

show: specifies whether to draw the tick marks

count: the number of tick marks to draw, if left undefined the axis will determine the proper amount of ticks to draw automatically based on the range of data available to the axis

Note: This property is not compatible with text labels (i.e. x axis values are "Gizmos", "Widgets", instead of numbers)

offset: distance in pixels or percent from the axis border to begin drawing the tick marks, min_interval: Defines the minimum interval between major tick marks / labels. This will override the auto generation of ticks to cap the interval to the value when defined.

max_interval: Defines the maximum interval between major tick marks / labels. This will override the auto generation of ticks to cap the interval to the value when defined.

4.3.1.1.15 max_extreme (inherited)

Definition

float max extreme = undefined

Description

Defines the maximum value of the the axis. This will only affect the axis when set during chart creation and may be used to extend or truncate the value range displayed. To retrieve and set this value after the chart has been created, see EJSC.Axis.getExtremes and EJSC.Axis.setExtremes

Example

>> Force the axis range to extend beyond the data it contains

4.3.1.1.16 min_extreme (inherited)

Definition

float min = undefined

Description

Defines the minimum value of the the axis. This will only affect the axis when set during chart creation and may be used to extend or truncate the value range displayed. To retrieve and set this value after the chart has been created, see EJSC.Axis.getExtremes and EJSC.Axis.setExtremes

Example

>> Force the axis range to extend beyond the data it contains

```
var chart = new EJSC.Chart( "chart", {
```

4.3.1.1.17 minor_ticks (inherited)

Definition

```
object minor_ticks = {
    show: false,
    color: "rgb(0,0,0)",
    opacity: 20
    thickness: 1,
    count: 7,
    size: 4,
    offset: 0
}
```

Description

Defines the properties of the minor tick marks to be drawn on the axis. The color, opacity and thickness (width of ticks in pixels) properties define the style of the tick marks. The count property defines the number of tick marks to be drawn between each major tick mark. The size property defines the height of the ticks (in pixels or percent). The offset property defines the distance away from the axis the minor tick marks begin drawing.

Example

>> Display red minor tick marks on the bottom axis

4.3.1.1.18 size (inherited)

Definition

integer size = 20

Description

Defines the height of horizontal axes or width of vertical axes (in pixels) of the tick area. To fully enable staggered ticks on horizontal axes, set this property to a multiple of 20 (or axis tick height), i.e. two levels = 40, three levels = 60.

For additional control over the format of the labels, see the EJSC.Axis.label_class property.

Example

>> Make axis tick area twice as tall, enabling staggered ticks (default tick label height is 20 pixels)

```
var chart = new EJSC.Chart( "chart", {
```

```
axis_bottom: { size: 40 }
} );
4.3.1.1.19 stagger_ticks (inherited)
```

Definition

boolean stagger_ticks = true

Description

Determines whether the axis tick labels are staggered.

NOTE: This property is only applicable to horizontal axes (i.e. EJSC.Chart.axis_top and EJSC.Chart.axis_bottom)

Example

>> Disable tick staggering for the bottom axis

4.3.1.1.20 visible (inherited)

Definition

boolean visible = true

Description

Defines if the axis (containing axis caption and tick labels) should be displayed.

Example

>> Remove the bottom axis from the chart to allow additional room for data

Definition

```
object zero_plane = {
    color: "rgb(0,0,0)",
    show: false,
    opacity: 100,
    thickness: 1,
    coordinate: 0
}
```

Description

Defines the properties of the zero plane line to be drawn at 0 (or whatever the coordinate property is

set to). It is used to specify if the line should be shown as well as its color, thickness and opacity. The coordinate property allows the base of EJSC.BarSeries, EJSC.StackedBarSeries and EJSC.AreaSeries changed.

Example

>> Display a 2 pixel thick dark green line on the zero plane of the left axis

4.3.1.2 Methods

4.3.1.2.1 addBin (inherited)

Definition

void addBin(String label, boolean redraw)

Description

Adds a new static label to the axis and sets the appropriate flags if necessary to force the chart to draw using static labels (as opposed to a dynamic range based on series data).

This method is useful if there is a need to include bins which may not be part of any series added (i.e. chart labels should be "Apples", "Oranges", "Pears" but the series data only contains data pertaining to Apples and Pears).

If redraw is false, drawing will not occur immediately but will not be entirely prevented. Certain actions such as adding an additional series with redraw = true, or chart dimensions changing may still trigger the chart to draw. The default, if redraw is omitted is **true**.

Note:

Manually added bins may only be removed if there are no series currently utilizing them.

Example

>> Add bins in a specific order to ensure they appear the same each time the chart is loaded, regardless of the order in which they appear in the data.

4.3.1.2.2 getExtremes (inherited)

Definition

object getExtremes()

```
RETURNS:
```

{ min: float, max: float }

Description

Returns the current axis extreme values.

To set the extreme values, see EJSC.Axis.setExtremes

4.3.1.2.3 getZoom (inherited)

Definition

```
object getZoom( )

RETURNS:
{ min: float, max: float }
```

Description

Returns the current zoom coordinates for a given axis in chart units.

To set the zoom coordinates, see EJSC.Axis.setZoom

4.3.1.2.4 getZoomBoxCoordinates (inherited)

Definition

void getZoomBoxCoordinates()

```
RETURNS:
```

{ min: float, max: float }

Description

Returns the min and max values for a given axis of the current zoom box. These values are in chart coordinates, not pixels.

4.3.1.2.5 hide (inherited)

Definition

void hide()

Description

Hides the axis, resizes the chart area and redraws all visible series.

No effect if the axis is already hidden.

4.3.1.2.6 hideGrid (inherited)

Definition

void hideGrid(boolean redraw)

Description

Hides the background grid for a given axis and if redraw is omitted or true, redraws the chart

No effect if the grid is already hidden.

4.3.1.2.7 pixelToPoint (inherited)

Definition

float pixelToPoint(integer Pixel)

Description

Converts the pixel coordinate into chart units based on an axis. The result will be undefined if the pixel location is outside of the chart area.

4.3.1.2.8 pointToPixel (inherited)

Definition

```
integer pointToPixel( number coordinate )
object pointToPixel( number coordinate, boolean ignoreBounds )
object result: {
            p: integer,
                outsideBounds: boolean
}
```

Description

Converts the chart coordinates based on axis data into the appropriate pixel position for that point (x or y depending on the orientation of the axis)

When ignoreBounds is not specified or specified as undefined, the result will be NaN if the coordinate provided is outside the currently displayed range.

4.3.1.2.9 removeBin (inherited)

Definition

void removeBin(String label, boolean redraw)

Description

Removes a bin (static text label) from the axis.

If redraw is false, drawing will not occur immediately but will not be entirely prevented. Certain actions such as adding an additional series with redraw = true, or chart dimensions changing may still trigger the chart to draw. The default, if redraw is omitted is **true**.

Note:

Bins may only be removed using this method if they were added using EJSC.Axis.addBin and no series are currently utilizing them.

4.3.1.2.10 resetZoom (inherited)

Definition

void resetZoom()

Description

Resets the zoom for a given axis to use its extreme values for min and max (as if a user had double-clicked the chart or drawn the zoom rectangle anywhere but down and right)

4.3.1.2.11 setCaption (inherited)

Definition

void setCaption(string caption)

Description

Updates the axis caption. This method must be used to change the caption once the chart has been rendered. To set a default caption on creation, see EJSC.Axis.caption.

4.3.1.2.12 setCrosshair (inherited)

Definition

void **setCrosshair**(boolean visible, float coordinate, boolean fireEvent)

Description

This method may be used to hide, show and position the cursor position indicator. If the fireEvent parameter is set to true or left undefined the EJSC.Axis.onShowCrosshair or EJSC.Axis.onHideCrosshair events will fire.

4.3.1.2.13 setExtremes (inherited)

Definition

void setExtremes(float min, float max)

Description

Updates the manual extremes for the axis. Use this method if the series data does not span the range to be displayed on the chart or to limit 100% zoom to a range smaller than the series data.

Example

>> Series data only spans 18 hours on the bottom axis but the chart needs to display an entire day

```
var myChart = new EJSC.Chart( "chart" );
myChart.axis_bottom.setExtremes( 0, 86400000 );
```

4.3.1.2.14 setZoom (inherited)

Definition:

void setZoom(float min, float max)

Description

Sets the current zoom of the axis to the specified coordinates.

4.3.1.2.15 show (inherited)

Definition

void show()

Description

Shows the axis, resizes the chart area and redraws all visible series.

No effect if the axis is already visible.

4.3.1.2.16 showGrid (inherited)

Definition

void **showGrid**(boolean redraw)

Description

Shows the background grid for the axis and if redraw is omitted or true, redraws the chart.

No effect if the grid is already visible.

4.3.1.3 Events

4.3.1.3.1 onHideCrosshair (inherited)

Definition

void onHideCrosshair(EJSC.Axis axis, EJSC.Chart chart)

Description

Called when the axis crosshair is hidden by the chart. This can occur when the user moves their mouse outside of the chart area or when EJSC.Axis.setCrosshair is called, sending false for the visible parameter and true for the fireEvent parameter.

4.3.1.3.2 onHideCursorPosition (inherited)

Definition

void onHideCursorPosition(EJSC.Axis axis, EJSC.Chart chart)

Description

This event is fired when the cursor position indicator for an axis is hidden. This will occur when the user's mouse leaves the chart area.

4.3.1.3.3 onNeedsTicks (inherited)

Definition

array onNeedsTicks(float min, float max, EJSC.Axis axis, EJSC.Chart chart)

Description

This event is triggered whenever the axis ticks need to be redrawn / recalculated. It expects an array of [float y, string label] to be returned which defines exactly where to put the tick marks and labels. In addition, null may be returned in order to skip custom ticks for the current draw and use the chart's build in tick controls.

min: The current minimum value visible on the chart for the axis.

max: The current maximum y value visible on the chart for the axis.

axis: The axis which needs ticks.

chart: The chart that triggered the event.

Notes

- To use the label formatter already assigned to the axis, set label to null (i.e. [min, null])
- To use on an axis with bins (text instead of numbers), simply send in the bin (i.e. ["First Bin", null])

Example

A typical event handler may look like the following:

```
function doBottomAxisNeedsTicks(min, max, axis, chart) {
       // Display 3 tick marks, one at min, one at max and one directly in between
       var result = new Array();
       result.push( [min, null] );
       result.push( [min + ((max - min) / 2), null] );
       result.push([max, null]);
       // Given a chart with a min and max of 0 and 100, the resulting array looks like:
       //
             [0, null],
       //
             [50, null],
       11
             [100, null]
       //
       // ]
       return result;
```

4.3.1.3.4 onShowCrosshair (inherited)

Definition

void onShowCrosshair(float coordinate, EJSC.Axis axis, EJSC.Chart chart)

Description

Called when the axis crosshair is shown by the chart. This can occur when the user moves their mouse into the chart area or when EJSC.Axis.setCrosshair is called, sending true for the visible parameter and true for the fireEvent parameter.

4.3.1.3.5 onShowCursorPosition (inherited)

Definition

void onShowCursorPosition(float coordinate, EJSC.Axis axis, EJSC.Chart chart)

Description

Called when the cursor position indicator becomes visible or changes position on a given axis. This will occur when the user enters the chart area or moves their mouse within the chart area.

4.3.2 LogarithmicAxis

LogarithmicAxis may be created and assigned to any of the four chart axes in order to enable a logarithmic scale.

The constructor takes an optional set of object properties used to perform initial configuration.

Constructor

EJSC.LogarithmicAxis([object options])

Defining Properties and Events

LogarithmicAxis properties may be set individually after the chart has been initialized and/or the axis has been created or in batch using the options parameter during instantiation.

Setting properties individually

Setting properties in batch

```
color: "#F00"
});
```

4.3.2.1 Properties

4.3.2.1.1 background (inherited)

Definition

```
object background = {
          color: "#fff",
          opacity: 0,
          includeTitle: false
};
```

Description

Defines the color and opacity of the axis area background. Setting the includeTitle property to true will fill the axis caption area as well as the ticks. If opacity is set to 0, no fill will occur.

4.3.2.1.2 base

Definition

number base = 10

Description

The term "base" refers to the number which is set to incremental powers to determine the ticks on the axis.

The tick values, if base = b, would be b^x where x is the linear incremental power.

When base = 10, and your range is 10 - 10,000, the tick marks would be:

```
10^1 = 10

10^2 = 100

10^3 = 1,000

10^4 = 10,000
```

4.3.2.1.3 border (inherited)

Definition

Description

Defines the appearance of the axis side bordering the chart area. By default the border color inherits

the axis color property (EJSC.Axis.color)

Example

>> Provide a 2 pixel tall green border on the bottom axis.

4.3.2.1.4 caption (inherited)

Definition

```
string caption = "Axis"
```

Description

Defines the text to be displayed below or beside the axis.

For styling the caption, see EJSC.Axis.caption_class

Example

>> Customize the bottom axis caption.

```
var chart = new EJSC.Chart( "chart", {
                axis_bottom: { caption: "Year" }
} );
```

4.3.2.1.5 caption_class (inherited)

Definition

```
string caption_class = ""
```

Description

Defines the CSS className to assign to the axis caption.

For styling the tick labels, see EJSC.Axis.label_class

Example

>> Style the axis caption bold.

4.3.2.1.6 color (inherited)

Definition

```
string color = "#FFF"
```

Description

Defines the default color of the axis border and tick marks. If the sub properties such as minor_ticks.color, major_ticks.color, border.color are left undefined, they inherit the value set here.

Example

>> Color the axis border and tick marks red

```
var chart = new EJSC.Chart( "chart", {
          axis_bottom: { color: "#F00" }
} );
```

4.3.2.1.7 crosshair (inherited)

Definition

```
object crosshair = {
            show: false,
            color: "#F00"
}
```

Description

Defines if crosshair should be shown on the chart at the current mouse coordinates as they relate to the given axis. May be enabled and disabled for each axis independently. This is automatically disabled for all axes if EJSC.Chart.allow_interactivity is set to false.

Example

>> Show crosshair based on the bottom axis mouse position.

4.3.2.1.8 cursor_position (inherited)

Definition

```
object cursor_position = {
    show: false,
    color: "#F00",
    textColor: "#FFF",
    formatter: undefined,
    caption: undefined,
    className: undefined}
```

Description

Defines the display properties of the cursor position feature for an axis. These properties may be used to turn the cursor position indicator on and off as well as configure the styling and color.

show: determines whether or not to display the cursor position while the mouse is within the chart area

color: sets the background and line color

textColor: sets the text color

formatter: defines a formatter to use when displaying coordinates, if left undefined it will use the axis formatter

caption: defines text to use as a prefix to the current coordinate **className**: a CSS class name to be used for additional styling

Example

>> Turn on cursor position for the bottom axis and configure to display a related label

4.3.2.1.9 extremes_ticks (inherited)

Definition

boolean extremes_ticks = false

Description

Defines if the min and max values should be forced to land on the next tick mark.

Example

>> Force tick marks at the min and max coordinates of the bottom axis (left and right sides of the chart)

```
var chart = new EJSC.Chart( "chart", {
          axis_bottom: { extremes_ticks: true }
} );
```

4.3.2.1.10 force_static_points (inherited)

Definition

boolean force_static_points = false

Description

Defines if the chart should force ticks to match up to every point by converting the data to strings.

Example

>> Display every bottom axis data point, essentially disable auto axis scaling.

```
var chart = new EJSC.Chart( "chart", {
```

```
axis_bottom: { force_static_points: true }
} );
4.3.2.1.11 formatter (inherited)
```

Definition

EJSC.Formatter formatter = EJSC.Formatter

Description

Defines the formatter that will be used to format the tick marks on the axis before displaying them.

```
Types:
EJSC.DateFormatter
EJSC.NumberFormatter
EJSC.StringFormatter
```

Example

>> Display bottom axis tick labels as \$0.00

4.3.2.1.12 grid (inherited)

Definition

```
object grid = {
    thickness: 1,
    color: "rgb(230,230,230)",
    opacity: 100,
    show: true
}
```

Description

Defines the appearance and visibility of the grid drawn in the background.

Example

>> Do not draw the background grid for the top and right axes.

4.3.2.1.13 hint_caption

Definition

string hint_caption = "Value:"

Description

Defines the text to display in front of the axis-related value in the hint (leave blank to hide the value when displaying the hint).

Example

>> Customize the value label in the hint window

4.3.2.1.14 label_class (inherited)

Definition

```
string label class = ""
```

Description

Defines the CSS className to assign to the axis tick labels. Used in conjunction with EJSC.Axis.stagger_ticks and EJSC.Axis.size, this property allows for greater control over the size and staggering of tick labels on the top and bottom axes.

For styling the caption, see EJSC.Axis.caption_class

Example

>> Style the axis tick labels grey, make them 24 pixels high to enable text wrapping and enable two levels of tick staggering.

4.3.2.1.15 major_ticks (inherited)

Definition

```
object major_ticks = {
    thickness: 1,
    size: 4,
    color: undefined,
    opacity: 100,
    show: true,
    count: undefined,
    offset: 0,
```

```
min_interval: undefined,
    max_interval: undefined
}
```

Description

This set of properties defines the characteristics of the major ticks for a given axis.

thickness: the height or width (depending on axis orientation) of the tick mark size: the amount the tick mark extends from the axis border, may be specified as a number or a string containing % for a percentage

color: the color of the tick marks, if left undefined this property inherits its value from EJSC.Axis.color

opacity: the opacity of the tick marks

show: specifies whether to draw the tick marks

count: the number of tick marks to draw, if left undefined the axis will determine the proper amount of ticks to draw automatically based on the range of data available to the axis

Note: This property is not compatible with text labels (i.e. x axis values are "Gizmos", "Widgets", instead of numbers)

offset: distance in pixels or percent from the axis border to begin drawing the tick marks, min_interval: Defines the minimum interval between major tick marks / labels. This will override the auto generation of ticks to cap the interval to the value when defined.

max_interval: Defines the maximum interval between major tick marks / labels. This will override the auto generation of ticks to cap the interval to the value when defined.

4.3.2.1.16 max_extreme (inherited)

Definition

float max extreme = undefined

Description

Defines the maximum value of the the axis. This will only affect the axis when set during chart creation and may be used to extend or truncate the value range displayed. To retrieve and set this value after the chart has been created, see EJSC.Axis.getExtremes and EJSC.Axis.setExtremes

Example

>> Force the axis range to extend beyond the data it contains

4.3.2.1.17 min_extreme (inherited)

Definition

float min = undefined

Defines the minimum value of the the axis. This will only affect the axis when set during chart creation and may be used to extend or truncate the value range displayed. To retrieve and set this value after the chart has been created, see EJSC.Axis.getExtremes and EJSC.Axis.setExtremes

Example

>> Force the axis range to extend beyond the data it contains

4.3.2.1.18 minor_ticks (inherited)

Definition

```
object minor_ticks = {
    show: false,
    color: "rgb(0,0,0)",
    opacity: 20
    thickness: 1,
    count: 7,
    size: 4,
    offset: 0
}
```

Description

Defines the properties of the minor tick marks to be drawn on the axis. The color, opacity and thickness (width of ticks in pixels) properties define the style of the tick marks. The count property defines the number of tick marks to be drawn between each major tick mark. The size property defines the height of the ticks (in pixels or percent). The offset property defines the distance away from the axis the minor tick marks begin drawing.

Example

>> Display red minor tick marks on the bottom axis

4.3.2.1.19 size (inherited)

Definition

integer size = 20

Description

Defines the height of horizontal axes or width of vertical axes (in pixels) of the tick area. To fully enable staggered ticks on horizontal axes, set this property to a multiple of 20 (or axis tick height), i.e.

two levels = 40, three levels = 60.

For additional control over the format of the labels, see the EJSC.Axis.label_class property.

Example

>> Make axis tick area twice as tall, enabling staggered ticks (default tick label height is 20 pixels)

Definition

boolean stagger_ticks = true

Description

Determines whether the axis tick labels are staggered.

NOTE: This property is only applicable to horizontal axes (i.e. EJSC.Chart.axis_top and EJSC.Chart.axis_bottom)

Example

>> Disable tick staggering for the bottom axis

Definition

boolean visible = true

Description

Defines if the axis (containing axis caption and tick labels) should be displayed.

Example

>> Remove the bottom axis from the chart to allow additional room for data

Definition

```
object zero_plane = {
    color: "rgb(0,0,0)",
```

```
show: false,
opacity: 100,
thickness: 1,
coordinate: 0
```

Description

Defines the properties of the zero plane line to be drawn at 0 (or whatever the coordinate property is set to). It is used to specify if the line should be shown as well as its color, thickness and opacity. The coordinate property allows the base of EJSC.BarSeries, EJSC.StackedBarSeries and EJSC.AreaSeries changed.

Example

>> Display a 2 pixel thick dark green line on the zero plane of the left axis

4.3.2.2 Methods

4.3.2.2.1 addBin (inherited)

Definition

void addBin(String label, boolean redraw)

Description

Adds a new static label to the axis and sets the appropriate flags if necessary to force the chart to draw using static labels (as opposed to a dynamic range based on series data).

This method is useful if there is a need to include bins which may not be part of any series added (i.e. chart labels should be "Apples", "Oranges", "Pears" but the series data only contains data pertaining to Apples and Pears).

If redraw is false, drawing will not occur immediately but will not be entirely prevented. Certain actions such as adding an additional series with redraw = true, or chart dimensions changing may still trigger the chart to draw. The default, if redraw is omitted is **true**.

Note:

Manually added bins may only be removed if there are no series currently utilizing them.

Example

>> Add bins in a specific order to ensure they appear the same each time the chart is loaded, regardless of the order in which they appear in the data.

```
var myChart = new EJSC.Chart("chart");
myChart.axis_bottom.addBin("Salesman 1");
myChart.axis_bottom.addBin("Salesman 2");
myChart.axis_bottom.addBin("Salesman 3");
```

4.3.2.2.2 getExtremes (inherited)

Definition

```
object getExtremes()

RETURNS:
{ min: float, max: float }
```

Description

Returns the current axis extreme values.

To set the extreme values, see EJSC.Axis.setExtremes

4.3.2.2.3 getZoom (inherited)

Definition

```
object getZoom( )

RETURNS:
{ min: float, max: float }
```

Description

Returns the current zoom coordinates for a given axis in chart units.

To set the zoom coordinates, see EJSC.Axis.setZoom

4.3.2.2.4 getZoomBoxCoordinates (inherited)

Definition

```
void getZoomBoxCoordinates()
```

```
RETURNS:
```

{ min: float, max: float }

Description

Returns the min and max values for a given axis of the current zoom box. These values are in chart coordinates, not pixels.

4.3.2.2.5 hide (inherited)

Definition

void hide()

Hides the axis, resizes the chart area and redraws all visible series.

No effect if the axis is already hidden.

4.3.2.2.6 hideGrid (inherited)

Definition

void hideGrid(boolean redraw)

Description

Hides the background grid for a given axis and if redraw is omitted or true, redraws the chart

No effect if the grid is already hidden.

4.3.2.2.7 pixelToPoint (inherited)

Definition

float pixelToPoint(integer Pixel)

Description

Converts the pixel coordinate into chart units based on an axis. The result will be undefined if the pixel location is outside of the chart area.

4.3.2.2.8 pointToPixel (inherited)

Definition

```
integer pointToPixel( number coordinate )
object pointToPixel( number coordinate, boolean ignoreBounds )
object result: {
            p: integer,
                outsideBounds: boolean
}
```

Description

Converts the chart coordinates based on axis data into the appropriate pixel position for that point (x or y depending on the orientation of the axis)

When ignoreBounds is not specified or specified as undefined, the result will be NaN if the coordinate provided is outside the currently displayed range.

4.3.2.2.9 removeBin (inherited)

Definition

void removeBin(String label, boolean redraw)

Removes a bin (static text label) from the axis.

If redraw is false, drawing will not occur immediately but will not be entirely prevented. Certain actions such as adding an additional series with redraw = true, or chart dimensions changing may still trigger the chart to draw. The default, if redraw is omitted is **true**.

Note:

Bins may only be removed using this method if they were added using EJSC.Axis.addBin and no series are currently utilizing them.

4.3.2.2.10 resetZoom (inherited)

Definition

void resetZoom()

Description

Resets the zoom for a given axis to use its extreme values for min and max (as if a user had double-clicked the chart or drawn the zoom rectangle anywhere but down and right)

4.3.2.2.11 setCaption (inherited)

Definition

void setCaption(string caption)

Description

Updates the axis caption. This method must be used to change the caption once the chart has been rendered. To set a default caption on creation, see EJSC.Axis.caption.

4.3.2.2.12 setCrosshair (inherited)

Definition

void setCrosshair(boolean visible, float coordinate, boolean fireEvent)

Description

This method may be used to hide, show and position the cursor position indicator. If the fireEvent parameter is set to true or left undefined the EJSC.Axis.onShowCrosshair or EJSC.Axis.onHideCrosshair events will fire.

4.3.2.2.13 setExtremes (inherited)

Definition

void setExtremes(float min, float max)

Updates the manual extremes for the axis. Use this method if the series data does not span the range to be displayed on the chart or to limit 100% zoom to a range smaller than the series data.

Example

>> Series data only spans 18 hours on the bottom axis but the chart needs to display an entire day

```
var myChart = new EJSC.Chart( "chart" );
myChart.axis_bottom.setExtremes( 0, 86400000 );
```

4.3.2.2.14 setZoom (inherited)

Definition:

void setZoom(float min, float max)

Description

Sets the current zoom of the axis to the specified coordinates.

4.3.2.2.15 show (inherited)

Definition

void show()

Description

Shows the axis, resizes the chart area and redraws all visible series.

No effect if the axis is already visible.

4.3.2.2.16 showGrid (inherited)

Definition

void showGrid(boolean redraw)

Description

Shows the background grid for the axis and if redraw is omitted or true, redraws the chart.

No effect if the grid is already visible.

4.3.2.3 Events

4.3.2.3.1 onHideCrosshair (inherited)

Definition

void onHideCrosshair(EJSC.Axis axis, EJSC.Chart chart)

Called when the axis crosshair is hidden by the chart. This can occur when the user moves their mouse outside of the chart area or when EJSC.Axis.setCrosshair is called, sending false for the visible parameter and true for the fireEvent parameter.

4.3.2.3.2 onHideCursorPosition (inherited)

Definition

void onHideCursorPosition(EJSC.Axis axis, EJSC.Chart chart)

Description

This event is fired when the cursor position indicator for an axis is hidden. This will occur when the user's mouse leaves the chart area.

4.3.2.3.3 onNeedsTicks (inherited)

Definition

array onNeedsTicks(float min, float max, EJSC.Axis axis, EJSC.Chart chart)

Description

This event is triggered whenever the axis ticks need to be redrawn / recalculated. It expects an array of [float y, string label] to be returned which defines exactly where to put the tick marks and labels. In addition, null may be returned in order to skip custom ticks for the current draw and use the chart's build in tick controls.

min: The current minimum value visible on the chart for the axis.

max: The current maximum y value visible on the chart for the axis.

axis: The axis which needs ticks.

chart: The chart that triggered the event.

Notes

- To use the label formatter already assigned to the axis, set label to null (i.e. [min, null])
- To use on an axis with bins (text instead of numbers), simply send in the bin (i.e. ["First Bin", null])

Example

A typical event handler may look like the following:

```
function doBottomAxisNeedsTicks(min, max, axis, chart) {
    // Display 3 tick marks, one at min, one at max and one directly in between
    var result = new Array();

    result.push( [min, null] );
    result.push( [min + ((max - min) / 2), null] );
    result.push( [max, null] );

    // Given a chart with a min and max of 0 and 100, the resulting array looks like:
    // [
        // [0, null],
        // [50, null],
        // [100, null]
        // [100, null]
```

```
return result;
}
```

4.3.2.3.4 onShowCrosshair (inherited)

Definition

void onShowCrosshair(float coordinate, EJSC.Axis axis, EJSC.Chart chart)

Description

Called when the axis crosshair is shown by the chart. This can occur when the user moves their mouse into the chart area or when EJSC.Axis.setCrosshair is called, sending true for the visible parameter and true for the fireEvent parameter.

4.3.2.3.5 onShowCursorPosition (inherited)

Definition

void onShowCursorPosition(float coordinate, EJSC.Axis axis, EJSC.Chart chart)

Description

Called when the cursor position indicator becomes visible or changes position on a given axis. This will occur when the user enters the chart area or moves their mouse within the chart area.

4.3.3 DateAxis

DateAxis may be created and assigned to any of the four chart axes in order to enable a date scale.

The constructor takes an optional set of object properties used to perform initial configuration.

Constructor

Defining Properties and Events

DateAxis properties may be set individually after the chart has been initialized and/or the axis has been created or in batch using the options parameter during instantiation.

Setting properties individually

Setting properties in batch

4.3.3.1 Properties

4.3.3.1.1 background (inherited)

Definition

```
object background = {
      color: "#fff",
      opacity: 0,
      includeTitle: false
};
```

Description

Defines the color and opacity of the axis area background. Setting the includeTitle property to true will fill the axis caption area as well as the ticks. If opacity is set to 0, no fill will occur.

4.3.3.1.2 border (inherited)

Definition

```
object border = {
    thickness: 1,
    color: undefined,
    opacity: 100,
    show: true
}
```

Description

Defines the appearance of the axis side bordering the chart area. By default the border color inherits the axis color property (EJSC.Axis.color)

Example

>> Provide a 2 pixel tall green border on the bottom axis.

4.3.3.1.3 caption (inherited)

Definition

```
string caption = "Axis"
```

Description

Defines the text to be displayed below or beside the axis.

For styling the caption, see EJSC.Axis.caption_class

Example

>> Customize the bottom axis caption.

```
var chart = new EJSC.Chart( "chart", {
            axis_bottom: { caption: "Year" }
} );
```

4.3.3.1.4 caption_class (inherited)

Definition

```
string caption_class = ""
```

Description

Defines the CSS className to assign to the axis caption.

For styling the tick labels, see EJSC.Axis.label_class

Example

>> Style the axis caption bold.

4.3.3.1.5 color (inherited)

Definition

```
string color = "#FFF"
```

Description

Defines the default color of the axis border and tick marks. If the sub properties such as minor_ticks.color, major_ticks.color, border.color are left undefined, they inherit the value set here.

Example

>> Color the axis border and tick marks red

```
var chart = new EJSC.Chart( "chart", {
                axis_bottom: { color: "#F00" }
} );
```

4.3.3.1.6 crosshair (inherited)

Definition

```
object crosshair = {
            show: false,
            color: "#F00"
}
```

Description

Defines if crosshair should be shown on the chart at the current mouse coordinates as they relate to the given axis. May be enabled and disabled for each axis independently. This is automatically disabled for all axes if EJSC.Chart.allow interactivity is set to false.

Example

>> Show crosshair based on the bottom axis mouse position.

4.3.3.1.7 cursor_position (inherited)

Definition

```
object cursor_position = {
    show: false,
    color: "#F00",
    textColor: "#FFF",
    formatter: undefined,
    caption: undefined,
    className: undefined}
```

Description

Defines the display properties of the cursor position feature for an axis. These properties may be used to turn the cursor position indicator on and off as well as configure the styling and color.

show: determines whether or not to display the cursor position while the mouse is within the chart area

color: sets the background and line color

textColor: sets the text color

formatter: defines a formatter to use when displaying coordinates, if left undefined it will use the axis formatter

caption: defines text to use as a prefix to the current coordinate **className**: a CSS class name to be used for additional styling

Example

>> Turn on cursor position for the bottom axis and configure to display a related label

```
var chart = new EJSC.Chart( "chart", {
```

4.3.3.1.8 extreme_ticks (inherited)

Definition

boolean extremes_ticks = false

Description

Defines if the min and max values should be forced to land on the next tick mark.

Example

>> Force tick marks at the min and max coordinates of the bottom axis (left and right sides of the chart)

```
var chart = new EJSC.Chart( "chart", {
          axis_bottom: { extremes_ticks: true }
} );
```

4.3.3.1.9 force_static_points (inherited)

Definition

boolean force_static_points = false

Description

Defines if the chart should force ticks to match up to every point by converting the data to strings.

Example

>> Display every bottom axis data point, essentially disable auto axis scaling.

```
var chart = new EJSC.Chart( "chart", {
                axis_bottom: { force_static_points: true }
} );
```

4.3.3.1.10 formatters (inherited)

Definition

EJSC.Formatter formatter = EJSC.Formatter

Description

Defines the formatter that will be used to format the tick marks on the axis before displaying them.

```
Types: EJSC.DateFormatter
```

EJSC.NumberFormatter EJSC.StringFormatter

Example

>> Display bottom axis tick labels as \$0.00

4.3.3.1.11 grid (inherited)

Definition

```
object grid = {
    thickness: 1,
    color: "rgb(230,230,230)",
    opacity: 100,
    show: true
}
```

Description

Defines the appearance and visibility of the grid drawn in the background.

Example

>> Do not draw the background grid for the top and right axes.

4.3.3.1.12 label_class (inherited)

Definition

```
string label_class = ""
```

Description

Defines the CSS className to assign to the axis tick labels. Used in conjunction with EJSC.Axis.stagger_ticks and EJSC.Axis.size, this property allows for greater control over the size and staggering of tick labels on the top and bottom axes.

For styling the caption, see EJSC.Axis.caption_class

Example

>> Style the axis tick labels grey, make them 24 pixels high to enable text wrapping and enable two levels of tick staggering.

4.3.3.1.13 max_extreme (inherited)

Definition

float max_extreme = undefined

Description

Defines the maximum value of the the axis. This will only affect the axis when set during chart creation and may be used to extend or truncate the value range displayed. To retrieve and set this value after the chart has been created, see EJSC.Axis.getExtremes and EJSC.Axis.setExtremes

Example

>> Force the axis range to extend beyond the data it contains

4.3.3.1.14 major_ticks (inherited)

Definition

```
object major_ticks = {
    thickness: 1,
    size: 4,
    color: undefined,
    opacity: 100,
    show: true,
    increment: undefined,
    offset: 0
}
```

Description

This set of properties defines the characteristics of the major ticks for a given axis.

thickness: the height or width (depending on axis orientation) of the tick mark size: the amount the tick mark extends from the axis border, may be specified as a number or a string containing % for a percentage

color: the color of the tick marks, if left undefined this property inherits its value from EJSC.Axis.color

opacity: the opacity of the tick marks

show: specifies whether to draw the tick marks **increment**: (values: <u>regex</u>('([0-9](.*))[YMWDHNSZ]')) **offset**: distance in pixels or percent from the axis border to begin drawing the tick marks,

4.3.3.1.15 min_extreme (inherited)

Definition

float min = undefined

Description

Defines the minimum value of the the axis. This will only affect the axis when set during chart creation and may be used to extend or truncate the value range displayed. To retrieve and set this value after the chart has been created, see EJSC.Axis.getExtremes and EJSC.Axis.setExtremes

Example

>> Force the axis range to extend beyond the data it contains

4.3.3.1.16 minor_ticks (inherited)

Definition

```
object minor_ticks = {
    show: false,
    color: "rgb(0,0,0)",
    opacity: 20
    thickness: 1,
    count: 7,
    size: 4,
    offset: 0
}
```

Description

Defines the properties of the minor tick marks to be drawn on the axis. The color, opacity and thickness (width of ticks in pixels) properties define the style of the tick marks. The count property defines the number of tick marks to be drawn between each major tick mark. The size property defines the height of the ticks (in pixels or percent). The offset property defines the distance away from the axis the minor tick marks begin drawing.

Example

>> Display red minor tick marks on the bottom axis

```
var chart = new EJSC.Chart( "chart", {
          axis_bottom: {
```

```
minor_ticks: { show: true, color: "#FF0000" }
} );
4.3.3.1.17 size (inherited)
```

Definition

integer size = 20

Description

Defines the height of horizontal axes or width of vertical axes (in pixels) of the tick area. To fully enable staggered ticks on horizontal axes, set this property to a multiple of 20 (or axis tick height), i.e. two levels = 40, three levels = 60.

For additional control over the format of the labels, see the EJSC.Axis.label_class property.

Example

>> Make axis tick area twice as tall, enabling staggered ticks (default tick label height is 20 pixels)

```
var chart = new EJSC.Chart( "chart", {
          axis_bottom: { size: 40 }
} );
```

4.3.3.1.18 stagger_ticks (inherited)

Definition

boolean stagger_ticks = true

Description

Determines whether the axis tick labels are staggered.

NOTE: This property is only applicable to horizontal axes (i.e. EJSC.Chart.axis_top and EJSC.Chart.axis_bottom)

Example

>> Disable tick staggering for the bottom axis

```
var chart = new EJSC.Chart( "chart", {
          axis_bottom: { stagger_ticks: false }
} );
```

4.3.3.1.19 visible (inherited)

Definition

boolean visible = true

Description

Defines if the axis (containing axis caption and tick labels) should be displayed.

Example

>> Remove the bottom axis from the chart to allow additional room for data

```
var chart = new EJSC.Chart( "chart", {
          axis_bottom: { visible: false }
} );
```

4.3.3.1.20 zero_plane (inherited)

Definition

```
object zero_plane = {
        color: "rgb(0,0,0)",
        show: false,
        opacity: 100,
        thickness: 1,
        coordinate: 0
}
```

Description

Defines the properties of the zero plane line to be drawn at 0 (or whatever the coordinate property is set to). It is used to specify if the line should be shown as well as its color, thickness and opacity. The coordinate property allows the base of EJSC.BarSeries, EJSC.StackedBarSeries and EJSC.AreaSeries changed.

Example

>> Display a 2 pixel thick dark green line on the zero plane of the left axis

4.3.3.2 Methods

4.3.3.2.1 addBin (inherited)

Definition

void addBin(String label, boolean redraw)

Description

Adds a new static label to the axis and sets the appropriate flags if necessary to force the chart to draw using static labels (as opposed to a dynamic range based on series data).

This method is useful if there is a need to include bins which may not be part of any series added (i.e. chart labels should be "Apples", "Oranges", "Pears" but the series data only contains data pertaining to Apples and Pears).

If redraw is false, drawing will not occur immediately but will not be entirely prevented. Certain actions such as adding an additional series with redraw = true, or chart dimensions changing may still trigger the chart to draw. The default, if redraw is omitted is **true**.

Note:

Manually added bins may only be removed if there are no series currently utilizing them.

Example

>> Add bins in a specific order to ensure they appear the same each time the chart is loaded, regardless of the order in which they appear in the data.

4.3.3.2.2 getExtremes (inherited)

Definition

```
object getExtremes()

RETURNS:
{ min: float, max: float }
```

Description

Returns the current axis extreme values.

To set the extreme values, see EJSC.Axis.setExtremes

4.3.3.2.3 getZoom (inherited)

Definition

```
object getZoom()

RETURNS:
{ min: float, max: float }
```

Description

Returns the current zoom coordinates for a given axis in chart units.

To set the zoom coordinates, see EJSC.Axis.setZoom

4.3.3.2.4 getZoomBoxCoordinates (inherited)

Definition

```
void getZoomBoxCoordinates()
```

```
RETURNS: { min: float, max: float }
```

Description

Returns the min and max values for a given axis of the current zoom box. These values are in chart coordinates, not pixels.

4.3.3.2.5 hide (inherited)

Definition

void hide()

Description

Hides the axis, resizes the chart area and redraws all visible series.

No effect if the axis is already hidden.

4.3.3.2.6 hideGrid (inherited)

Definition

void hideGrid(boolean redraw)

Description

Hides the background grid for a given axis and if redraw is omitted or true, redraws the chart

No effect if the grid is already hidden.

4.3.3.2.7 pixelToPoint (inherited)

Definition

float pixelToPoint(integer Pixel)

Description

Converts the pixel coordinate into chart units based on an axis. The result will be undefined if the pixel location is outside of the chart area.

4.3.3.2.8 pointToPixel (inherited)

Definition

Converts the chart coordinates based on axis data into the appropriate pixel position for that point (x or y depending on the orientation of the axis)

When ignoreBounds is not specified or specified as undefined, the result will be NaN if the coordinate provided is outside the currently displayed range.

4.3.3.2.9 removeBin (inherited)

Definition

void removeBin(String label, boolean redraw)

Description

Removes a bin (static text label) from the axis.

If redraw is false, drawing will not occur immediately but will not be entirely prevented. Certain actions such as adding an additional series with redraw = true, or chart dimensions changing may still trigger the chart to draw. The default, if redraw is omitted is **true**.

Note:

Bins may only be removed using this method if they were added using EJSC.Axis.addBin and no series are currently utilizing them.

4.3.3.2.10 resetZoom (inherited)

Definition

void resetZoom()

Description

Resets the zoom for a given axis to use its extreme values for min and max (as if a user had double-clicked the chart or drawn the zoom rectangle anywhere but down and right)

4.3.3.2.11 setCaption (inherited)

Definition

void setCaption(string caption)

Description

Updates the axis caption. This method must be used to change the caption once the chart has been rendered. To set a default caption on creation, see EJSC.Axis.caption.

4.3.3.2.12 setCrosshair (inherited)

Definition

void setCrosshair(boolean visible, float coordinate, boolean fireEvent)

This method may be used to hide, show and position the cursor position indicator. If the fireEvent parameter is set to true or left undefined the EJSC.Axis.onShowCrosshair or EJSC.Axis.onHideCrosshair events will fire.

4.3.3.2.13 setExtremes (inherited)

Definition

void setExtremes(float min, float max)

Description

Updates the manual extremes for the axis. Use this method if the series data does not span the range to be displayed on the chart or to limit 100% zoom to a range smaller than the series data.

Example

>> Series data only spans 18 hours on the bottom axis but the chart needs to display an entire day

```
var myChart = new EJSC.Chart( "chart" );
myChart.axis_bottom.setExtremes( 0, 86400000 );
```

4.3.3.2.14 setZoom (inherited)

Definition:

void setZoom(float min, float max)

Description

Sets the current zoom of the axis to the specified coordinates.

4.3.3.2.15 show (inherited)

Definition

void show()

Description

Shows the axis, resizes the chart area and redraws all visible series.

No effect if the axis is already visible.

4.3.3.2.16 showGrid (inherited)

Definition

void showGrid(boolean redraw)

Shows the background grid for the axis and if redraw is omitted or true, redraws the chart.

No effect if the grid is already visible.

4.3.3.3 Events

4.3.3.3.1 onHideCrosshair (inherited)

Definition

void onHideCrosshair(EJSC.Axis axis, EJSC.Chart chart)

Description

Called when the axis crosshair is hidden by the chart. This can occur when the user moves their mouse outside of the chart area or when EJSC.Axis.setCrosshair is called, sending false for the visible parameter and true for the fireEvent parameter.

4.3.3.3.2 onHideCursorPosition (inherited)

Definition

void onHideCursorPosition(EJSC.Axis axis, EJSC.Chart chart)

Description

This event is fired when the cursor position indicator for an axis is hidden. This will occur when the user's mouse leaves the chart area.

4.3.3.3 onNeedsTicks (inherited)

Definition

array onNeedsTicks(float min, float max, EJSC.Axis axis, EJSC.Chart chart)

Description

This event is triggered whenever the axis ticks need to be redrawn / recalculated. It expects an array of [float y, string label] to be returned which defines exactly where to put the tick marks and labels. In addition, null may be returned in order to skip custom ticks for the current draw and use the chart's build in tick controls.

min: The current minimum value visible on the chart for the axis.

max: The current maximum y value visible on the chart for the axis.

axis: The axis which needs ticks.

chart: The chart that triggered the event.

Notes

- To use the label formatter already assigned to the axis, set label to null (i.e. [min, null])
- To use on an axis with bins (text instead of numbers), simply send in the bin (i.e. ["First Bin", null])

Example

A typical event handler may look like the following:

```
function doBottomAxisNeedsTicks(min, max, axis, chart) {
    // Display 3 tick marks, one at min, one at max and one directly in between
    var result = new Array();

    result.push( [min, null] );
    result.push( [min + ((max - min) / 2), null] );
    result.push( [max, null] );

    // Given a chart with a min and max of 0 and 100, the resulting array looks like:
    // [
        // [0, null],
        // [50, null],
        // [100, null]
        // ]
        return result;
}
```

4.3.3.3.4 onShowCrosshair (inherited)

Definition

void onShowCrosshair(float coordinate, EJSC.Axis axis, EJSC.Chart chart)

Description

Called when the axis crosshair is shown by the chart. This can occur when the user moves their mouse into the chart area or when EJSC.Axis.setCrosshair is called, sending true for the visible parameter and true for the fireEvent parameter.

4.3.3.3.5 onShowCursorPosition (inherited)

Definition

void onShowCursorPosition(float coordinate, EJSC.Axis axis, EJSC.Chart chart)

Description

Called when the cursor position indicator becomes visible or changes position on a given axis. This will occur when the user enters the chart area or moves their mouse within the chart area.

4.4 Series Types

4.4.1 EJSC.AlarmSeries



The AlarmSeries is rendered as a line denoting an alarm value, with an optional fill to denote an alarm range.

The constructor expects a value and an optional set of object properties.

Constructor

```
EJSC.AlarmSeries( value, {object options} )
```

Example

Defining Properties and Events

AlarmSeries properties may be set individually after the series has been created or in batch using the options parameter during instantiation.

Setting properties individually

```
var mySeries = new EJSC.AlarmSeries(10);
mySeries.title = "Alarm Series";
mySeries.opacity = 20;
mySeries.fill = 'down';
mySeries.fillTo = 2;
mySeries.flag = {visible:true};
mySeries.color = '#66cc66';
```

Setting properties in batch

```
var mySeries = new EJSC.AlarmSeries( 10, {
    title: "Alarm Series",
```

```
opacity: 20,
    fill: 'down',
    fillTo: 2,
    flag: {visible:true},
    color: '#66cc66',
} );
```

4.4.1.1 Properties

4.4.1.1.1 autosort (inherited)

Definition

boolean autosort = true

Description

Defines whether the series applies the appropriate sort to points prior to drawing. Drawing routines are generally optimized to accept data in a certain order and this property eliminates the need for the developer to worry about that order prior to sending data to the series. If set to false, the data must be properly ordered beforehand in order to ensure the series renders correctly.

Note: May not be applicable to all series (i.e. EJSC.PieSeries, EJSC.AnalogGaugeSeries)

4.4.1.1.2 axis

Definition

```
string axis = 'left'
```

Description

Defines the axis the alarm should display on.

Positions:

- top
- left
- bottom
- right

4.4.1.1.3 color (inherited)

Definition

string color = undefined

Description

Defines the series color. If left undefined, the color is pulled from the array of default colors stored in the chart.

Note: May not be applicable to all series (i.e. EJSC.PieSeries)

4.4.1.1.4 coloredLegend (inherited)

Definition

boolean coloredLegend = true

Description

Determines whether the legend text inherits the series color. Setting to false will allow the legend text to inherit its normal cascaded color. To modify this property after series creation see EJSC.Series.setColoredLegend()

4.4.1.1.5 delayLoad (inherited)

EXPERIMENTAL

Definition

boolean delayLoad = true

Description

This property allows a series to force its data handler to begin data retrieval as soon as it is added to a chart. When set to false, the series will initiate data retrieval as soon as it is added to a chart. When true, the data retrieval is initialized when the series first needs to draw.

4.4.1.1.6 fill

Definition

string fill = undefined

Description

Defines if the alarm should fill from the value up or down

Fill Positions:

- up
- down

4.4.1.1.7 fillTo

Definition

float fillTo = undefined

Description

Defines the value the alarm should fill to (if undefined, fills to the min/max of the axis)

4.4.1.1.8 flag

Definition

Description

Defines attributes for the flag attached to the alarm

Properties

```
Boolean
                         visible
                                                            - Defines if the flag is visible
string
                 axis
                                                   - ('same', 'opposite'): Defines if the flag should display
on the axis it's attached to or the opposite one
                 offset
                                                   - Defines the number of pixels to move the flag to
integer
make room if flags are too close
integer
                 opacity
                                                   - (0-100): The % opacity for the fill of the flag
                 fontColor
color
                                                   - The color to drag the text on the flag in
```

4.4.1.1.9 hint_string (inherited)

Definition

string hint_string = undefined

Description

This property may be used to define a series specific string to be used when displaying point hints. This string may contain replacement indicators (see Text Replacement Options). When left undefined, a default hint defined by the series type will be displayed.

Example

>> Modify the default hint to include custom text.

4.4.1.1.10 legendlsVisible (inherited)

Definition

boolean legendlsVisible = true

Description

Determines whether the legend item associated with the series appears in the legend window. Use the Series.showLegend and Series.hideLegend methods to control legend item visibility after series creation.

4.4.1.1.11 lineOpacity (inherited)

Definition

integer lineOpacity = 100

Description

Determines the line opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setLineOpacity()

4.4.1.1.12 lineWidth (inherited)

Definition

```
integer lineWidth = 1
```

Description

Defines the width of the line connecting series points.

4.4.1.1.13 opacity (inherited)

Definition

integer opacity = 50

Description

Determines the fill opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setOpacity()

4.4.1.1.14 padding (inherited)

Definition

```
object padding = {
    x_axis_min: undefined,
    x_axis_max: undefined,
    y_axis_min: undefined,
    y_axis_max: undefined
}
```

Description

The padding property may be used to override the series default padding. Padding is the amount of pixels added to the min and max series values in order to push the extremes and prevent the series from hitting the edge of the chart.

The amount of default padding is dependant upon the series type and axis configuration and may not be applicable to all series types.

This property is only applicable during series creation. To retrieve or modify the series padding after creation please see Series.getPadding() and Series.setPadding()

Example

>> Remove all padding from the BarSeries

Definition

string title = "Series <index>"

Description

Defines the series title used in hints and legend display.

Note: The default title of Series <index> (where <index> equals the current position in the series array for its owner chart) is assigned when a series is added to a chart using addSeries. This default title is only applied if the title is blank (i.e. "") at the time the addSeries method is called.

4.4.1.1.16 visible (inherited)

Definition

boolean visible = true

Description

Defines whether the series is visible and can draw on the chart

4.4.1.2 Methods

4.4.1.2.1 findClosestByPixel (inherited)

Definition

Description

Returns the point object closest to the screen pixel coordinates provided. The x and y properties of the

point object should be in the same scale as the x and y axes assigned to the series. To locate points based on pixel coordinates, see Series.findClosestByPixel()

4.4.1.2.2 findClosestByPoint (inherited)

Definition

Description

Returns the point object closest to the axis coordinates provided. The x and y properties of the coordinate object should be based on the top left of the viewport and take into account the page scroll. To locate points based on axis coordinates, see Series.findClosestByPoint()

4.4.1.2.3 getDataHandler (inherited)

Definition

EJSC.DataHandler getDataHandler()

Description

Returns the EJSC.DataHandler descendant currently assigned to the series. This is not applicable to all series and will return null if a data handler has not been defined or is not used.

4.4.1.2.4 getPadding (inherited)

Definition

Description

Returns an object containing the series current padding. If padding has been set either by the Series.setPadding() method of the Series.padding property during construction the result of this method will be adjusted to return the most current padding values.

4.4.1.2.5 getVisibility (inherited)

Definition

boolean getVisibility()

Description

Returns a boolean indicating the series current visible state

4.4.1.2.6 hide (inherited)

Definition

void hide()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already hidden.

4.4.1.2.7 hideLegend (inherited)

Definition

void hideLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already hidden.

4.4.1.2.8 reload (inherited)

Definition

void reload()

Description

Triggers a series reload if the functionality is defined in a child class. This may involve retrieving data again or simply recalculating. While the reload() method exists in the base Series class, implementation of the protected methods triggered by calling reload() is at the discretion of the child class.

4.4.1.2.9 setColor (inherited)

Definition

void setColor(string color)

Description

Changes the series color and causes the chart to redraw.

4.4.1.2.10 setColoredLegend (inherited)

Definition

void setColoredLegend(boolean coloredLegend)

Description

Sets the EJSC.Series.coloredLegend property and updates the legend to reflect the change.

4.4.1.2.11 setDataHandler (inherited)

Definition

void setDataHandler(EJSC.DataHandler dataHandler, boolean reload)

Description

Updates the series data handler and triggers a data reload if reload parameter is **true**. This method may not be implemented in all child classes.

4.4.1.2.12 setLineOpacity (inherited)

Definition

void setLineOpacity(integer opacity)

Description

Sets the EJSC.Series.lineOpacity property and redraws the series to reflect the change.

4.4.1.2.13 setLineWidth (inherited)

Definition

void setLineWidth(integer width)

Description

Updates the lineWidth property and redraws the chart.

4.4.1.2.14 setOpacity (inherited)

Definition

void setOpacity(integer opacity)

Description

Sets the EJSC.Series.opacity property and redraws the series to reflect the change.

4.4.1.2.15 setPadding (inherited)

Definition

void setPadding(object Padding, boolean Redraw)

The padding object should be defined as when used in the series constructor. See Series.padding.

Description

This method updates the user-defined series padding and optionally recalculates the chart extremes and redraws the chart.

4.4.1.2.16 setTitle (inherited)

Definition

void setTitle(string title)

Description

Changes the series title and update the legend caption (if applicable).

Note: this will not cause updates to a hint which is visible at the time it is called, though the next time a hint is rendered it will show the new property value.

4.4.1.2.17 show (inherited)

Definition

void show()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already visible.

4.4.1.2.18 showLegend (inherited)

Definition

void showLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already visible.

4.4.1.3 Events

4.4.1.3.1 onAfterDataAvailable (inherited)

Definition

boolean onAfterDataAvailable(EJSC.Chart chart, EJSC.Series series)

Description

Fired after the series has processed its data and before the chart is told to redraw. Returning **false** from this event handler will cancel redrawing the chart.

4.4.1.3.2 onAfterVisibilityChange (inherited)

Definition

boolean onAfterVisibilityChange(EJSC.Series series, EJSC.Chart chart, boolean visible)

Description

Fired when the series visibility changes. Sends series which changed, its owner chart and its new visible property value.

Returning false from this event handler will cancel redrawing the chart.

4.4.1.3.3 onBeforeVisibilityChange (inherited)

Definition

boolean onBeforeVisibilityChange(EJSC.Series series, EJSC.Chart chart)

Description

Fired before the series visibility is about to change. Sends series which changed, its owner chart. The current visible state of the series may be checked using the series.visible property.

Returning false from this event handler will cancel the change in visibility.

4.4.1.3.4 onShowHint (inherited)

Definition


string onShowHint(EJSC.Point point, EJSC.Series series, EJSC.Chart chart, string hint_string)

Description

Fired before the displaying the hint, this event allows the current hint string to be overridden. See Text Replacement Options for a list of the automatic substitutions available.

4.4.2 EJSC.AnalogGaugeSeries

Emprise JavaScript Charts





The AnalogGaugeSeries is rendered as a circular (or semi-circular) gauge with a needle directed towards the current value stored in its EJSC.GaugePoint.

The constructor expects an instantiated EJSC.DataHandler descendant and an optional set of object properties.

Constructor

```
EJSC.AnalogGaugeSeries( EJSC.DataHandler dataHandler [, object options] )
```

Example

Defining Properties and Events

AnalogGaugeSeries properties may be set individually after the series has been created or in batch using the options parameter during instantiation.

Setting properties individually

```
var mySeries = new EJSC.AnalogGaugeSeries(new EJSC.ArrayDataHandler([[50,"Gauge
Value"]]));
   mySeries.title = "New Analog Gauge Series";
   mySeries.min = 0;
   mySeries.max = 100;
```

Setting properties in batch

);

4.4.2.1 Properties

4.4.2.1.1 anchor

Definition

Description

Defines the parameters for the anchor on the gauge.

Properties

```
string color — Defines the color of the anchor.
integer opacity — Defines the opacity of the anchor.
integer size — Defines the diameter (in pixels) of the anchor.
```

4.4.2.1.2 axis

Definition

```
object axis = {
        color:
                                                'rgb(255,255,255)',
        innerBorderColor:
                                        'rgb(0,0,0)',
                                        100,
        innerBorderOpacity:
        innerBorderWidth:
                                        1,
        innerBorderVisible:
                                        true.
        opacity:
        outerBorderColor:
                                        'rgb(0,0,0)',
        outerBorderOpacity:
                                        100,
        outerBorderWidth:
                                        1,
        outerBorderVisible:
                                        true,
        thickness:
                                                15
}
```

Description

Defines the parameters for the axis on the gauge.

Properties

string the axis.	color	 Defines the background color of
string integer integer integer	innerBorderColor innerBorderOpacity innerBorderWidth innerBorderVisible	 Defines the color of the inner border. Defines the opacity of the inner border. Defines the width of the inner border. Defines whether the inner border is visible or not.

integer opacity background color of the axis.

outerBorderColor strina outerBorderOpacity integer outerBorderWidth integer

boolean outerBorderVisible

thickness integer

Defines the opacity of the

- Defines the color of the outer border.
- Defines the opacity of the outer border.
- Defines the width of the outer border.
- Defines whether the outer border is visible or not.
 - Defines the thickness of the axis.

4.4.2.1.3 delayLoad (inherited)

EXPERIMENTAL

Definition

boolean delayLoad = true

Description

This property allows a series to force its data handler to begin data retrieval as soon as it is added to a chart. When set to false, the series will initiate data retrieval as soon as it is added to a chart. When true, the data retrieval is initialized when the series first needs to draw.

4.4.2.1.4 fillColor

Definition

string fillColor = undefined

Description

Defines the background fill color of the gauge. Leave undefined for no fill color. This should be defined as rgb(<RED>,<GREEN>,<BLUE>), i.e. red = "rgb(255,0,0)"

4.4.2.1.5 fillOpacity

Definition

integer fillOpacity = 100

Description

Defines the opacity for the background fill color of the gauge.

4.4.2.1.6 height

Definition

string height = "100%"

Description

Defines the total height of the gauge. This may be specified in percent of the chart as shown above as the default value, or in exact pixels by specifying a number (i.e. height = 150;).

4.4.2.1.7 label

Definition

Description

Defines the parameters for the label on the gauge.

Properties

string className - Defines a class (to be defined in an attached stylesheet) to be applied to the label. textAlign - Defines the alignment of the text in the label ('left', 'center', string or 'right'). string position - Defines the position on the gauge the label will be placed (see below). - Defines the number of lines to display in the label. integer lines (Text will overflow unless otherwise specified in the attached style class).

Values for position:

- bottom
- centerBottom
- centerLeft
- centerRight
- centerTop
- left
- right
- top

4.4.2.1.8 legendIsVisible (inherited)

Definition

boolean legendlsVisible = true

Description

Determines whether the legend item associated with the series appears in the legend window. Use the Series.showLegend and Series.hideLegend methods to control legend item visibility after series creation.

4.4.2.1.9 lock

Definition

```
object lock = { color: 'rgb(0,0,0)',
```

```
offset: 5 ,
opacity: 100 ,
size: 6 ,
visible: false
```

}

Defines the parameters for the "locks", or "pegs" on the gauge.

Properties

string **color** – Defines the color of the locks.

integer offset – Defines the distance (in pixels) the needle is allow to extend past

the min/max value. Set to undefined to turn locks off.

integer **opacity** – Defines the opacity of the locks.

integer size — Defines the diameter (in pixels) of the locks.
boolean visible — Defines whether or not to visually show the locks.

4.4.2.1.10 marker_position

Definition

```
string marker_position = "outer"
```

Description

Defines where the tick markers will be positioned with respect to the axis.

Quadrants:

- outer
- inner

4.4.2.1.11 max

Definition

float max = 100

Description

Defines the maximum value to be displayed on the gauge.

4.4.2.1.12 min

Definition

float min = 0

Description

Defines the minimum value to be displayed on the gauge.

4.4.2.1.13 minorTick

Definition

```
object minorTick = {
            color: 'rgb(150,150,150)' ,
            count: 4 ,
            offset: 0 ,
            opacity: 100 ,
            size: 1 ,
            thickness: 15
}
```

Description

Defines the parameters for the minor ticks on the gauge.

Properties

```
string
                color
                                                 - Defines the color of the minor tick marks.
integer
                count
                                                 - Defines the number of minor tick marks to display
between each major tick mark.
                offset
                                                 - Defines the distance (in pixels) the minor tick marks
integer
are pushed out from the inner axis border.
integer
                opacity
                                                 - Defines the opacity of the minor tick marks.
integer
                size
                                                 - Defines the width (in pixels) of the minor tick
marks.
                thickness
                                        - Defines the thickness (in pixels) of the minor tick marks.
integer
```

4.4.2.1.14 needle

Definition

Description

Defines the parameters for the needle on the gauge.

Properties

string	borderColor	 Defines the color of the border.
integer	borderOpacity	 Defines the opacity of the border.
integer	borderWidth	 Defines the width of the border.
string	color	 Defines the background color of the needle.
integer	opacity	 Defines the opacity of the needle.
integer	size	 Defines the width (in pixels) of the needle at its
base.		` · · ·

4.4.2.1.15 position

Definition

```
string position = "center"
```

Description

Defines the quadrant of the chart that the gauge will appear in.

Quadrants:

- topLeft
- topCenter
- topRight
- centerLeft
- center
- centerRight
- bottomLeft
- bottomCenter
- bottomRight
- left
- right

4.4.2.1.16 range

Definition

```
object range = {
       borderColor:
                                'rgb(0,0,0)',
       borderOpacity:
                                100,
       borderWidth:
                                1,
       offset:
                                        0,
       opacity:
                                100,
       style:
                                        'doughnut',
       thickness:
                                15
}
```

Description

Defines the parameters for the ranges on the gauge.

Properties

string	borderColor	 Defines the color of the border.
integer	borderOpacity	 Defines the opacity of the border.
integer	borderWidth	 Defines the width of the border.
integer	offset	 Defines the distance (in pixels) the ranges are
pushed in from the axis.		
integer	opacity	 Defines the opacity of the ranges.
string	style	 Defines the style to draw the range in ('doughnut' or
'pie')		
integer	thickness	 Defines the thickness (in pixels) of the ranges.

4.4.2.1.17 range_degrees

Definition

```
integer range_degrees = 180
```

Description

Defines the total angle (in degrees) the gauge will take up.

4.4.2.1.18 ranges

Definition

```
array ranges = new Array();
```

Description

Defines a series of ranges to be marked in the gauge.

Implementation

```
mySeries.ranges = [ [ int min, int max, string color ] , ... ]
```

Example

```
mySeries.ranges = [
  [0,10,'rgb(255,0,0)'],
  [10,20,'rgb(0,255,0)']
];
```

4.4.2.1.19 start_degree

Definition

```
integer start_degree = 270
```

Description

Defines the angle (in degrees) at which the gauges' min value is displayed.

4.4.2.1.20 tick

Definition

Description

Defines the parameters for the major ticks on the gauge.

Properties

className - Defines a class (to be defined in an attached stylesheet) to string

be applied to the tick markers.

string color offset integer

pushed out from the inner axis border.

integer opacity

size integer thickness integer

- Defines the color of the tick marks.
- Defines the distance (in pixels) the tick marks are
- Defines the opacity of the tick marks.
- Defines the width (in pixels) of the tick marks.
- Defines the thickness (in pixels) of the tick marks.

4.4.2.1.21 tickCount

Definition

integer tickCount = 11

Description

Defines the number of major ticks to be displayed on the gauge's axis

4.4.2.1.22 title (inherited)

Definition

string title = "Series <index>"

Description

Defines the series title used in hints and legend display.

Note: The default title of Series <index> (where <index> equals the current position in the series array for its owner chart) is assigned when a series is added to a chart using addSeries. This default title is only applied if the title is blank (i.e. "") at the time the addSeries method is called.

4.4.2.1.23 visible (inherited)

Definition

boolean visible = true

Description

Defines whether the series is visible and can draw on the chart

4.4.2.1.24 width

Definition

string width = "100%"

Description

Defines the total width of the gauge. This may be specified in percent of the chart as shown above as the default value, or in exact pixels by specifying a number (i.e. width = 150;).

4.4.2.1.25 x_axis_formatter (inherited)

Definition

string x_axis_formatter = undefined

Description

Defines the formatter that will be used to format hints for the X values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

Types: EJSC.DateFormatter EJSC.NumberFormatter

4.4.2.2 Methods

4.4.2.2.1 getDataHandler (inherited)

Definition

EJSC.DataHandler getDataHandler()

Description

Returns the EJSC.DataHandler descendant currently assigned to the series. This is not applicable to all series and will return null if a data handler has not been defined or is not used.

4.4.2.2.2 getVisibility (inherited)

Definition

boolean getVisibility()

Description

Returns a boolean indicating the series current visible state

4.4.2.2.3 hide (inherited)

Definition

void hide()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already hidden.

4.4.2.2.4 hideLegend (inherited)

Definition

void hideLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already hidden.

4.4.2.2.5 reload (inherited)

Definition

void reload()

Description

Triggers a series reload if the functionality is defined in a child class. This may involve retrieving data again or simply recalculating. While the reload() method exists in the base Series class, implementation of the protected methods triggered by calling reload() is at the discretion of the child class.

4.4.2.2.6 setDataHandler (inherited)

Definition

void setDataHandler(EJSC.DataHandler dataHandler, boolean reload)

Description

Updates the series data handler and triggers a data reload if reload parameter is **true**. This method may not be implemented in all child classes.

4.4.2.2.7 setTitle (inherited)

Definition

void setTitle(string title)

Description

Changes the series title and update the legend caption (if applicable).

Note: this will not cause updates to a hint which is visible at the time it is called, though the next time a hint is rendered it will show the new property value.

4.4.2.2.8 show (inherited)

Definition

void show()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already visible.

4.4.2.2.9 showLegend (inherited)

Definition

void showLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already visible.

4.4.2.3 Events

4.4.2.3.1 onAfterDataAvailable (inherited)

Definition

boolean onAfterDataAvailable(EJSC.Chart chart, EJSC.Series series)

Description

Fired after the series has processed its data and before the chart is told to redraw. Returning **false** from this event handler will cancel redrawing the chart.

4.4.2.3.2 onAfterVisibilityChange (inherited)

Definition

boolean onAfterVisibilityChange(EJSC.Series series, EJSC.Chart chart, boolean visible)

Description

Fired when the series visibility changes. Sends series which changed, its owner chart and its new visible property value.

Returning false from this event handler will cancel redrawing the chart.

4.4.2.3.3 onBeforeVisibilityChange (inherited)

Definition

boolean onBeforeVisibilityChange(EJSC.Series series, EJSC.Chart chart)

Description

Fired before the series visibility is about to change. Sends series which changed, its owner chart. The current visible state of the series may be checked using the series visible property.

Returning false from this event handler will cancel the change in visibility.

4.4.2.4 Data Formats

The x parameter is required, label and userdata are both optional.

XML (EJSC.XMLDataHandler, EJSC.XMLStringDataHandler):

Unused parameters may be omitted

Full:

Compact: The values parameter is formatted as CSV

```
<G> <L values="CSV string"/> </G>
```

Array (EJSC.ArrayDataHandler):

```
[ "x", "label", "userdata"]
]

Null should be used to skip unused parameters:
[ "x", null, "userdata"]
]
```

CSV (EJSC.CSVFileDataHandler, EJSC.CSVStringDataHandler):

```
"x|label|userdata"
```

Null should be used to skip unused parameters


"x|null|userdata"

JSON (EJSC.JSONFileDataHandler, EJSC.JSONStringDataHandler):

Unused parameters may be omitted.

```
[{"x":"number or string","label":"string","userdata":"string"}]
```

4.4.3 EJSC.AreaSeries



AreaSeries is rendered by drawing a line from point to point and then filling the area defined.

The constructor expects an instantiated EJSC.DataHandler descendant and an optional set of object properties.

Constructor

```
EJSC.AreaSeries( EJSC.DataHandler dataHandler [, object options] )
```

Example

Defining Properties and Events

AreaSeries properties may be set individually after the series has been created or in batch using the options parameter during instantiation.

Setting properties individually

```
var mySeries = new EJSC.AreaSeries(new
EJSC.ArrayDataHandler([[1,1],[2,2],[3,3],[4,3],[5,2],[6,4]]));
   mySeries.lineWidth = 1;
   mySeries.title = "New Area Series";
```

Setting properties in batch

4.4.3.1 Properties

4.4.3.1.1 autosort (inherited)

Definition

boolean autosort = true

Description

Defines whether the series applies the appropriate sort to points prior to drawing. Drawing routines are generally optimized to accept data in a certain order and this property eliminates the need for the developer to worry about that order prior to sending data to the series. If set to false, the data must be properly ordered beforehand in order to ensure the series renders correctly.

Note: May not be applicable to all series (i.e. EJSC.PieSeries, EJSC.AnalogGaugeSeries)

4.4.3.1.2 closeLine

Definition

boolean closeLine = true

Description

Defines whether the line drawn around the area returns to the zero plane to create a complete shape (true) or if it drawn only through the points in the data set (false).

4.4.3.1.3 color (inherited)

Definition

string color = undefined

Description

Defines the series color. If left undefined, the color is pulled from the array of default colors stored in the chart.

Note: May not be applicable to all series (i.e. EJSC.PieSeries)

4.4.3.1.4 coloredLegend (inherited)

Definition

boolean coloredLegend = true

Description

Determines whether the legend text inherits the series color. Setting to false will allow the legend text to inherit its normal cascaded color. To modify this property after series creation see EJSC.Series.setColoredLegend()

4.4.3.1.5 delayLoad (inherited)

EXPERIMENTAL

Definition

boolean delayLoad = true

Description

This property allows a series to force its data handler to begin data retrieval as soon as it is added to a chart. When set to false, the series will initiate data retrieval as soon as it is added to a chart. When true, the data retrieval is initialized when the series first needs to draw.

4.4.3.1.6 drawPoints (inherited)

Definition

boolean drawPoints = false

Description

Determines whether the individual points in the series are visually indicated by round dots on the chart. The size and color of the fill and border are determined by the pointColor, pointSize, pointBorderColor and pointBorderSize properties.

Note: Setting this property to true for series which have a large number of points may impact performance as additional draws are required to render the points.

4.4.3.1.7 hint_string (inherited)

Definition

string hint_string = undefined

Description

This property may be used to define a series specific string to be used when displaying point hints. This string may contain replacement indicators (see Text Replacement Options). When left undefined, a default hint defined by the series type will be displayed.

Example

>> Modify the default hint to include custom text.

4.4.3.1.8 legendlsVisible (inherited)

Definition

boolean legendls Visible = true

Description

Determines whether the legend item associated with the series appears in the legend window. Use the Series.showLegend and Series.hideLegend methods to control legend item visibility after series creation.

4.4.3.1.9 lineOpacity (inherited)

Definition

integer lineOpacity = 100

Description

Determines the line opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setLineOpacity()

4.4.3.1.10 lineWidth (inherited)

Definition

integer lineWidth = 1

Description

Defines the width of the line connecting series points.

4.4.3.1.11 opacity (inherited)

Definition

integer opacity = 50

Description

Determines the fill opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setOpacity()

4.4.3.1.12 padding (inherited)

Definition

```
object padding = {
    x_axis_min: undefined,
    x_axis_max: undefined,
    y_axis_min: undefined,
    y_axis_max: undefined
}
```

Description

The padding property may be used to override the series default padding. Padding is the amount of pixels added to the min and max series values in order to push the extremes and prevent the series from hitting the edge of the chart.

The amount of default padding is dependant upon the series type and axis configuration and may not be applicable to all series types.

This property is only applicable during series creation. To retrieve or modify the series padding after creation please see Series.getPadding() and Series.setPadding()

Example

>> Remove all padding from the BarSeries

4.4.3.1.13 pointBorderColor (inherited)

Definition

```
string pointBorderColor = "rgb(255,255,255)"
```

Description

Defines the color of the border drawn around the points. This property is only applicable when the series drawPoints property is set to true and pointBorderSize is greater than 0.

4.4.3.1.14 pointBorderSize (inherited)

Definition

integer pointBorderSize = 0

Description

Defines the size in pixels of the border drawn around the points. This property is only applicable when

the series.drawPoints property is set to true.

To draw points without any border, leave pointBorderSize set to 0.

4.4.3.1.15 pointColor (inherited)

Definition

string pointColor = undefined

Description

Defines the color of the point (circle) drawn at each data point in the series. If left undefined the point will inherit the series color.

This property is only applicable when the series.drawPoints property is set to true.

4.4.3.1.16 pointSize (inherited)

Definition

integer pointSize = undefined

Description

Defines the size of the point (circle) drawn at each data point in the series. If left undefined the point diameter will be twice the line width of the series.

This property is only applicable when the series.drawPoints property is set to true.

4.4.3.1.17 title (inherited)

Definition

string title = "Series <index>"

Description

Defines the series title used in hints and legend display.

Note: The default title of Series <index> (where <index> equals the current position in the series array for its owner chart) is assigned when a series is added to a chart using addSeries. This default title is only applied if the title is blank (i.e. "") at the time the addSeries method is called.

4.4.3.1.18 visible (inherited)

Definition

boolean visible = true

Description

Defines whether the series is visible and can draw on the chart

4.4.3.1.19 x_axis (inherited)

Definition

```
string x_axis = "bottom"
```

Description

Defines the horizontal axis to use for X values. Valid options are "top" or "bottom".

4.4.3.1.20 x_axis_formatter (inherited)

Definition

```
string x_axis_formatter = undefined
```

Description

Defines the formatter that will be used to format hints for the X values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

Types: EJSC.DateFormatter EJSC.NumberFormatter

4.4.3.1.21 y_axis (inherited)

Definition

```
string y_axis = "left"
```

Description

Defines the vertical axis to use for Y values. Valid options are "left" or "right".

4.4.3.1.22 y_axis_formatter (inherited)

Definition

```
string y_axis_formatter = undefined
```

Description

Defines the formatter that will be used to format hints for the Y values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

Types: EJSC.DateFormatter EJSC.NumberFormatter

4.4.3.2 Methods

4.4.3.2.1 findClosestByPixel (inherited)

Definition

Description

Returns the point object closest to the screen pixel coordinates provided. The x and y properties of the point object should be in the same scale as the x and y axes assigned to the series. To locate points based on pixel coordinates, see Series.findClosestByPixel()

4.4.3.2.2 findClosestByPoint (inherited)

Definition

Description

Returns the point object closest to the axis coordinates provided. The x and y properties of the coordinate object should be based on the top left of the viewport and take into account the page scroll. To locate points based on axis coordinates, see Series.findClosestByPoint()

4.4.3.2.3 getDataHandler (inherited)

Definition

EJSC.DataHandler getDataHandler()

Description

Returns the EJSC.DataHandler descendant currently assigned to the series. This is not applicable to all series and will return null if a data handler has not been defined or is not used.

4.4.3.2.4 getPadding (inherited)

Definition

```
object getPadding()
```

Returns an object containing the series current padding. If padding has been set either by the Series.setPadding() method of the Series.padding property during construction the result of this method will be adjusted to return the most current padding values.

4.4.3.2.5 getVisibility (inherited)

Definition

boolean getVisibility()

Description

Returns a boolean indicating the series current visible state

4.4.3.2.6 hide (inherited)

Definition

void hide()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already hidden.

4.4.3.2.7 hideLegend (inherited)

Definition

void hideLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already hidden.

4.4.3.2.8 reload (inherited)

Definition

void reload()

Triggers a series reload if the functionality is defined in a child class. This may involve retrieving data again or simply recalculating. While the reload() method exists in the base Series class, implementation of the protected methods triggered by calling reload() is at the discretion of the child class.

4.4.3.2.9 setColor (inherited)

Definition

void setColor(string color)

Description

Changes the series color and causes the chart to redraw.

4.4.3.2.10 setColoredLegend (inherited)

Definition

void setColoredLegend(boolean coloredLegend)

Description

Sets the EJSC.Series.coloredLegend property and updates the legend to reflect the change.

4.4.3.2.11 setDataHandler (inherited)

Definition

void setDataHandler(EJSC.DataHandler dataHandler, boolean reload)

Description

Updates the series data handler and triggers a data reload if reload parameter is **true**. This method may not be implemented in all child classes.

4.4.3.2.12 setLineOpacity (inherited)

Definition

void setLineOpacity(integer opacity)

Description

Sets the EJSC.Series.lineOpacity property and redraws the series to reflect the change.

4.4.3.2.13 setLineWidth (inherited)

Definition

void setLineWidth(integer width)

Updates the lineWidth property and redraws the chart.

4.4.3.2.14 setOpacity (inherited)

Definition

void setOpacity(integer opacity)

Description

Sets the EJSC.Series.opacity property and redraws the series to reflect the change.

4.4.3.2.15 setPadding (inherited)

Definition

void setPadding(object Padding, boolean Redraw)

The padding object should be defined as when used in the series constructor. See Series.padding.

Description

This method updates the user-defined series padding and optionally recalculates the chart extremes and redraws the chart.

4.4.3.2.16 setTitle (inherited)

Definition

void setTitle(string title)

Description

Changes the series title and update the legend caption (if applicable).

Note: this will not cause updates to a hint which is visible at the time it is called, though the next time a hint is rendered it will show the new property value.

4.4.3.2.17 show (inherited)

Definition

void show()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already visible.

4.4.3.2.18 showLegend (inherited)

Definition

void showLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already visible.

4.4.3.3 Events

4.4.3.3.1 onAfterDataAvailable (inherited)

Definition

boolean onAfterDataAvailable(EJSC.Chart chart, EJSC.Series series)

Description

Fired after the series has processed its data and before the chart is told to redraw. Returning **false** from this event handler will cancel redrawing the chart.

4.4.3.3.2 onAfterVisibilityChange (inherited)

Definition

boolean onAfterVisibilityChange(EJSC.Series series, EJSC.Chart chart, boolean visible)

Description

Fired when the series visibility changes. Sends series which changed, its owner chart and its new visible property value.

Returning false from this event handler will cancel redrawing the chart.

4.4.3.3.3 onBeforeVisibilityChange (inherited)

Definition

boolean onBeforeVisibilityChange(EJSC.Series series, EJSC.Chart chart)

Description

Fired before the series visibility is about to change. Sends series which changed, its owner chart. The current visible state of the series may be checked using the series visible property.

Returning false from this event handler will cancel the change in visibility.

4.4.3.3.4 onShowHint (inherited)

Definition

string onShowHint(EJSC.Point point, EJSC.Series series, EJSC.Chart chart, string hint_string)

Description

Fired before the displaying the hint, this event allows the current hint string to be overridden. See Text Replacement Options for a list of the automatic substitutions available.

4.4.3.4 Data Formats

The x and y parameters are required, label and userdata are both optional.

XML (EJSC.XMLDataHandler, EJSC.XMLStringDataHandler):

Null should be used to skip unused parameters:

["x", "y", null, "userdata"],

Unused parameters may be omitted

Full:

[

```
<graph>
                                      <plot>
                                                      <point x="number or string" y="number</pre>
or string" label="string" userdata="string"/>
                                                      <point x="number or string" y="number</pre>
or string" label="string" userdata="string"/>
                                      </plot>
                       <graph>
       Short:
                       <G>
                                      <L>
                                                      <P x="number or string" y="number or
string" label="string" userdata="string"/>
                                                      <P x="number or string" y="number or
string" label="string" userdata="string"/>
                                      </L>
                       </G>
       Compact: The values parameter is formatted as CSV
                       <G>
                                      <L values="CSV string"/>
                       </G>
Array (EJSC.ArrayDataHandler):
       [
                       ["x", "y", "label", "userdata"],
                       ["x", "y", "label", "userdata"]
       1
```

```
["x", "y", null, "userdata"]
```

CSV (EJSC.CSVFileDataHandler, EJSC.CSVStringDataHandler):

"x|y|label|userdata,x|y|label|userdata"

Null should be used to skip unused parameters

"x|y|null|userdata,x|y|null|userdata"

JSON (EJSC.JSONFileDataHandler, EJSC.JSONStringDataHandler):


Unused parameters may be omitted.

4.4.3.5 Text Replacement Options

String	With
[chart_title]	title of the chart
series title	title of the series the selected
. – .	point resides in
[xaxis]	caption of the series x axis
[yaxis]	caption of the series y axis
[x]	preformatted X value of the
	point
[y]	preformatted Y value of the
	point
[label]	label property of the current
-	point
	•

14/-41

4.4.4 EJSC.BarSeries



BarSeries renders its points as vertical or horizontal bars which are fixed to a baseline.

The constructor expects an instantiated EJSC.DataHandler descendant and an optional set of object properties.

Constructor

```
EJSC.BarSeries( EJSC.DataHandler dataHandler [, object options] )
```

Example

Defining Properties and Events

BarSeries properties may be set individually after the series has been created or in batch using the options parameter during instantiation.

Setting properties individually

```
var mySeries = new EJSC.BarSeries(new
EJSC.ArrayDataHandler([[1,1],[2,2],[3,3],[4,3],[5,2],[6,4]]));
   mySeries.lineWidth = 1;
   mySeries.title = "New Bar Series";
```

Setting properties in batch

);

4.4.4.1 Properties

4.4.4.1.1 autosort (inherited)

Definition

boolean autosort = true

Description

Defines whether the series applies the appropriate sort to points prior to drawing. Drawing routines are generally optimized to accept data in a certain order and this property eliminates the need for the developer to worry about that order prior to sending data to the series. If set to false, the data must be properly ordered beforehand in order to ensure the series renders correctly.

Note: May not be applicable to all series (i.e. EJSC.PieSeries, EJSC.AnalogGaugeSeries)

4.4.4.1.2 color (inherited)

Definition

string color = undefined

Description

Defines the series color. If left undefined, the color is pulled from the array of default colors stored in the chart.

Note: May not be applicable to all series (i.e. EJSC.PieSeries)

4.4.4.1.3 coloredLegend (inherited)

Definition

boolean coloredLegend = true

Description

Determines whether the legend text inherits the series color. Setting to false will allow the legend text to inherit its normal cascaded color. To modify this property after series creation see EJSC.Series.setColoredLegend()

4.4.4.1.4 defaultColors

Definition

array **defaultColors** = EJSC.DefaultBarColors

Description

Defines the pool of default colors available for bar series bars.

NOTE: To make use of individually colored bars, the EJSC.BarSeries.useColorArray property must be set to true.

4.4.4.1.5 delayLoad (inherited)

EXPERIMENTAL

Definition

boolean delayLoad = true

Description

This property allows a series to force its data handler to begin data retrieval as soon as it is added to a chart. When set to false, the series will initiate data retrieval as soon as it is added to a chart. When true, the data retrieval is initialized when the series first needs to draw.

4.4.4.1.6 groupedBars

Definition

boolean groupedBars = true

Description

Defines whether the bars from different bar series in a single chart are grouped or overlayed.

NOTE: Only the first bar series added to the chart may use this property to affect the grouped/overlay display. To change the style after the first bar series has been added, use the EJSC.BarSeries.setGroupedBars from any bar series in the chart. Currently you cannot mix both overlayed and grouped bars within the same chart.

Example

>> Make the bar series overlay

4.4.4.1.7 hint_string (inherited)

Definition

string hint_string = undefined

Description

This property may be used to define a series specific string to be used when displaying point hints. This string may contain replacement indicators (see Text Replacement Options). When left undefined, a default hint defined by the series type will be displayed.

Example

>> Modify the default hint to include custom text.

4.4.4.1.8 intervalOffset

Definition

float intervalOffset = 0.8

Description

Defines the spacing between the bars as a percentage of 1. 1 = bars take up the entire width available, with their sides touching.

Example

>> Make the bars take up 1/2 their available width. (i.e. more space between bars than by default)

```
var chart = new EJSC.Chart("chart");
var bar = chart.addSeries(new EJSC.BarSeries(
    data,
    {
        intervalOffset: 0.5
    }
));
```

4.4.4.1.9 legendIsVisible (inherited)

Definition

boolean legendlsVisible = true

Description

Determines whether the legend item associated with the series appears in the legend window. Use the Series.showLegend and Series.hideLegend methods to control legend item visibility after series creation.

4.4.4.1.10 lineOpacity (inherited)

Definition

integer lineOpacity = 100

Description

Determines the line opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setLineOpacity()

4.4.4.1.11 lineWidth (inherited)

Definition

integer lineWidth = 1

Description

Defines the width of the line connecting series points.

4.4.4.1.12 opacity (inherited)

Definition

integer opacity = 50

Description

Determines the fill opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setOpacity()

4.4.4.1.13 padding (inherited)

Definition

```
object padding = {
    x_axis_min: undefined,
    x_axis_max: undefined,
    y_axis_min: undefined,
    y_axis_max: undefined
}
```

Description

The padding property may be used to override the series default padding. Padding is the amount of pixels added to the min and max series values in order to push the extremes and prevent the series from hitting the edge of the chart.

The amount of default padding is dependant upon the series type and axis configuration and may not be applicable to all series types.

This property is only applicable during series creation. To retrieve or modify the series padding after creation please see Series.getPadding() and Series.setPadding()

Example

>> Remove all padding from the BarSeries

4.4.4.1.14 orientation

Definition

string orientation = "vertical"

Description

This property determines the orientation of the bar series. The supported property values are "vertical" and "horizontal".

Note: Currently this is a creation-time only property and should not be changed after the series has been created.

4.4.4.1.15 ranges

Definition

```
array ranges = new Array()
```

Description

This property is used to store the ranges for a given bar series. The range objects are used to draw bars in varying styles based on their Y value.

The range objects stored are defined as:

Example

>> Define ranges so that bars with a Y value from 0 to 10 and 90 to 100 are colored red, bars 10 - 90 are colored green

4.4.4.1.16 title (inherited)

Definition

string title = "Series <index>"

Description

Defines the series title used in hints and legend display.

Note: The default title of Series <index> (where <index> equals the current position in the series array for its owner chart) is assigned when a series is added to a chart using addSeries. This default title is only applied if the title is blank (i.e. "") at the time the addSeries method is called.

4.4.4.1.17 treeLegend

Definition

boolean treeLegend = false

Description

Defines whether to display each bar individually in the legend.

If the useColorArray property is true and treeLegend left at its default (not defined in options), the treeLegend property will automatically be set to true to enable tree-style legend display.

4.4.4.1.18 useColorArray

Definition

boolean useColorArray = false

Description

Defines whether to make use of the EJSC.BarSeries.defaultColors property

Example

>> Use the color array to make a chart of multi colored bars

```
var chart = new EJSC.Chart("chart");
var bar = chart.addSeries(new EJSC.BarSeries(
    data,
    {
        useColorArray: true
    }
));
```

4.4.4.1.19 visible (inherited)

Definition

boolean visible = true

Description

Defines whether the series is visible and can draw on the chart

4.4.4.1.20 x_axis (inherited)

Definition

```
string x_axis = "bottom"
```

Description

Defines the horizontal axis to use for X values. Valid options are "top" or "bottom".

4.4.4.1.21 x_axis_formatter (inherited)

Definition

```
string x_axis_formatter = undefined
```

Description

Defines the formatter that will be used to format hints for the X values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

Types: EJSC.DateFormatter EJSC.NumberFormatter

4.4.4.1.22 y_axis (inherited)

Definition

```
string y_axis = "left"
```

Description

Defines the vertical axis to use for Y values. Valid options are "left" or "right".

4.4.4.1.23 y_axis_formatter (inherited)

Definition

```
string y_axis_formatter = undefined
```

Description

Defines the formatter that will be used to format hints for the Y values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

Types: EJSC.DateFormatter EJSC.NumberFormatter

4.4.4.2 Methods

4.4.4.2.1 addRange

Definition

void **addRange**(float min, float max, string color, integer opacity, integer lineOpacity, integer lineWidth, boolean redraw)

Description

Adds a new range to the bar series and optionally triggers a redraw.

4.4.4.2.2 clearRanges

Definition

void clearRanges (boolean redraw)

Description

Clears all ranges defined for the series and optionally redraws the the chart.

4.4.4.2.3 deleteRange

Definition

void deleteRange(float min, float max, boolean redraw)

Description

Deletes the matching range (min and max must exactly match an existing range) and optionally redraws the chart.

4.4.4.2.4 findClosestByPixel (inherited)

Definition

Description

Returns the point object closest to the screen pixel coordinates provided. The x and y properties of the point object should be in the same scale as the x and y axes assigned to the series. To locate points based on pixel coordinates, see Series.findClosestByPixel()

4.4.4.2.5 findClosestByPoint (inherited)

Definition

Description

Returns the point object closest to the axis coordinates provided. The x and y properties of the coordinate object should be based on the top left of the viewport and take into account the page scroll. To locate points based on axis coordinates, see Series.findClosestByPoint()

4.4.4.2.6 getBarSize

Definition

integer getBarSize()

Description

This method returns the size in pixels (width or height depending on orientation) of a single bar.

4.4.4.2.7 getBarSizeInPoints

Definition

integer getBarSizeInPoints()

Description

This method returns the size in chart points (width or height depending on orientation) of a single bar.

4.4.4.2.8 getDataHandler (inherited)

Definition

EJSC.DataHandler getDataHandler()

Description

Returns the EJSC.DataHandler descendant currently assigned to the series. This is not applicable to all series and will return null if a data handler has not been defined or is not used.

4.4.4.2.9 getPadding (inherited)

Definition

object getPadding()

Returns an object containing the series current padding. If padding has been set either by the Series.setPadding() method of the Series.padding property during construction the result of this method will be adjusted to return the most current padding values.

4.4.4.2.10 getPoints

Definition

array getPoints()

Description

This method returns an array of all EJSC.BarPoint objects in the series.

4.4.4.2.11 getVisibility (inherited)

Definition

boolean getVisibility()

Description

Returns a boolean indicating the series current visible state

4.4.4.2.12 hide (inherited)

Definition

void hide()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already hidden.

4.4.4.2.13 hideLegend (inherited)

Definition

void hideLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already hidden.

4.4.4.2.14 reload (inherited)

Definition

void reload()

Description

Triggers a series reload if the functionality is defined in a child class. This may involve retrieving data again or simply recalculating. While the reload() method exists in the base Series class, implementation of the protected methods triggered by calling reload() is at the discretion of the child class.

4.4.4.2.15 setColor (inherited)

Definition

void setColor(string color)

Description

Changes the series color and causes the chart to redraw.

4.4.4.2.16 setColoredLegend (inherited)

Definition

void setColoredLegend(boolean coloredLegend)

Description

Sets the EJSC.Series.coloredLegend property and updates the legend to reflect the change.

4.4.4.2.17 setDataHandler (inherited)

Definition

void setDataHandler(EJSC.DataHandler dataHandler, boolean reload)

Description

Updates the series data handler and triggers a data reload if reload parameter is **true**. This method may not be implemented in all child classes.

4.4.4.2.18 setDefaultColors

Definition

void setDefaultColors(array colors, boolean reload)

Set the array of default colors available for bar series bars.

If reload = **true** the bars (if loaded) will pull their colors from the given color array and the chart will be redrawn.

If onBarNeedsColor is assigned, this method will ignore that event and load the colors from the array.

Example

myBarSeries.setDefaultColors(colors, true);

4.4.4.2.19 setGroupedBars

Definition

void setGroupedBars(boolean grouped, boolean redraw)

Description

Changes the chart between grouped and overlayed bars and optionally triggers a redraw.

4.4.4.2.20 setIntervalOffset

Definition

void **setIntervalOffset**(float offset, boolean redraw)

Description

Updates the interval offset property (spacing between the bars) and optionally redraws the chart. See EJSC.BarSeries.intervalOffset for additional information.

4.4.4.2.21 setLineWidth (inherited)

Definition

void setLineWidth(integer width)

Description

Updates the lineWidth property and redraws the chart.

4.4.4.2.22 setOpacity (inherited)

Definition

void setOpacity(integer opacity)

Description

Sets the EJSC. Series opacity property and redraws the series to reflect the change.

4.4.4.2.23 setPadding (inherited)

Definition

void **setPadding**(object Padding, boolean Redraw)

The padding object should be defined as when used in the series constructor. See Series padding.

Description

This method updates the user-defined series padding and optionally recalculates the chart extremes and redraws the chart.

4.4.4.2.24 setTitle (inherited)

Definition

void setTitle(string title)

Description

Changes the series title and update the legend caption (if applicable).

Note: this will not cause updates to a hint which is visible at the time it is called, though the next time a hint is rendered it will show the new property value.

4.4.4.2.25 show (inherited)

Definition

void show()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already visible.

4.4.4.2.26 showLegend (inherited)

Definition

void showLegend()

Changes the series legend item visible state.

No effect if the series legend item is already visible.

4.4.4.3 Events

4.4.4.3.1 onAfterDataAvailable (inherited)

Definition

boolean onAfterDataAvailable(EJSC.Chart chart, EJSC.Series series)

Description

Fired after the series has processed its data and before the chart is told to redraw. Returning **false** from this event handler will cancel redrawing the chart.

4.4.4.3.2 onAfterVisibilityChange (inherited)

Definition

boolean onAfterVisibilityChange(EJSC.Series series, EJSC.Chart chart, boolean visible)

Description

Fired when the series visibility changes. Sends series which changed, its owner chart and its new visible property value.

Returning false from this event handler will cancel redrawing the chart.

4.4.4.3.3 onBarNeedsColor

Definition

```
string onBarNeedsColor( EJSC.BarPoint point, EJSC.Series series, EJSC.Chart chart ) object onBarNeedsColor( EJSC.BarPoint point, EJSC.Series series, EJSC.Chart chart )
```

Description

Fired when a bar needs a color. This event may return either a string (i.e. "rgb(0,255,0)") or an object with additional styling properties.

The object returned is expected to be formatted as:

```
{
    color: string, opacity: integer, lineWidth: integer
}
```

Example

>> Display bars with userdata of "bold" with thicker lines

4.4.4.3.4 onBeforeVisibilityChange (inherited)

Definition

boolean onBeforeVisibilityChange(EJSC.Series series, EJSC.Chart chart)

Description

Fired before the series visibility is about to change. Sends series which changed, its owner chart. The current visible state of the series may be checked using the series visible property.

Returning false from this event handler will cancel the change in visibility.

4.4.4.3.5 onShowHint (inherited)

Definition

string onShowHint(EJSC.Point point, EJSC.Series series, EJSC.Chart chart, string hint_string)

Description

Fired before the displaying the hint, this event allows the current hint string to be overridden. See Text Replacement Options for a list of the automatic substitutions available.

4.4.4.4 Data Formats

The x and y parameters are required, label and userdata are both optional.

XML (EJSC.XMLDataHandler, EJSC.XMLStringDataHandler):

Unused parameters may be omitted

Full:

<graph>

<plot>

or string" label="string" userdata="string"/>

<point x="number or string" y="number</pre>

<point x="number or string" y="number</pre>

```
or string" label="string" userdata="string"/>
                                     </plot>
                      <graph>
       Short:
                      <G>
                                     <L>
                                                   <P x="number or string" y="number or
string" label="string" userdata="string"/>
                                                   <P x="number or string" y="number or
string" label="string" userdata="string"/>
                                     </L>
                      </G>
       Compact: The values parameter is formatted as CSV
                      <G>
                                     <L values="CSV string"/>
                      </G>
Array (EJSC.ArrayDataHandler):
       [
                      ["x", "y", "label", "userdata"],
                      ["x", "y", "label", "userdata"]
       1
       Null should be used to skip unused parameters:
       [
                      ["x", "y", null, "userdata"],
                      ["x", "y", null, "userdata"]
       1
CSV (EJSC.CSVFileDataHandler, EJSC.CSVStringDataHandler):
       "x|y|label|userdata,x|y|label|userdata"
       Null should be used to skip unused parameters
       "x|y|null|userdata,x|y|null|userdata"
JSON (EJSC.JSONFileDataHandler, EJSC.JSONStringDataHandler):
       Unused parameters may be omitted.
       Ε
                      {"x":"number or string", "y": "number or
string", "label": "string", "userdata": "string"},
                      {"x":"number or string","y":"number or
string", "label": "string", "userdata": "string" }
```

]

4.4.4.5 Text Replacement Options

String	With
[chart_title]	title of the chart
[series_title]	title of the series the selected
. – .	point resides in
[xaxis]	caption of the series x axis
[yaxis] [x]	caption of the series y axis
[x]	preformatted X value of the
	point
[y]	preformatted Y value of the
	point
[label]	label property of the current
-	point
	•

4.4.5 EJSC.CandlestickSeries



CandlestickSeries renders its point data as vertical boxes with optional "wicks" to express open and close values.

The constructor expects an instantiated EJSC.DataHandler descendant and an optional set of object properties.

Constructor

```
EJSC.CandlestickSeries( EJSC.DataHandler dataHandler [, object options] )
```

Example

);

Defining Properties and Events

CandlestickSeries properties may be set individually after the series has been created or in batch using the options parameter during instantiation.

Setting properties individually

```
var mySeries = new EJSC.CandlestickSeries(new
EJSC.ArrayDataHandler([[1,10,1,2,9],[2,20,7,10,19]]));
   mySeries.lineWidth = 1;
   mySeries.title = "New Candlestick Series";
```

Setting properties in batch

4.4.5.1 Properties

4.4.5.1.1 autosort (inherited)

Definition

boolean autosort = true

Description

Defines whether the series applies the appropriate sort to points prior to drawing. Drawing routines are generally optimized to accept data in a certain order and this property eliminates the need for the developer to worry about that order prior to sending data to the series. If set to false, the data must be properly ordered beforehand in order to ensure the series renders correctly.

Note: May not be applicable to all series (i.e. EJSC.PieSeries, EJSC.AnalogGaugeSeries)

4.4.5.1.2 color (inherited)

Definition

string color = undefined

Description

Defines the series color. If left undefined, the color is pulled from the array of default colors stored in the chart.

Note: May not be applicable to all series (i.e. EJSC.PieSeries)

4.4.5.1.3 coloredLegend (inherited)

Definition

boolean coloredLegend = true

Description

Determines whether the legend text inherits the series color. Setting to false will allow the legend text to inherit its normal cascaded color. To modify this property after series creation see EJSC.Series.setColoredLegend()

4.4.5.1.4 delayLoad (inherited)

EXPERIMENTAL

Definition

boolean delayLoad = true

Description

This property allows a series to force its data handler to begin data retrieval as soon as it is added to a chart. When set to false, the series will initiate data retrieval as soon as it is added to a chart. When true, the data retrieval is initialized when the series first needs to draw.

4.4.5.1.5 gain

Definition

Description

Defines the appearance of the points which represent a gain.

Example

4.4.5.1.6 hint_string (inherited)

Definition

string hint_string = undefined

This property may be used to define a series specific string to be used when displaying point hints. This string may contain replacement indicators (see Text Replacement Options). When left undefined, a default hint defined by the series type will be displayed.

Example

>> Modify the default hint to include custom text.

4.4.5.1.7 intervalOffset

Definition

float intervalOffset = 0.8

Description

Defines the spacing between the points as a percentage of 1. 1 = points take up the entire width available, with their sides touching.

Example

```
var chart = new EJSC.Chart("chart");
var series = chart.addSeries(new EJSC.CandlestickSeries(
    data,
    {
        intervalOffset: 1
    }
));
```

4.4.5.1.8 legendIsVisible (inherited)

Definition

boolean legendls Visible = true

Description

Determines whether the legend item associated with the series appears in the legend window. Use the Series.showLegend and Series.hideLegend methods to control legend item visibility after series creation.

4.4.5.1.9 lineOpacity (inherited)

Definition

integer lineOpacity = 100

Description

Determines the line opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setLineOpacity()

4.4.5.1.10 lineWidth (inherited)

Definition

integer lineWidth = 1

Description

Defines the width of the line connecting series points.

4.4.5.1.11 loss

Definition

Description

Defines the appearance of the points which represent a loss.

Example

4.4.5.1.12 opacity (inherited)

Definition

integer opacity = 50

Description

Determines the fill opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setOpacity()

4.4.5.1.13 padding (inherited)

Definition

```
object padding = {
    x_axis_min: undefined,
    x_axis_max: undefined,
    y_axis_min: undefined,
    y_axis_max: undefined
}
```

Description

The padding property may be used to override the series default padding. Padding is the amount of pixels added to the min and max series values in order to push the extremes and prevent the series from hitting the edge of the chart.

The amount of default padding is dependent upon the series type and axis configuration and may not be applicable to all series types.

This property is only applicable during series creation. To retrieve or modify the series padding after creation please see Series.getPadding() and Series.setPadding()

Example

>> Remove all padding from the BarSeries

4.4.5.1.14 title (inherited)

Definition

```
string title = "Series <index>"
```

Description

Defines the series title used in hints and legend display.

Note: The default title of Series <index> (where <index> equals the current position in the series array for its owner chart) is assigned when a series is added to a chart using addSeries. This default title is only applied if the title is blank (i.e. "") at the time the addSeries method is called.

4.4.5.1.15 visible (inherited)

Definition

boolean visible = true

Defines whether the series is visible and can draw on the chart

4.4.5.1.16 x_axis (inherited)

Definition

```
string x_axis = "bottom"
```

Description

Defines the horizontal axis to use for X values. Valid options are "top" or "bottom".

4.4.5.1.17 x_axis_formatter (inherited)

Definition

```
string x_axis_formatter = undefined
```

Description

Defines the formatter that will be used to format hints for the X values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

Types: EJSC.DateFormatter EJSC.NumberFormatter

4.4.5.1.18 y_axis (inherited)

Definition

```
string y_axis = "left"
```

Description

Defines the vertical axis to use for Y values. Valid options are "left" or "right".

4.4.5.1.19 y_axis_formatter (inherited)

Definition

```
string y_axis_formatter = undefined
```

Description

Defines the formatter that will be used to format hints for the Y values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

Types: EJSC.DateFormatter EJSC.NumberFormatter

4.4.5.2 Methods

4.4.5.2.1 findClosestByPixel (inherited)

Definition

Description

Returns the point object closest to the screen pixel coordinates provided. The x and y properties of the point object should be in the same scale as the x and y axes assigned to the series. To locate points based on pixel coordinates, see Series.findClosestByPixel()

4.4.5.2.2 findClosestByPoint (inherited)

Definition

Description

Returns the point object closest to the axis coordinates provided. The x and y properties of the coordinate object should be based on the top left of the viewport and take into account the page scroll. To locate points based on axis coordinates, see Series.findClosestByPoint()

4.4.5.2.3 getDataHandler (inherited)

Definition

EJSC.DataHandler getDataHandler()

Description

Returns the EJSC.DataHandler descendant currently assigned to the series. This is not applicable to all series and will return null if a data handler has not been defined or is not used.

4.4.5.2.4 getPadding (inherited)

Definition

```
object getPadding()
```

Returns an object containing the series current padding. If padding has been set either by the Series.setPadding() method of the Series.padding property during construction the result of this method will be adjusted to return the most current padding values.

4.4.5.2.5 getVisibility (inherited)

Definition

boolean getVisibility()

Description

Returns a boolean indicating the series current visible state

4.4.5.2.6 hide (inherited)

Definition

void hide()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already hidden.

4.4.5.2.7 hideLegend (inherited)

Definition

void hideLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already hidden.

4.4.5.2.8 reload (inherited)

Definition

void reload()

Triggers a series reload if the functionality is defined in a child class. This may involve retrieving data again or simply recalculating. While the reload() method exists in the base Series class, implementation of the protected methods triggered by calling reload() is at the discretion of the child class.

4.4.5.2.9 setColor (inherited)

Definition

void setColor(string color)

Description

Changes the series color and causes the chart to redraw.

4.4.5.2.10 setColoredLegend (inherited)

Definition

void setColoredLegend(boolean coloredLegend)

Description

Sets the EJSC.Series.coloredLegend property and updates the legend to reflect the change.

4.4.5.2.11 setDataHandler (inherited)

Definition

void setDataHandler(EJSC.DataHandler dataHandler, boolean reload)

Description

Updates the series data handler and triggers a data reload if reload parameter is **true**. This method may not be implemented in all child classes.

4.4.5.2.12 setLineOpacity (inherited)

Definition

void setLineOpacity(integer opacity)

Description

Sets the EJSC.Series.lineOpacity property and redraws the series to reflect the change.

4.4.5.2.13 setLineWidth (inherited)

Definition

void setLineWidth(integer width)

Updates the lineWidth property and redraws the chart.

4.4.5.2.14 setOpacity (inherited)

Definition

void setOpacity(integer opacity)

Description

Sets the EJSC.Series.opacity property and redraws the series to reflect the change.

4.4.5.2.15 setPadding (inherited)

Definition

void setPadding(object Padding, boolean Redraw)

The padding object should be defined as when used in the series constructor. See Series padding.

Description

This method updates the user-defined series padding and optionally recalculates the chart extremes and redraws the chart.

4.4.5.2.16 setTitle (inherited)

Definition

void setTitle(string title)

Description

Changes the series title and update the legend caption (if applicable).

Note: this will not cause updates to a hint which is visible at the time it is called, though the next time a hint is rendered it will show the new property value.

4.4.5.2.17 show (inherited)

Definition

void show()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already visible.

4.4.5.2.18 showLegend (inherited)

Definition

void showLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already visible.

4.4.5.3 Events

4.4.5.3.1 onAfterDataAvailable (inherited)

Definition

boolean onAfterDataAvailable(EJSC.Chart chart, EJSC.Series series)

Description

Fired after the series has processed its data and before the chart is told to redraw. Returning **false** from this event handler will cancel redrawing the chart.

4.4.5.3.2 onAfterVisibilityChange (inherited)

Definition

boolean onAfterVisibilityChange(EJSC.Series series, EJSC.Chart chart, boolean visible)

Description

Fired when the series visibility changes. Sends series which changed, its owner chart and its new visible property value.

Returning false from this event handler will cancel redrawing the chart.

4.4.5.3.3 onBeforeVisibilityChange (inherited)

Definition

boolean onBeforeVisibilityChange(EJSC.Series series, EJSC.Chart chart)

Description

Fired before the series visibility is about to change. Sends series which changed, its owner chart. The current visible state of the series may be checked using the series visible property.

Returning false from this event handler will cancel the change in visibility.

4.4.5.3.4 onShowHint (inherited)

Definition

string onShowHint(EJSC.Point point, EJSC.Series series, EJSC.Chart chart, string hint_string)

Description

Fired before the displaying the hint, this event allows the current hint string to be overridden. See Text Replacement Options for a list of the automatic substitutions available.

4.4.5.4 Data Formats

```
XML (EJSC.XMLDataHandler, EJSC.XMLStringDataHandler):
       Unused parameters may be omitted
       Full:
                      <graph>
                                     <plot>
                                                    <point x="number or string"</pre>
high="number" low="number" open="number" close="number" label="string"
userdata="string"/>
                                                    <point x="number or string"</pre>
high="number" low="number" open="number" close="number" label="string"
userdata="string"/>
                                     </plot>
                      <graph>
       Short:
                      <G>
                                     <L>
                                                    <P x="number or string" high="number"
low="number" open="number" close="number" label="string" userdata="string"/>
                                                    <P x="number or string" high="number"
low="number" open="number" close="number" label="string" userdata="string"/>
                                     </L>
                      </G>
       Compact: The values parameter is formatted as CSV
                      <G>
                                     <L values="CSV string"/>
                      </G>
Array (EJSC.ArrayDataHandler):
       [
                      ["x", "high", "low", "open", "close", "label", "userdata"],
                      ["x", "high", "low", "open", "close", "label", "userdata"]
       1
       Null should be used to skip unused parameters:
```

[

```
["x", null, null, "open", "close", null, "userdata"], ["x", null, null, "open", "close", null, "userdata"]
```

CSV (EJSC.CSVFileDataHandler, EJSC.CSVStringDataHandler):

"x|high|low|open|close|label|userdata,x|high|low|open|close|label|userdata"

Null should be used to skip unused parameters

"x|null|null|open|close|null|userdata,x|null|null|open|close|null|userdata"

JSON (EJSC.JSONFileDataHandler, EJSC.JSONStringDataHandler):

Unused parameters may be omitted.

4.4.5.5 Text Replacement Options

String [chart_title] [series_title]	With title of the chart title of the series the selected
	point resides in
[xaxis] [yaxis] [x]	caption of the series x axis caption of the series y axis preformatted X value of the
	point
[high]	preformatted high value of the
ri 1	point
[low]	preformatted low value of the
[an an]	point proformatted ones value of
[open]	preformatted open value of
[close]	the point preformatted close value of
[close]	the point
[label]	label property of the current
frame - 1	point
	In the state of th

4.4.6 EJSC.DoughnutSeries

Emprise JavaScript Charts



The DoughnutSeries is rendered similar to the PieSeries, but with part of the center missing. You can use "Donut" instead of Doughnut for shorthand.

DoughnutSeries is rendered by drawing slices to form an ellipse. Each slice represents a percentage of the total of the sum of all point values in the dataset.

The constructor expects an instantiated EJSC.DataHandler descendant and an optional set of object properties.

Constructor

```
EJSC.DoughnutSeries( EJSC.DataHandler dataHandler [, object options] )
```

Example

Defining Properties and Events

DoughnutSeries properties may be set individually after the series has been created or in batch using the options parameter during instantiation.

Setting properties individually

```
var mySeries = new EJSC.PieSeries(new EJSC.ArrayDataHandler([[10,"Label 1"],[20,"Label
2"],[120,"Label 3"]]));
   mySeries.title = "New Doughnut Series";
```

Setting properties in batch

```
var mySeries = new EJSC.PieSeries(
```

4.4.6.1 Properties

4.4.6.1.1 defaultColors (inherited)

Definition

array defaultColors = EJSC.DefaultPieColors

Description

Defines the pool of default colors available for pie pieces.

4.4.6.1.2 delayLoad (inherited)

EXPERIMENTAL

Definition

boolean delayLoad = true

Description

This property allows a series to force its data handler to begin data retrieval as soon as it is added to a chart. When set to false, the series will initiate data retrieval as soon as it is added to a chart. When true, the data retrieval is initialized when the series first needs to draw.

4.4.6.1.3 doughnutOffset

Definition

float doughnutOffset = .5

Description

Float (0-1): Defines the amount of the radius that the <u>donut</u> inner radius should be (0 being like Pie, 1 being inner radius = outer radius)

4.4.6.1.4 height (inherited)

Definition

string **height** = "100%"

Description

Defines the total height of the pie series. This may be specified in percent of the chart as shown above as the default value, or in exact pixels by specifying a number (i.e. height = 150).

4.4.6.1.5 hint_string (inherited)

Definition

string hint_string = undefined

Description

This property may be used to define a series specific string to be used when displaying point hints. This string may contain replacement indicators (see Text Replacement Options). When left undefined, a default hint defined by the series type will be displayed.

Example

>> Modify the default hint to include custom text.

4.4.6.1.6 legendIsVisible (inherited)

Definition

boolean legendlsVisible = true

Description

Determines whether the legend item associated with the series appears in the legend window. Use the Series.showLegend and Series.hideLegend methods to control legend item visibility after series creation.

4.4.6.1.7 lineOpacity (inherited)

Definition

integer lineOpacity = 100

Description

Determines the line opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setLineOpacity()

4.4.6.1.8 lineWidth (inherited)

Definition

integer lineWidth = 1

Description

Defines the width of the line connecting series points.

4.4.6.1.9 opacity (inherited)

Definition

integer opacity = 50

Description

Determines the fill opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setOpacity()

4.4.6.1.10 position (inherited)

Definition

string **position** = "center"

Description

Defines the quadrant of the chart that the pie will appear in.

Quadrants:

- topLeft
- topCenter
- topRight
- centerLeft
- center
- centerRight
- bottomLeft
- bottomCenter
- bottomRight
- left
- right

4.4.6.1.11 title (inherited)

Definition

string title = "Series <index>"

Description

Defines the series title used in hints and legend display.

Note: The default title of Series <index> (where <index> equals the current position in the series array for its owner chart) is assigned when a series is added to a chart using addSeries. This default title is only applied if the title is blank (i.e. "") at the time the addSeries method is called.

4.4.6.1.12 total_value (inherited)

Definition

integer total_value = undefined

Description

Defines the total value (sum) of all pie pieces in the series. If left undefined, this value will be calculated automatically by adding all the piece values when the series data is loaded.

This property is only applicable during series creation. To determine or modify the total value once the series has been created use the getTotalValue and setTotalValue methods.

To force the chart to recalculate the total value based on actual series data, use the resetTotalValue method.

4.4.6.1.13 treeLegend (inherited)

Definition

boolean treeLegend = true

Description

Defines whether to display each pie piece individually in the legend.

4.4.6.1.14 visible (inherited)

Definition

boolean visible = true

Description

Defines whether the series is visible and can draw on the chart

4.4.6.1.15 width (inherited)

Definition

string width = "100%"

Description

Defines the total width of the pie series. This may be specified in percent of the chart as shown above as the default value, or in exact pixels by specifying a number (i.e. width = 150).

4.4.6.1.16 x_axis_formatter (inherited)

Definition

string x_axis_formatter = undefined

Description

Defines the formatter that will be used to format hints for the X values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

Types: EJSC.DateFormatter EJSC.NumberFormatter

4.4.6.2 Methods

4.4.6.2.1 findCenter (inherited)

Definition

object findCenter(EJSC.PiePoint point)

The object returned is formatted as:

```
{
    x: integer,
    y: integer
}
```

Description

This method takes a pie point (see getPoints) and returns an object containing the x and y screen coordinates of the piece's center.

4.4.6.2.2 findCenterOfCurve (inherited)

Definition

object findCenterOfCurve(EJSC.PiePoint point)

The object returned is formatted as:

```
{
    x: integer,
    y: integer
```

Description

This method takes a pie point (see getPoints) and returns an object containing the x and y screen coordinates of the center of the piece's arc.

4.4.6.2.3 getDataHandler (inherited)

Definition

EJSC.DataHandler getDataHandler()

Description

Returns the EJSC.DataHandler descendant currently assigned to the series. This is not applicable to all series and will return null if a data handler has not been defined or is not used.

4.4.6.2.4 getPoints (inherited)

Definition

array getPoints()

Description

This method returns an array of all EJSC.PiePoint objects in the series.

4.4.6.2.5 getTotalValue (inherited)

Definition

integer getTotalValue()

Description

Returns the current total value of the pie series. If the total_value property was set during creation or the setTotalValue has been called, the static value will be returned. If the series is set to calculate the total value based on the series data, the dynamic value will be returned.

4.4.6.2.6 getVisibility (inherited)

Definition

boolean getVisibility()

Description

Returns a boolean indicating the series current visible state

4.4.6.2.7 hide (inherited)

Definition

void hide()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already hidden.

4.4.6.2.8 hideLegend (inherited)

Definition

void hideLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already hidden.

4.4.6.2.9 reload (inherited)

Definition

void reload()

Description

Triggers a series reload if the functionality is defined in a child class. This may involve retrieving data again or simply recalculating. While the reload() method exists in the base Series class, implementation of the protected methods triggered by calling reload() is at the discretion of the child class.

4.4.6.2.10 resetTotalValue (inherited)

Definition

void resetTotalValue(boolean redraw)

Description

This method causes the series to recalculate its total value based on the actual series data and optionally redraws the series to reflect the change.

To retrieve the total value after this method is called, use getTotalValue.

4.4.6.2.11 setDataHandler (inherited)

Definition

void setDataHandler(EJSC.DataHandler dataHandler, boolean reload)

Description

Updates the series data handler and triggers a data reload if reload parameter is **true**. This method may not be implemented in all child classes.

4.4.6.2.12 setDefaultColors (inherited)

Definition

void setDefaultColors(array colors, boolean reload)

Description

Set the array of default colors available for pie pieces.

If reload = **true** the pie pieces (if loaded) will pull their colors from the given color array and the chart will be redrawn.

If onPieceNeedsColor is assigned, this method will ignore that event and load the colors from the array.

Example

Definition

void setLineOpacity(integer opacity)

Description

Sets the EJSC.Series.lineOpacity property and redraws the series to reflect the change.

4.4.6.2.14 setLineWidth (inherited)

Definition

void setLineWidth(integer width)

Description

Updates the lineWidth property and redraws the chart.

4.4.6.2.15 setOpacity (inherited)

Definition

void setOpacity(integer opacity)

Description

Sets the EJSC.Series.opacity property and redraws the series to reflect the change.

4.4.6.2.16 setTitle (inherited)

Definition

void setTitle(string title)

Description

Changes the series title and update the legend caption (if applicable).

Note: this will not cause updates to a hint which is visible at the time it is called, though the next time a hint is rendered it will show the new property value.

4.4.6.2.17 setTotalValue (inherited)

Definition

void setTotalValue(integer value, boolean redraw)

Description

Sets the total value of the pie series and optionally redraws the series to reflect the change.

To force the chart to calculate its total value based on the actual series data, call resetTotalValue.

4.4.6.2.18 show (inherited)

Definition

void show()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already visible.

4.4.6.2.19 showLegend (inherited)

Definition

void showLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already visible.

4.4.6.3 Events

4.4.6.3.1 onAfterDataAvailable (inherited)

Definition

boolean onAfterDataAvailable(EJSC.Chart chart, EJSC.Series series)

Description

Fired after the series has processed its data and before the chart is told to redraw. Returning **false** from this event handler will cancel redrawing the chart.

4.4.6.3.2 onAfterVisibilityChange (inherited)

Definition

boolean onAfterVisibilityChange(EJSC.Series series, EJSC.Chart chart, boolean visible)

Description

Fired when the series visibility changes. Sends series which changed, its owner chart and its new visible property value.

Returning **false** from this event handler will cancel redrawing the chart.

4.4.6.3.3 onBeforeVisibilityChange (inherited)

Definition

boolean onBeforeVisibilityChange(EJSC.Series series, EJSC.Chart chart)

Description

Fired before the series visibility is about to change. Sends series which changed, its owner chart. The current visible state of the series may be checked using the series visible property.

Returning false from this event handler will cancel the change in visibility.

4.4.6.3.4 onPieceNeedsColor (inherited)

Definition

boolean onPieceNeedsColor(EJSC.PiePoint point, EJSC.PieSeries series, EJSC.Chart chart)

Description

If assigned, this event is triggered for each piece in a pie series immediately before it pulls a color from the default colors array. The event provides the EJSC.PiePoint object which represents the piece which needs a color, the EJSC.PieSeries which owns the piece and the EJSC.Chart which owns the series. Return a color string formatted as "rgb(<red value>, <green value>, <blue value>)", i.e. Orange would be "rgb(237,173,0)"

4.4.6.3.5 onShowHint (inherited)

Definition

string onShowHint(EJSC.Point point, EJSC.Series series, EJSC.Chart chart, string hint_string)

Description

Fired before the displaying the hint, this event allows the current hint string to be overridden. See Text Replacement Options for a list of the automatic substitutions available.

4.4.6.4 Data Formats

The x parameter is required, label and userdata are both optional.

XML (EJSC.XMLDataHandler, EJSC.XMLStringDataHandler):

Unused parameters may be omitted


Full:

```
<graph>
                                      <plot>
                                                      <point x="number or string"</pre>
label="string" userdata="string"/>
                                                      <point x="number or string"</pre>
label="string" userdata="string"/>
                                      </plot>
                       <graph>
       Short:
                       <G>
                                      <L>
                                                      <P x="number or string" label="string"
userdata="string"/>
                                                      <P x="number or string" label="string"
userdata="string"/>
                                      </L>
                       </G>
       Compact: The values parameter is formatted as CSV
                       <G>
                                      <L values="CSV string"/>
                       </G>
Array (EJSC.ArrayDataHandler):
       [
                       ["x", "label", "userdata"],
                       ["x", "label", "userdata"]
       1
       Null should be used to skip unused parameters:
       [
                       ["x", null, "userdata"],
                       ["x", null, "userdata"]
       ]
CSV (EJSC.CSVFileDataHandler, EJSC.CSVStringDataHandler):
       "x|label|userdata,x|label|userdata"
       Null should be used to skip unused parameters
       "x|null|userdata,x|null|userdata"
JSON (EJSC.JSONFileDataHandler, EJSC.JSONStringDataHandler):
       Unused parameters may be omitted.
```

4.4.6.5 Text Replacement Options

String [chart_title] [series_title]	With title of the chart title of the series the selected
	point resides in
[x]	preformatted value of the
	point
[total]	total value represented by the
	sum of all piece values
[percent]	percent of the total value the
L 3	current point represents
[label]	label property of the current
[]	point
	-

4.4.7 EJSC.ErrorSeries



The ErrorSeries is rendered as a set of markers which may include an average (or expected) value, a high error, and a low error.

The average is denoted by a diamond while the errors are denoted by a "T". Connecting line(s) will be drawn between the average (if defined) and the error markers.

The constructor expects a value and an optional set of object properties.

Constructor

```
EJSC.ErrorSeries( EJSC.DataHandler dataHandler, {object options} )
```

Example

Defining Properties and Events

ErrorSeries properties may be set individually after the series has been created or in batch using the options parameter during instantiation.

Setting properties individually

```
var mySeries = new EJSC.ErrorSeries(new EJSC.ArrayDataHandler( [[0,0],[1,2],[2,1]] ) );
mySeries.title = "Error Series";
mySeries.capSize = 5;
mySeries.capDist = 6;
mySeries.avgSize = 1;
mySeries.orientation = 'horizontal';
```

Setting properties in batch

```
var mySeries = new EJSC.ErrorSeries(new EJSC.ArrayDataHandler( [[0,0],[1,2],[2,1]] ), {
    title: "Error Series",
    capSize: 5,
    capDist: 6,
    avgSize: 1,
    orientation: 'horizontal'
} );
```

4.4.7.1 Properties

4.4.7.1.1 avgSize

Definition

integer avgSize = 3

Description

Defines the radius of the average marker

4.4.7.1.2 autosort (inherited)

Definition

boolean autosort = true

Description

Defines whether the series applies the appropriate sort to points prior to drawing. Drawing routines are generally optimized to accept data in a certain order and this property eliminates the need for the

developer to worry about that order prior to sending data to the series. If set to false, the data must be properly ordered beforehand in order to ensure the series renders correctly.

Note: May not be applicable to all series (i.e. EJSC.PieSeries, EJSC.AnalogGaugeSeries)

4.4.7.1.3 capSize

Definition

integer capSize = 10

Description

Defines the length of the cap arms

4.4.7.1.4 capDist

Definition

integer capDist = 5

Description

Defines the length of the cap connector if average is NULL

4.4.7.1.5 color (inherited)

Definition

string color = undefined

Description

Defines the series color. If left undefined, the color is pulled from the array of default colors stored in the chart.

Note: May not be applicable to all series (i.e. EJSC.PieSeries)

4.4.7.1.6 coloredLegend (inherited)

Definition

boolean coloredLegend = true

Description

Determines whether the legend text inherits the series color. Setting to false will allow the legend text to inherit its normal cascaded color. To modify this property after series creation see EJSC.Series.setColoredLegend()

4.4.7.1.7 delayLoad (inherited)

EXPERIMENTAL

Definition

boolean delayLoad = true

Description

This property allows a series to force its data handler to begin data retrieval as soon as it is added to a chart. When set to false, the series will initiate data retrieval as soon as it is added to a chart. When true, the data retrieval is initialized when the series first needs to draw.

4.4.7.1.8 hint_string (inherited)

Definition

string hint_string = undefined

Description

This property may be used to define a series specific string to be used when displaying point hints. This string may contain replacement indicators (see Text Replacement Options). When left undefined, a default hint defined by the series type will be displayed.

Example

>> Modify the default hint to include custom text.

4.4.7.1.9 legendIsVisible (inherited)

Definition

boolean legendlsVisible = true

Description

Determines whether the legend item associated with the series appears in the legend window. Use the Series.showLegend and Series.hideLegend methods to control legend item visibility after series creation.

4.4.7.1.10 lineOpacity (inherited)

Definition

integer lineOpacity = 100

Description

Determines the line opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see

EJSC.Series.setLineOpacity()

4.4.7.1.11 lineWidth (inherited)

Definition

integer lineWidth = 1

Description

Defines the width of the line connecting series points.

4.4.7.1.12 orientation

Definition

string orientation = 'vertical'

Description

Defines the orientation of the bars

Options:

- vertical
- horizontal

4.4.7.1.13 opacity (inherited)

Definition

integer opacity = 50

Description

Determines the fill opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setOpacity()

4.4.7.1.14 padding (inherited)

Definition

```
object padding = {
    x_axis_min: undefined,
    x_axis_max: undefined,
    y_axis_min: undefined,
    y_axis_max: undefined
}
```

Description

The padding property may be used to override the series default padding. Padding is the amount of

pixels added to the min and max series values in order to push the extremes and prevent the series from hitting the edge of the chart.

The amount of default padding is dependent upon the series type and axis configuration and may not be applicable to all series types.

This property is only applicable during series creation. To retrieve or modify the series padding after creation please see Series.getPadding() and Series.setPadding()

Example

>> Remove all padding from the BarSeries

4.4.7.1.15 title (inherited)

Definition

string title = "Series <index>"

Description

Defines the series title used in hints and legend display.

Note: The default title of Series <index> (where <index> equals the current position in the series array for its owner chart) is assigned when a series is added to a chart using addSeries. This default title is only applied if the title is blank (i.e. "") at the time the addSeries method is called.

4.4.7.1.16 visible (inherited)

Definition

boolean visible = true

Description

Defines whether the series is visible and can draw on the chart

```
4.4.7.1.17 x_axis (inherited)
```

Definition

```
string x_axis = "bottom"
```

Description

Defines the horizontal axis to use for X values. Valid options are "top" or "bottom".

4.4.7.1.18 x_axis_formatter (inherited)

Definition

```
string x_axis_formatter = undefined
```

Description

Defines the formatter that will be used to format hints for the X values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

```
Types:
EJSC.DateFormatter
EJSC.NumberFormatter
```

4.4.7.1.19 y_axis (inherited)

Definition

```
string y_axis = "left"
```

Description

Defines the vertical axis to use for Y values. Valid options are "left" or "right".

4.4.7.1.20 y_axis_formatter (inherited)

Definition

```
string y_axis_formatter = undefined
```

Description

Defines the formatter that will be used to format hints for the Y values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

```
Types: EJSC.DateFormatter EJSC.NumberFormatter
```

4.4.7.2 Methods

4.4.7.2.1 findClosestByPixel (inherited)

Definition

Description

Returns the point object closest to the screen pixel coordinates provided. The x and y properties of the point object should be in the same scale as the x and y axes assigned to the series. To locate points based on pixel coordinates, see Series.findClosestByPixel()

4.4.7.2.2 findClosestByPoint (inherited)

Definition

Description

Returns the point object closest to the axis coordinates provided. The x and y properties of the coordinate object should be based on the top left of the viewport and take into account the page scroll. To locate points based on axis coordinates, see Series.findClosestByPoint()

4.4.7.2.3 getDataHandler (inherited)

Definition

EJSC.DataHandler getDataHandler()

Description

Returns the EJSC.DataHandler descendant currently assigned to the series. This is not applicable to all series and will return null if a data handler has not been defined or is not used.

4.4.7.2.4 getPadding (inherited)

Definition

Description

Returns an object containing the series current padding. If padding has been set either by the Series.setPadding() method of the Series.padding property during construction the result of this method will be adjusted to return the most current padding values.

4.4.7.2.5 getVisibility (inherited)

Definition

boolean getVisibility()

Description

Returns a boolean indicating the series current visible state

4.4.7.2.6 hide (inherited)

Definition

void hide()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already hidden.

4.4.7.2.7 hideLegend (inherited)

Definition

void hideLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already hidden.

4.4.7.2.8 reload (inherited)

Definition

void reload()

Description

Triggers a series reload if the functionality is defined in a child class. This may involve retrieving data again or simply recalculating. While the reload() method exists in the base Series class, implementation of the protected methods triggered by calling reload() is at the discretion of the child class.

4.4.7.2.9 setColor (inherited)

Definition

void setColor(string color)

Description

Changes the series color and causes the chart to redraw.

4.4.7.2.10 setColoredLegend (inherited)

Definition

void setColoredLegend(boolean coloredLegend)

Description

Sets the EJSC.Series.coloredLegend property and updates the legend to reflect the change.

4.4.7.2.11 setDataHandler (inherited)

Definition

void setDataHandler(EJSC.DataHandler dataHandler, boolean reload)

Description

Updates the series data handler and triggers a data reload if reload parameter is **true**. This method may not be implemented in all child classes.

4.4.7.2.12 setLineOpacity (inherited)

Definition

void setLineOpacity(integer opacity)

Description

Sets the EJSC.Series.lineOpacity property and redraws the series to reflect the change.

4.4.7.2.13 setLineWidth (inherited)

Definition

void setLineWidth(integer width)

Description

Updates the lineWidth property and redraws the chart.

4.4.7.2.14 setOpacity (inherited)

Definition

void setOpacity(integer opacity)

Description

Sets the EJSC.Series.opacity property and redraws the series to reflect the change.

4.4.7.2.15 setPadding (inherited)

Definition

void setPadding(object Padding, boolean Redraw)

The padding object should be defined as when used in the series constructor. See Series.padding.

Description

This method updates the user-defined series padding and optionally recalculates the chart extremes and redraws the chart.

4.4.7.2.16 setTitle (inherited)

Definition

void setTitle(string title)

Description

Changes the series title and update the legend caption (if applicable).

Note: this will not cause updates to a hint which is visible at the time it is called, though the next time a hint is rendered it will show the new property value.

4.4.7.2.17 show (inherited)

Definition

void show()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already visible.

4.4.7.2.18 showLegend (inherited)

Definition

void showLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already visible.

4.4.7.3 Events

4.4.7.3.1 onAfterDataAvailable (inherited)

Definition

boolean onAfterDataAvailable(EJSC.Chart chart, EJSC.Series series)

Description

Fired after the series has processed its data and before the chart is told to redraw. Returning **false** from this event handler will cancel redrawing the chart.

4.4.7.3.2 onAfterVisibilityChange (inherited)

Definition

boolean onAfterVisibilityChange(EJSC.Series series, EJSC.Chart chart, boolean visible)

Description

Fired when the series visibility changes. Sends series which changed, its owner chart and its new visible property value.

Returning false from this event handler will cancel redrawing the chart.

4.4.7.3.3 onBeforeVisibilityChange (inherited)

Definition

boolean onBeforeVisibilityChange(EJSC.Series series, EJSC.Chart chart)

Description

Fired before the series visibility is about to change. Sends series which changed, its owner chart. The current visible state of the series may be checked using the series visible property.

Returning false from this event handler will cancel the change in visibility.

4.4.7.3.4 onShowHint (inherited)

Definition

string onShowHint(EJSC.Point point, EJSC.Series series, EJSC.Chart chart, string hint_string)

Description

Fired before the displaying the hint, this event allows the current hint string to be overridden. See Text Replacement Options for a list of the automatic substitutions available.

4.4.8 EJSC.FloatingBarSeries



FloatingBarSeries renders its points as vertical or horizontal bars which are not fixed to a baseline.

The constructor expects an instantiated EJSC.DataHandler descendant and an optional set of object properties.

Constructor

```
EJSC.FloatingBarSeries( EJSC.DataHandler dataHandler [, object options])
```

Example

```
var mySeries = new EJSC.FloatingBarSeries(
    new EJSC.ArrayDataHandler([[1,1],[2,2],[3,3],[4,3],[5,2],[6,4]]),
    { title: "New Floating Bar Series" }
);
```

Defining Properties and Events

FloatingBarSeries properties may be set individually after the series has been created or in batch using the options parameter during instantiation.

Setting properties individually

```
var mySeries = new EJSC.FloatingBarSeries(new
EJSC.ArrayDataHandler([[1,1],[2,2],[3,3],[4,3],[5,2],[6,4]]));
   mySeries.lineWidth = 1;
   mySeries.title = "New Floating Bar Series";
```

Setting properties in batch

4.4.8.1 Properties

4.4.8.1.1 autosort (inherited)

Definition

boolean autosort = true

Description

Defines whether the series applies the appropriate sort to points prior to drawing. Drawing routines are generally optimized to accept data in a certain order and this property eliminates the need for the developer to worry about that order prior to sending data to the series. If set to false, the data must be properly ordered beforehand in order to ensure the series renders correctly.

Note: May not be applicable to all series (i.e. EJSC.PieSeries, EJSC.AnalogGaugeSeries)

4.4.8.1.2 color (inherited)

Definition

string color = undefined

Description

Defines the series color. If left undefined, the color is pulled from the array of default colors stored in the chart.

Note: May not be applicable to all series (i.e. EJSC.PieSeries)

4.4.8.1.3 coloredLegend (inherited)

Definition

boolean coloredLegend = true

Description

Determines whether the legend text inherits the series color. Setting to false will allow the legend text to inherit its normal cascaded color. To modify this property after series creation see EJSC.Series.setColoredLegend()

4.4.8.1.4 defaultColors (inherited)

Definition

array **defaultColors** = EJSC.DefaultBarColors

Description

Defines the pool of default colors available for bar series bars.

NOTE: To make use of individually colored bars, the EJSC.BarSeries.useColorArray property must be set to true.

4.4.8.1.5 delayLoad (inherited)

EXPERIMENTAL

Definition

boolean delayLoad = true

Description

This property allows a series to force its data handler to begin data retrieval as soon as it is added to a chart. When set to false, the series will initiate data retrieval as soon as it is added to a chart. When true, the data retrieval is initialized when the series first needs to draw.

4.4.8.1.6 groupedBars (inherited)

Definition

boolean groupedBars = true

Description

Defines whether the bars from different bar series in a single chart are grouped or overlayed.

NOTE: Only the first bar series added to the chart may use this property to affect the grouped/overlay display. To change the style after the first bar series has been added, use the EJSC.BarSeries.setGroupedBars from any bar series in the chart. Currently you cannot mix both overlayed and grouped bars within the same chart.

Example

>> Make the bar series overlay

4.4.8.1.7 hint_string (inherited)

Definition

string hint_string = undefined

Description

This property may be used to define a series specific string to be used when displaying point hints. This string may contain replacement indicators (see Text Replacement Options). When left undefined, a default hint defined by the series type will be displayed.

Example

>> Modify the default hint to include custom text.

4.4.8.1.8 intervalOffset (inherited)

Definition

float intervalOffset = 0.8

Description

Defines the spacing between the bars as a percentage of 1. 1 = bars take up the entire width available, with their sides touching.

Example

>> Make the bars take up 1/2 their available width. (i.e. more space between bars than by default)

```
var chart = new EJSC.Chart("chart");
var bar = chart.addSeries(new EJSC.BarSeries(
    data,
    {
        intervalOffset: 0.5
    }
));
```

4.4.8.1.9 legendIsVisible (inherited)

Definition

boolean legendlsVisible = true

Description

Determines whether the legend item associated with the series appears in the legend window. Use the Series.showLegend and Series.hideLegend methods to control legend item visibility after series creation.

4.4.8.1.10 lineOpacity (inherited)

Definition

integer lineOpacity = 100

Description

Determines the line opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setLineOpacity()

4.4.8.1.11 lineWidth (inherited)

Definition

integer lineWidth = 1

Description

Defines the width of the line connecting series points.

4.4.8.1.12 opacity (inherited)

Definition

integer opacity = 50

Description

Determines the fill opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setOpacity()

4.4.8.1.13 orientation (inherited)

Definition

string orientation = "vertical"

Description

This property determines the orientation of the bar series. The supported property values are "vertical" and "horizontal".

Note: Currently this is a creation-time only property and should not be changed after the series has been created.

4.4.8.1.14 padding (inherited)

Definition

```
object padding = {
    x_axis_min: undefined,
    x_axis_max: undefined,
    y_axis_min: undefined,
    y_axis_max: undefined
}
```

Description

The padding property may be used to override the series default padding. Padding is the amount of pixels added to the min and max series values in order to push the extremes and prevent the series from hitting the edge of the chart.

The amount of default padding is dependant upon the series type and axis configuration and may not be applicable to all series types.

This property is only applicable during series creation. To retrieve or modify the series padding after creation please see Series.getPadding() and Series.setPadding()

Example

>> Remove all padding from the BarSeries

4.4.8.1.15 ranges (inherited)

Definition

array ranges = new Array()

Description

This property is used to store the ranges for a given bar series. The range objects are used to draw bars in varying styles based on their Y value.

The range objects stored are defined as:

Example

>> Define ranges so that bars with a Y value from 0 to 10 and 90 to 100 are colored red, bars 10 - 90 are colored green

4.4.8.1.16 title (inherited)

Definition

string title = "Series <index>"

Description

Defines the series title used in hints and legend display.

Note: The default title of Series <index> (where <index> equals the current position in the series array for its owner chart) is assigned when a series is added to a chart using addSeries. This default title is only applied if the title is blank (i.e. "") at the time the addSeries method is called.

4.4.8.1.17 treeLegend (inherited)

Definition

boolean treeLegend = false

Description

Defines whether to display each bar individually in the legend.

If the useColorArray property is true and treeLegend left at its default (not defined in options), the treeLegend property will automatically be set to true to enable tree-style legend display.

4.4.8.1.18 useColorArray (inherited)

Definition

boolean useColorArray = false

Description

Defines whether to make use of the EJSC.BarSeries.defaultColors property

Example

>> Use the color array to make a chart of multi colored bars

```
var chart = new EJSC.Chart("chart");
var bar = chart.addSeries(new EJSC.BarSeries(
    data,
    {
        useColorArray: true
    }
));
```

4.4.8.1.19 visible (inherited)

Definition

boolean visible = true

Description

Defines whether the series is visible and can draw on the chart

4.4.8.1.20 x_axis (inherited)

Definition

string x_axis = "bottom"

Description

Defines the horizontal axis to use for X values. Valid options are "top" or "bottom".

4.4.8.1.21 x_axis_formatter (inherited)

Definition

string x_axis_formatter = undefined

Description

Defines the formatter that will be used to format hints for the X values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

Types: EJSC.DateFormatter EJSC.NumberFormatter

4.4.8.1.22 y_axis (inherited)

Definition

```
string y_axis = "left"
```

Description

Defines the vertical axis to use for Y values. Valid options are "left" or "right".

4.4.8.1.23 y_axis_formatter (inherited)

Definition

```
string y_axis_formatter = undefined
```

Description

Defines the formatter that will be used to format hints for the Y values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

Types: EJSC.DateFormatter EJSC.NumberFormatter

4.4.8.2 Methods

4.4.8.2.1 addRange (inherited)

Definition

void **addRange**(float min, float max, string color, integer opacity, integer lineOpacity, integer lineWidth, boolean redraw)

Description

Adds a new range to the bar series and optionally triggers a redraw.

4.4.8.2.2 clearRanges (inherited)

Definition

void clearRanges (boolean redraw)

Description

Clears all ranges defined for the series and optionally redraws the the chart.

4.4.8.2.3 deleteRange (inherited)

Definition

void deleteRange(float min, float max, boolean redraw)

Description

Deletes the matching range (min and max must exactly match an existing range) and optionally redraws the chart.

4.4.8.2.4 findClosestByPixel (inherited)

Definition

Description

Returns the point object closest to the screen pixel coordinates provided. The x and y properties of the point object should be in the same scale as the x and y axes assigned to the series. To locate points based on pixel coordinates, see Series.findClosestByPixel()

4.4.8.2.5 findClosestByPoint (inherited)

Definition

Description

Returns the point object closest to the axis coordinates provided. The x and y properties of the coordinate object should be based on the top left of the viewport and take into account the page scroll. To locate points based on axis coordinates, see Series.findClosestByPoint()

4.4.8.2.6 getBarSize (inherited)

Definition

integer getBarSize()

Description

This method returns the size in pixels (width or height depending on orientation) of a single bar.

4.4.8.2.7 getBarSizeInPoints (inherited)

Definition

integer getBarSizeInPoints()

Description

This method returns the size in chart points (width or height depending on orientation) of a single bar.

4.4.8.2.8 getDataHandler (inherited)

Definition

EJSC.DataHandler getDataHandler()

Description

Returns the EJSC.DataHandler descendant currently assigned to the series. This is not applicable to all series and will return null if a data handler has not been defined or is not used.

4.4.8.2.9 getPadding (inherited)

Definition

object getPadding()

Description

Returns an object containing the series current padding. If padding has been set either by the Series.setPadding() method of the Series.padding property during construction the result of this method will be adjusted to return the most current padding values.

4.4.8.2.10 getPoints (inherited)

Definition

array getPoints()

Description

This method returns an array of all EJSC.BarPoint objects in the series.

4.4.8.2.11 getVisibility (inherited)

4.4.8.2.12 hide (inherited)

Definition

void hide()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already hidden.

4.4.8.2.13 hideLegend (inherited)

Definition

void hideLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already hidden.

4.4.8.2.14 reload (inherited)

Definition

void reload()

Description

Triggers a series reload if the functionality is defined in a child class. This may involve retrieving data again or simply recalculating. While the reload() method exists in the base Series class, implementation of the protected methods triggered by calling reload() is at the discretion of the child class.

4.4.8.2.15 setColor (inherited)

Definition

void setColor(string color)

Description

Changes the series color and causes the chart to redraw.

4.4.8.2.16 setColoredLegend (inherited)

Definition

void setColoredLegend(boolean coloredLegend)

Description

Sets the EJSC.Series.coloredLegend property and updates the legend to reflect the change.

4.4.8.2.17 setDataHandler (inherited)

Definition

void setDataHandler(EJSC.DataHandler dataHandler, boolean reload)

Description

Updates the series data handler and triggers a data reload if reload parameter is **true**. This method may not be implemented in all child classes.

4.4.8.2.18 setDefaultColors (inherited)

Definition

void setDefaultColors(array colors, boolean reload)

Description

Set the array of default colors available for bar series bars.

If reload = **true** the bars (if loaded) will pull their colors from the given color array and the chart will be redrawn.

If onBarNeedsColor is assigned, this method will ignore that event and load the colors from the array.

Example

myBarSeries.setDefaultColors(colors, true);

4.4.8.2.19 setIntervalOffset (inherited)

Definition

void setIntervalOffset(float offset, boolean redraw)

Description

Updates the interval offset property (spacing between the bars) and optionally redraws the chart. See EJSC.BarSeries.intervalOffset for additional information.

4.4.8.2.20 setLineWidth (inherited)

Definition

void setLineWidth(integer width)

Description

Updates the lineWidth property and redraws the chart.

4.4.8.2.21 setOpacity (inherited)

Definition

void setOpacity(integer opacity)

Description

Sets the EJSC.Series.opacity property and redraws the series to reflect the change.

4.4.8.2.22 setPadding (inherited)

Definition

void **setPadding**(object Padding, boolean Redraw)

The padding object should be defined as when used in the series constructor. See Series padding.

Description

This method updates the user-defined series padding and optionally recalculates the chart extremes and redraws the chart.

4.4.8.2.23 setTitle (inherited)

Definition

void setTitle(string title)

Description

Changes the series title and update the legend caption (if applicable).

Note: this will not cause updates to a hint which is visible at the time it is called, though the next time a hint is rendered it will show the new property value.

4.4.8.2.24 show (inherited)

Definition

void show()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already visible.

4.4.8.2.25 showLegend (inherited)

Definition

void showLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already visible.

4.4.8.3 Events

4.4.8.3.1 onAfterDataAvailable (inherited)

Definition

boolean onAfterDataAvailable(EJSC.Chart chart, EJSC.Series series)

Description

Fired after the series has processed its data and before the chart is told to redraw. Returning **false** from this event handler will cancel redrawing the chart.

4.4.8.3.2 onAfterVisibilityChange (inherited)

Definition

boolean onAfterVisibilityChange(EJSC.Series series, EJSC.Chart chart, boolean visible)

Description

Fired when the series visibility changes. Sends series which changed, its owner chart and its new visible property value.

Returning false from this event handler will cancel redrawing the chart.

4.4.8.3.3 onBarNeedsColor (inherited)

Definition

```
string onBarNeedsColor( EJSC.BarPoint point, EJSC.Series series, EJSC.Chart chart ) object onBarNeedsColor( EJSC.BarPoint point, EJSC.Series series, EJSC.Chart chart )
```

Description

Fired when a bar needs a color. This event may return either a string (i.e. "rgb(0,255,0)") or an object with additional styling properties.

The object returned is expected to be formatted as:

```
{
    color: string, opacity: integer, lineOpacity: integer, lineWidth: integer
}
```

Example

>> Display bars with userdata of "bold" with thicker lines

```
var chart = new EJSC.Chart("chart");
var bar = chart.addSeries(new EJSC.BarSeries( data, {
    lineOpacity: 80,
    lineWidth: 1,
    onBarNeedsColor: function(point, series, chart) {

    if (point.userdata == "bold") {
        return {
            color: "rgb(0,0,0)",
            opacity: 100,
            lineOpacity: 100,
            lineOpacity: 100,
            lineWidth: 100
        };
    } else {
        return "rgb(128,128,128)";
    }
}));
```

4.4.8.3.4 onBeforeVisibilityChange (inherited)

Definition

boolean onBeforeVisibilityChange(EJSC.Series series, EJSC.Chart chart)

Description

Fired before the series visibility is about to change. Sends series which changed, its owner chart. The current visible state of the series may be checked using the series visible property.

Returning false from this event handler will cancel the change in visibility.

XML (EJSC.XMLDataHandler, EJSC.XMLStringDataHandler):

Unused parameters may be omitted

4.4.8.3.5 onShowHint (inherited)

Definition

string onShowHint(EJSC.Point point, EJSC.Series series, EJSC.Chart chart, string hint_string)

Description

Fired before the displaying the hint, this event allows the current hint string to be overridden. See Text Replacement Options for a list of the automatic substitutions available.

4.4.8.4 Data Formats

```
Full:
                       Orientation == "vertical"
                       <graph>
                                       <plot>
                                                      <point x="number or string"</pre>
min="number" max="number" label="string" userdata="string"/>
                                                      <point x="number or string"</pre>
min="number" max="number" label="string" userdata="string"/>
                                       </plot>
                       <graph>
                       Orientation == "horizontal"
                       <graph>
                                       <plot>
                                                       <point y="number or string"</pre>
min="number" max="number" label="string" userdata="string"/>
                                                       <point y="number or string"</pre>
```

</plot>

Short:

Orientation == "vertical"

min="number" max="number" label="string" userdata="string"/>

<graph>


```
<G>
                                     <L>
                                                    <P x="number or string" min="number"
max="number" label="string" userdata="string"/>
                                                    <P x="number or string" min="number"
max="number" label="string" userdata="string"/>
                                     </L>
                      <G>
                      Orientation == "horizontal"
                      <G>
                                     <L>
                                                    <P x="number or string" min="number"
max="number" label="string" userdata="string"/>
                                                    <P x="number or string" min="number"
max="number" label="string" userdata="string"/>
                                     </L>
                      <G>
       Compact: The values parameter is formatted as CSV
                      <G>
                                     <L values="CSV string"/>
                      </G>
Array (EJSC.ArrayDataHandler):
       [
                      ["x or y", "min", "max", "label", "userdata"],
                      ["x or y", "min", "max", "label", "userdata"]
       1
       Null should be used to skip unused parameters:
       [
                      ["x or y", min, max, null, "userdata"],
                      ["x or y", min, max, null, "userdata"]
       1
CSV (EJSC.CSVFileDataHandler, EJSC.CSVStringDataHandler):
       "x or y|min|max|label|userdata,x or y|min|max||label|userdata"
       Null should be used to skip unused parameters
       "x or y|min|max|null|userdata,x or y|min|max|null|userdata"
JSON (EJSC.JSONFileDataHandler, EJSC.JSONStringDataHandler):
       Unused parameters may be omitted.
```

label":"string","userdata":"string"}

4.4.8.5 Text Replacement Options

String	With
[chart_title]	title of the chart
[series_title]	title of the series the selected
	point resides in
[xaxis]	caption of the series x axis
[yaxis]	caption of the series y axis
[x]	preformatted X value of the
	point
[y]	preformatted Y value of the
	point
[label]	label property of the current
	point
[min]	preformatted min value of the
	current point
[max]	preformatted max value of the
	currnt point

4.4.9 EJSC.FunctionSeries



The FunctionSeries is rendered as a line based on the results of the function specified.

The constructor expects a function which can be called as function(x), and an optional set of object properties.

Constructor

EJSC.FunctionSeries(function fn, {object options})

Example

Defining Properties and Events

FunctionSeries properties may be set individually after the series has been created or in batch using the options parameter during instantiation.

Setting properties individually

```
var mySeries = new EJSC.FunctionSeries(Math.cos);
mySeries.lineWidth = 2;
mySeries.title = "New Function Series";
```

Setting properties in batch

4.4.9.1 Properties

4.4.9.1.1 color (inherited)

Definition

string color = undefined

Description

Defines the series color. If left undefined, the color is pulled from the array of default colors stored in the chart.

Note: May not be applicable to all series (i.e. EJSC.PieSeries)

4.4.9.1.2 coloredLegend (inherited)

Definition

boolean coloredLegend = true

Description

Determines whether the legend text inherits the series color. Setting to false will allow the legend text to inherit its normal cascaded color. To modify this property after series creation see EJSC.Series.setColoredLegend()

4.4.9.1.3 hint_string (inherited)

Definition

string hint_string = undefined

Description

This property may be used to define a series specific string to be used when displaying point hints. This string may contain replacement indicators (see Text Replacement Options). When left undefined, a default hint defined by the series type will be displayed.

Example

>> Modify the default hint to include custom text.

4.4.9.1.4 legendIsVisible (inherited)

Definition

boolean legendlsVisible = true

Description

Determines whether the legend item associated with the series appears in the legend window. Use the Series.showLegend and Series.hideLegend methods to control legend item visibility after series creation.

4.4.9.1.5 lineOpacity (inherited)

Definition

```
integer lineOpacity = 100
```

Description

Determines the line opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setLineOpacity()

4.4.9.1.6 lineWidth (inherited)

Definition

```
integer lineWidth = 1
```

Description

Defines the width of the line connecting series points.

4.4.9.1.7 padding (inherited)

Definition

```
object padding = {
     x_axis_min: undefined,
     x_axis_max: undefined,
     y_axis_min: undefined,
     y_axis_max: undefined
}
```

Description

The padding property may be used to override the series default padding. Padding is the amount of pixels added to the min and max series values in order to push the extremes and prevent the series from hitting the edge of the chart.

The amount of default padding is dependant upon the series type and axis configuration and may not be applicable to all series types.

This property is only applicable during series creation. To retrieve or modify the series padding after creation please see Series.getPadding() and Series.setPadding()

Example

>> Remove all padding from the BarSeries

```
var barSeries = new EJSC.BarSeries(new EJSC.ArrayDataHandler([..data..]), {
          padding: {
```

4.4.9.1.8 title (inherited)

Definition

string title = "Series <index>"

Description

Defines the series title used in hints and legend display.

Note: The default title of Series <index> (where <index> equals the current position in the series array for its owner chart) is assigned when a series is added to a chart using addSeries. This default title is only applied if the title is blank (i.e. "") at the time the addSeries method is called.

4.4.9.1.9 visible (inherited)

Definition

boolean visible = true

Description

Defines whether the series is visible and can draw on the chart

4.4.9.1.10 x_axis (inherited)

Definition

```
string x_axis = "bottom"
```

Description

Defines the horizontal axis to use for X values. Valid options are "top" or "bottom".

4.4.9.1.11 x_axis_formatter (inherited)

Definition

```
string x_axis_formatter = undefined
```

Description

Defines the formatter that will be used to format hints for the X values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

Types: EJSC.DateFormatter EJSC.NumberFormatter

4.4.9.1.12 y_axis (inherited)

Definition

```
string y_axis = "left"
```

Description

Defines the vertical axis to use for Y values. Valid options are "left" or "right".

4.4.9.1.13 y_axis_formatter (inherited)

Definition

```
string y_axis_formatter = undefined
```

Description

Defines the formatter that will be used to format hints for the Y values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

```
Types:
EJSC.DateFormatter
EJSC.NumberFormatter
```

4.4.9.2 Methods

4.4.9.2.1 findClosestByPixel (inherited)

Definition

Description

Returns the point object closest to the screen pixel coordinates provided. The x and y properties of the point object should be in the same scale as the x and y axes assigned to the series. To locate points based on pixel coordinates, see Series.findClosestByPixel()

4.4.9.2.2 findClosestByPoint (inherited)

Returns the point object closest to the axis coordinates provided. The x and y properties of the coordinate object should be based on the top left of the viewport and take into account the page scroll. To locate points based on axis coordinates, see Series.findClosestByPoint()

4.4.9.2.3 getPadding (inherited)

Definition

Description

Returns an object containing the series current padding. If padding has been set either by the Series.setPadding() method of the Series.padding property during construction the result of this method will be adjusted to return the most current padding values.

4.4.9.2.4 getVisibility (inherited)

Definition

boolean getVisibility()

Description

Returns a boolean indicating the series current visible state

4.4.9.2.5 hide (inherited)

Definition

void hide()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already hidden.

4.4.9.2.6 hideLegend (inherited)

void hideLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already hidden.

4.4.9.2.7 reload (inherited)

Definition

void reload()

Description

Triggers a series reload if the functionality is defined in a child class. This may involve retrieving data again or simply recalculating. While the reload() method exists in the base Series class, implementation of the protected methods triggered by calling reload() is at the discretion of the child class.

4.4.9.2.8 setColor (inherited)

Definition

void setColor(string color)

Description

Changes the series color and causes the chart to redraw.

4.4.9.2.9 setColoredLegend (inherited)

Definition

void setColoredLegend(boolean coloredLegend)

Description

Sets the EJSC.Series.coloredLegend property and updates the legend to reflect the change.

4.4.9.2.10 setLineWidth (inherited)

Definition

void setLineWidth(integer width)

Description

Updates the lineWidth property and redraws the chart.

4.4.9.2.11 setPadding (inherited)

void setPadding(object Padding, boolean Redraw)

The padding object should be defined as when used in the series constructor. See Series.padding.

Description

This method updates the user-defined series padding and optionally recalculates the chart extremes and redraws the chart.

4.4.9.2.12 setTitle (inherited)

Definition

void setTitle(string title)

Description

Changes the series title and update the legend caption (if applicable).

Note: this will not cause updates to a hint which is visible at the time it is called, though the next time a hint is rendered it will show the new property value.

4.4.9.2.13 show (inherited)

Definition

void show()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already visible.

4.4.9.2.14 showLegend (inherited)

Definition

void showLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already visible.

4.4.9.3 Events

4.4.9.3.1 onAfterVisibilityChange (inherited)

Definition

boolean onAfterVisibilityChange(EJSC.Series series, EJSC.Chart chart, boolean visible)

Fired when the series visibility changes. Sends series which changed, its owner chart and its new visible property value.

Returning false from this event handler will cancel redrawing the chart.

4.4.9.3.2 onBeforeVisibilityChange (inherited)

Definition

boolean onBeforeVisibilityChange(EJSC.Series series, EJSC.Chart chart)

Description

Fired before the series visibility is about to change. Sends series which changed, its owner chart. The current visible state of the series may be checked using the series visible property.

Returning false from this event handler will cancel the change in visibility.

4.4.9.3.3 onShowHint (inherited)

Definition

string onShowHint(EJSC.Point point, EJSC.Series series, EJSC.Chart chart, string hint_string)

Description

Fired before the displaying the hint, this event allows the current hint string to be overridden. See Text Replacement Options for a list of the automatic substitutions available.


With

4.4.9.4 Text Replacement Options

String

oung	AAICH
[chart_title]	title of the chart
[series_title]	title of the series the selected
	point resides in
[xaxis]	caption of the series x axis
[yaxis]	caption of the series y axis
[x]	preformatted X value of the
	point
[y]	preformatted Y value of the
	point
[label]	label property of the current
	point

4.4.10 EJSC.LineSeries



LineSeries is rendered by drawing a line from point to point.

The constructor expects an instantiated EJSC.DataHandler descendant and an optional set of object properties.

Constructor

```
EJSC.LineSeries( EJSC.DataHandler dataHandler [, object options] )
```

Example

Defining Properties and Events

LineSeries properties may be set individually after the series has been created or in batch using the options parameter during instantiation.

Setting properties individually

```
var mySeries = new EJSC.LineSeries(new
EJSC.ArrayDataHandler([[1,1],[2,2],[3,3],[4,3],[5,2],[6,4]]));
   mySeries.lineWidth = 2;
   mySeries.title = "New Line Series";
```

Setting properties in batch

Gaps in line series

Gaps are supported in the line series and may be enabled by providing a blank string for a given X and/or Y value:

4.4.10.1 Properties

4.4.10.1.1 autosort (inherited)

Definition

boolean autosort = true

Description

Defines whether the series applies the appropriate sort to points prior to drawing. Drawing routines are generally optimized to accept data in a certain order and this property eliminates the need for the developer to worry about that order prior to sending data to the series. If set to false, the data must be properly ordered beforehand in order to ensure the series renders correctly.

Note: May not be applicable to all series (i.e. EJSC.PieSeries, EJSC.AnalogGaugeSeries)

4.4.10.1.2 color (inherited)

Definition

string color = undefined

Description

Defines the series color. If left undefined, the color is pulled from the array of default colors stored in the chart.

Note: May not be applicable to all series (i.e. EJSC.PieSeries)

4.4.10.1.3 coloredLegend (inherited)

Definition

boolean coloredLegend = true

Description

Determines whether the legend text inherits the series color. Setting to false will allow the legend text to inherit its normal cascaded color. To modify this property after series creation see EJSC.Series.setColoredLegend()

4.4.10.1.4 delayLoad (inherited)

EXPERIMENTAL

Definition

boolean delayLoad = true

Description

This property allows a series to force its data handler to begin data retrieval as soon as it is added to a chart. When set to false, the series will initiate data retrieval as soon as it is added to a chart. When true, the data retrieval is initialized when the series first needs to draw.

4.4.10.1.5 drawPoints

Definition

boolean drawPoints = false

Description

Determines whether the individual points in the series are visually indicated by round dots on the chart. The size and color of the fill and border are determined by the pointColor, pointSize, pointBorderColor and pointBorderSize properties.

Note: Setting this property to true for series which have a large number of points may impact performance as additional draws are required to render the points.

4.4.10.1.6 hint_string (inherited)

Definition

string hint_string = undefined

Description

This property may be used to define a series specific string to be used when displaying point hints. This string may contain replacement indicators (see Text Replacement Options). When left undefined, a default hint defined by the series type will be displayed.

Example

>> Modify the default hint to include custom text.

4.4.10.1.7 legendlsVisible (inherited)

Definition

boolean legendlsVisible = true

Description

Determines whether the legend item associated with the series appears in the legend window. Use the Series.showLegend and Series.hideLegend methods to control legend item visibility after series creation.

4.4.10.1.8 lineOpacity (inherited)

Definition

integer lineOpacity = 100

Description

Determines the line opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setLineOpacity()

4.4.10.1.9 lineWidth (inherited)

Definition

integer lineWidth = 1

Description

Defines the width of the line connecting series points.

4.4.10.1.10 padding (inherited)

Definition

```
object padding = {
    x_axis_min: undefined,
    x_axis_max: undefined,
    y_axis_min: undefined,
    y_axis_max: undefined
}
```

Description

The padding property may be used to override the series default padding. Padding is the amount of pixels added to the min and max series values in order to push the extremes and prevent the series from hitting the edge of the chart.

The amount of default padding is dependant upon the series type and axis configuration and may not be applicable to all series types.

This property is only applicable during series creation. To retrieve or modify the series padding after creation please see Series.getPadding() and Series.setPadding()

Example

>> Remove all padding from the BarSeries

```
var barSeries = new EJSC.BarSeries(new EJSC.ArrayDataHandler([..data..]), {
```

4.4.10.1.11 pointBorderColor

Definition

string pointBorderColor = "rgb(255,255,255)"

Description

Defines the color of the border drawn around the points. This property is only applicable when the series drawPoints property is set to true and pointBorderSize is greater than 0.

4.4.10.1.12 pointBorderSize

Definition

integer pointBorderSize = 0

Description

Defines the size in pixels of the border drawn around the points. This property is only applicable when the series.drawPoints property is set to true.

To draw points without any border, leave pointBorderSize set to 0.

4.4.10.1.13 pointColor

Definition

string pointColor = undefined

Description

Defines the color of the point (circle) drawn at each data point in the series. If left undefined the point will inherit the series color.

This property is only applicable when the series.drawPoints property is set to true.

4.4.10.1.14 pointSize

Definition

integer pointSize = undefined

Description

Defines the size of the point (circle) drawn at each data point in the series. If left undefined the point diameter will be twice the line width of the series.

This property is only applicable when the series.drawPoints property is set to true.

4.4.10.1.15 title (inherited)

Definition

string title = "Series <index>"

Description

Defines the series title used in hints and legend display.

Note: The default title of Series <index> (where <index> equals the current position in the series array for its owner chart) is assigned when a series is added to a chart using addSeries. This default title is only applied if the title is blank (i.e. "") at the time the addSeries method is called.

4.4.10.1.16 visible (inherited)

Definition

boolean visible = true

Description

Defines whether the series is visible and can draw on the chart

4.4.10.1.17 x_axis (inherited)

Definition

```
string x_axis = "bottom"
```

Description

Defines the horizontal axis to use for X values. Valid options are "top" or "bottom".

4.4.10.1.18 x_axis_formatter (inherited)

Definition

```
string x_axis_formatter = undefined
```

Description

Defines the formatter that will be used to format hints for the X values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

Types: EJSC.DateFormatter EJSC.NumberFormatter

4.4.10.1.19 y_axis (inherited)

```
string y_axis = "left"
```

Defines the vertical axis to use for Y values. Valid options are "left" or "right".

```
4.4.10.1.20 y_axis_formatter (inherited)
```

Definition

```
string y_axis_formatter = undefined
```

Description

Defines the formatter that will be used to format hints for the Y values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

```
Types: EJSC.DateFormatter EJSC.NumberFormatter
```

4.4.10.2 Methods

4.4.10.2.1 findClosestByPixel (inherited)

Definition

Description

Returns the point object closest to the screen pixel coordinates provided. The x and y properties of the point object should be in the same scale as the x and y axes assigned to the series. To locate points based on pixel coordinates, see Series.findClosestByPixel()

4.4.10.2.2 findClosestByPoint (inherited)

Definition

Description

Returns the point object closest to the axis coordinates provided. The x and y properties of the coordinate object should be based on the top left of the viewport and take into account the page scroll. To locate points based on axis coordinates, see Series.findClosestByPoint()

4.4.10.2.3 getDataHandler (inherited)

Definition

EJSC.DataHandler getDataHandler()

Description

Returns the EJSC.DataHandler descendant currently assigned to the series. This is not applicable to all series and will return null if a data handler has not been defined or is not used.

4.4.10.2.4 getPadding (inherited)

Definition

Description

Returns an object containing the series current padding. If padding has been set either by the Series.setPadding() method of the Series.padding property during construction the result of this method will be adjusted to return the most current padding values.

4.4.10.2.5 getVisibility (inherited)

Definition

boolean getVisibility()

Description

Returns a boolean indicating the series current visible state

4.4.10.2.6 hide (inherited)

Definition

void hide()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already hidden.

4.4.10.2.7 hideLegend (inherited)

Definition

void hideLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already hidden.

4.4.10.2.8 reload (inherited)

Definition

void reload()

Description

Triggers a series reload if the functionality is defined in a child class. This may involve retrieving data again or simply recalculating. While the reload() method exists in the base Series class, implementation of the protected methods triggered by calling reload() is at the discretion of the child class.

4.4.10.2.9 setColor (inherited)

Definition

void setColor(string color)

Description

Changes the series color and causes the chart to redraw.

4.4.10.2.10 setColoredLegend (inherited)

Definition

void setColoredLegend(boolean coloredLegend)

Description

Sets the EJSC.Series.coloredLegend property and updates the legend to reflect the change.

4.4.10.2.11 setDataHandler (inherited)

Definition

void setDataHandler (EJSC.DataHandler dataHandler, boolean reload)

Updates the series data handler and triggers a data reload if reload parameter is **true**. This method may not be implemented in all child classes.

4.4.10.2.12 setLineOpacity (inherited)

Definition

void setLineOpacity(integer opacity)

Description

Sets the EJSC.Series.lineOpacity property and redraws the series to reflect the change.

4.4.10.2.13 setLineWidth (inherited)

Definition

void setLineWidth(integer width)

Description

Updates the lineWidth property and redraws the chart.

4.4.10.2.14 setPadding (inherited)

Definition

void setPadding(object Padding, boolean Redraw)

The padding object should be defined as when used in the series constructor. See Series.padding.

Description

This method updates the user-defined series padding and optionally recalculates the chart extremes and redraws the chart.

4.4.10.2.15 setTitle (inherited)

Definition

void setTitle(string title)

Description

Changes the series title and update the legend caption (if applicable).

Note: this will not cause updates to a hint which is visible at the time it is called, though the next time a hint is rendered it will show the new property value.

4.4.10.2.16 show (inherited)

void show()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already visible.

4.4.10.2.17 showLegend (inherited)

Definition

void showLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already visible.

4.4.10.3 Events

4.4.10.3.1 onAfterDataAvailable (inherited)

Definition

boolean onAfterDataAvailable(EJSC.Chart chart, EJSC.Series series)

Description

Fired after the series has processed its data and before the chart is told to redraw. Returning **false** from this event handler will cancel redrawing the chart.

4.4.10.3.2 onAfterVisibilityChange (inherited)

Definition

boolean onAfterVisibilityChange(EJSC.Series series, EJSC.Chart chart, boolean visible)

Description

Fired when the series visibility changes. Sends series which changed, its owner chart and its new visible property value.

Returning false from this event handler will cancel redrawing the chart.

4.4.10.3.3 onBeforeVisibilityChange (inherited)

Definition

boolean onBeforeVisibilityChange(EJSC.Series series, EJSC.Chart chart)

Description

Fired before the series visibility is about to change. Sends series which changed, its owner chart. The current visible state of the series may be checked using the series visible property.

Returning false from this event handler will cancel the change in visibility.

4.4.10.3.4 onShowHint (inherited)

Definition

string onShowHint(EJSC.Point point, EJSC.Series series, EJSC.Chart chart, string hint_string)

Description

Fired before the displaying the hint, this event allows the current hint string to be overridden. See Text Replacement Options for a list of the automatic substitutions available.

\A/:41-

4.4.10.4 Text Replacement Options

C4=:-- --

String	With
[chart_title]	title of the chart
[series_title]	title of the series the selected
	point resides in
[xaxis]	caption of the series x axis
[yaxis] [x]	caption of the series y axis
[x]	preformatted X value of the
	point
[y]	preformatted Y value of the
	point
[label]	label property of the current
	point

4.4.10.5 Data Formats

The x and y parameters are required, label and userdata are both optional.


XML (EJSC.XMLDataHandler, EJSC.XMLStringDataHandler):

Unused parameters may be omitted

Full:

```
<P x="number or string" y="number or
string" label="string" userdata="string"/>
                                                   <P x="number or string" y="number or
string" label="string" userdata="string"/>
                      </G>
       Compact: The values parameter is formatted as CSV
                      <G>
                                    <L values="CSV string"/>
                      </G>
Array (EJSC.ArrayDataHandler):
       [
                      ["x", "y", "label", "userdata"],
                      ["x", "y", "label", "userdata"]
       1
       Null should be used to skip unused parameters:
       [
                      ["x", "y", null, "userdata"],
                      ["x", "y", null, "userdata"]
       1
CSV (EJSC.CSVFileDataHandler, EJSC.CSVStringDataHandler):
       "x|y|label|userdata,x|y|label|userdata"
       Null should be used to skip unused parameters
       "x|y|null|userdata,x|y|null|userdata"
JSON (EJSC.JSONFileDataHandler, EJSC.JSONStringDataHandler):
       Unused parameters may be omitted.
       Γ
                      {"x":"number or string","y":"number or
string", "label": "string", "userdata": "string"},
                      {"x":"number or string","y":"number or
string","label":"string","userdata":"string"}
       1
```

4.4.11 EJSC.OpenHighLowCloseSeries



OpenHighLowCloseSeries renders its point data as vertical lines with optional horizontal "wicks" to express open and close values.

The constructor expects an instantiated EJSC.DataHandler descendant and an optional set of object properties.

Constructor

```
EJSC.OpenHighLowCloseSeries( EJSC.DataHandler dataHandler [, object options])
```

Example

```
var mySeries = new EJSC.OpenHighLowCloseSeries(
    new EJSC.ArrayDataHandler([[1,10,1,2,9],[2,20,7,10,19]]),
    { title: "New OpenHighLowClose Series" }
);
```

Defining Properties and Events

OpenHighLowCloseSeries properties may be set individually after the series has been created or in batch using the options parameter during instantiation.

Setting properties individually

```
var mySeries = new EJSC.OpenHighLowCloseSeries(new
EJSC.ArrayDataHandler([[1,10,1,2,9],[2,20,7,10,19]]));
   mySeries.lineWidth = 1;
   mySeries.title = "New OpenHighLowClose Series";
```

Setting properties in batch

```
{ lineWidth: 1, title: "New OpenHighLowClose Series" } );
```

4.4.11.1 Properties

4.4.11.1.1 autosort (inherited)

Definition

boolean autosort = true

Description

Defines whether the series applies the appropriate sort to points prior to drawing. Drawing routines are generally optimized to accept data in a certain order and this property eliminates the need for the developer to worry about that order prior to sending data to the series. If set to false, the data must be properly ordered beforehand in order to ensure the series renders correctly.

Note: May not be applicable to all series (i.e. EJSC.PieSeries, EJSC.AnalogGaugeSeries)

4.4.11.1.2 color (inherited)

Definition

string color = undefined

Description

Defines the series color. If left undefined, the color is pulled from the array of default colors stored in the chart.

Note: May not be applicable to all series (i.e. EJSC.PieSeries)

4.4.11.1.3 coloredLegend (inherited)

Definition

boolean coloredLegend = true

Description

Determines whether the legend text inherits the series color. Setting to false will allow the legend text to inherit its normal cascaded color. To modify this property after series creation see EJSC.Series.setColoredLegend()

4.4.11.1.4 delayLoad (inherited)

EXPERIMENTAL

Definition

boolean delayLoad = true

This property allows a series to force its data handler to begin data retrieval as soon as it is added to a chart. When set to false, the series will initiate data retrieval as soon as it is added to a chart. When true, the data retrieval is initialized when the series first needs to draw.

4.4.11.1.5 gain

Definition

Description

Defines the appearance of the points which represent a gain.

Example

4.4.11.1.6 hint_string (inherited)

Definition

```
string hint_string = undefined
```

Description

This property may be used to define a series specific string to be used when displaying point hints. This string may contain replacement indicators (see Text Replacement Options). When left undefined, a default hint defined by the series type will be displayed.

Example

>> Modify the default hint to include custom text.

4.4.11.1.7 intervalOffset

Definition

float intervalOffset = 0.8

Defines the spacing between the points as a percentage of 1. 1 = points take up the entire width available, with their edges touching.

Example

4.4.11.1.8 legendlsVisible (inherited)

Definition

boolean legendlsVisible = true

Description

Determines whether the legend item associated with the series appears in the legend window. Use the Series.showLegend and Series.hideLegend methods to control legend item visibility after series creation.

4.4.11.1.9 lineOpacity (inherited)

Definition

```
integer lineOpacity = 100
```

Description

Determines the line opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setLineOpacity()

4.4.11.1.10 lineWidth (inherited)

Definition

```
integer lineWidth = 1
```

Description

Defines the width of the line connecting series points.

4.4.11.1.11 loss

```
object loss = {
```

```
lineColor: "rgb(249,95,95)",
lineOpacity: 100
}
```

Defines the appearance of the points which represent a loss.

Example

4.4.11.1.12 opacity (inherited)

Definition

integer opacity = 50

Description

Determines the fill opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setOpacity()

4.4.11.1.13 padding (inherited)

Definition

```
object padding = {
    x_axis_min: undefined,
    x_axis_max: undefined,
    y_axis_min: undefined,
    y_axis_max: undefined
}
```

Description

The padding property may be used to override the series default padding. Padding is the amount of pixels added to the min and max series values in order to push the extremes and prevent the series from hitting the edge of the chart.

The amount of default padding is dependant upon the series type and axis configuration and may not be applicable to all series types.

This property is only applicable during series creation. To retrieve or modify the series padding after creation please see Series.getPadding() and Series.setPadding()

Example

>> Remove all padding from the BarSeries

4.4.11.1.14 title (inherited)

Definition

```
string title = "Series <index>"
```

Description

Defines the series title used in hints and legend display.

Note: The default title of Series <index> (where <index> equals the current position in the series array for its owner chart) is assigned when a series is added to a chart using addSeries. This default title is only applied if the title is blank (i.e. "") at the time the addSeries method is called.

4.4.11.1.15 visible (inherited)

Definition

boolean visible = true

Description

Defines whether the series is visible and can draw on the chart

```
4.4.11.1.16 x_axis (inherited)
```

Definition

```
string x_axis = "bottom"
```

Description

Defines the horizontal axis to use for X values. Valid options are "top" or "bottom".

```
4.4.11.1.17 x_axis_formatter (inherited)
```

Definition

```
string x_axis_formatter = undefined
```

Description

Defines the formatter that will be used to format hints for the X values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

Types: EJSC.DateFormatter EJSC.NumberFormatter

4.4.11.1.18 y_axis (inherited)

Definition

```
string y_axis = "left"
```

Description

Defines the vertical axis to use for Y values. Valid options are "left" or "right".

4.4.11.1.19 y_axis_formatter (inherited)

Definition

```
string y_axis_formatter = undefined
```

Description

Defines the formatter that will be used to format hints for the Y values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

Types: EJSC.DateFormatter EJSC.NumberFormatter

4.4.11.2 Methods

4.4.11.2.1 findClosestByPixel (inherited)

Definition

Description

Returns the point object closest to the screen pixel coordinates provided. The x and y properties of the point object should be in the same scale as the x and y axes assigned to the series. To locate points based on pixel coordinates, see Series.findClosestByPixel()

4.4.11.2.2 findClosestByPoint (inherited)

Definition

EJSC.Point findClosestByPoint(object coordinate)

Returns the point object closest to the axis coordinates provided. The x and y properties of the coordinate object should be based on the top left of the viewport and take into account the page scroll. To locate points based on axis coordinates, see Series.findClosestByPoint()

4.4.11.2.3 getDataHandler (inherited)

Definition

EJSC.DataHandler getDataHandler()

Description

Returns the EJSC.DataHandler descendant currently assigned to the series. This is not applicable to all series and will return null if a data handler has not been defined or is not used.

4.4.11.2.4 getPadding (inherited)

Definition

Description

Returns an object containing the series current padding. If padding has been set either by the Series.setPadding() method of the Series.padding property during construction the result of this method will be adjusted to return the most current padding values.

4.4.11.2.5 getVisibility (inherited)

Definition

boolean getVisibility()

Description

Returns a boolean indicating the series current visible state

4.4.11.2.6 hide (inherited)

Definition

void hide()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already hidden.

4.4.11.2.7 hideLegend (inherited)

Definition

void hideLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already hidden.

4.4.11.2.8 reload (inherited)

Definition

void reload()

Description

Triggers a series reload if the functionality is defined in a child class. This may involve retrieving data again or simply recalculating. While the reload() method exists in the base Series class, implementation of the protected methods triggered by calling reload() is at the discretion of the child class.

4.4.11.2.9 setColor (inherited)

Definition

void setColor(string color)

Description

Changes the series color and causes the chart to redraw.

4.4.11.2.10 setColoredLegend (inherited)

Definition

void setColoredLegend(boolean coloredLegend)

Description

Sets the EJSC.Series.coloredLegend property and updates the legend to reflect the change.

4.4.11.2.11 setDataHandler (inherited)

Definition

void setDataHandler(EJSC.DataHandler dataHandler, boolean reload)

Description

Updates the series data handler and triggers a data reload if reload parameter is **true**. This method may not be implemented in all child classes.

4.4.11.2.12 setLineOpacity (inherited)

Definition

void setLineOpacity(integer opacity)

Description

Sets the EJSC.Series.lineOpacity property and redraws the series to reflect the change.

4.4.11.2.13 setLineWidth (inherited)

Definition

void setLineWidth(integer width)

Description

Updates the lineWidth property and redraws the chart.

4.4.11.2.14 setOpacity (inherited)

Definition

void setOpacity(integer opacity)

Description

Sets the EJSC. Series opacity property and redraws the series to reflect the change.

4.4.11.2.15 setPadding (inherited)

Definition

void setPadding(object Padding, boolean Redraw)

The padding object should be defined as when used in the series constructor. See Series.padding.

Description

This method updates the user-defined series padding and optionally recalculates the chart extremes and redraws the chart.

4.4.11.2.16 setTitle (inherited)

Definition

void setTitle(string title)

Description

Changes the series title and update the legend caption (if applicable).

Note: this will not cause updates to a hint which is visible at the time it is called, though the next time a hint is rendered it will show the new property value.

4.4.11.2.17 show (inherited)

Definition

void show()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already visible.

4.4.11.2.18 showLegend (inherited)

Definition

void showLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already visible.

4.4.11.3 Events

4.4.11.3.1 onAfterDataAvailable (inherited)

Definition

boolean onAfterDataAvailable(EJSC.Chart chart, EJSC.Series series)

Description

Fired after the series has processed its data and before the chart is told to redraw. Returning **false** from this event handler will cancel redrawing the chart.

4.4.11.3.2 onAfterVisibilityChange (inherited)

Definition

boolean onAfterVisibilityChange(EJSC.Series series, EJSC.Chart chart, boolean visible)

Description

Fired when the series visibility changes. Sends series which changed, its owner chart and its new visible property value.

Returning **false** from this event handler will cancel redrawing the chart.

4.4.11.3.3 onBeforeVisibilityChange (inherited)

Definition

boolean onBeforeVisibilityChange(EJSC.Series series, EJSC.Chart chart)

Description

Fired before the series visibility is about to change. Sends series which changed, its owner chart. The current visible state of the series may be checked using the series visible property.

Returning false from this event handler will cancel the change in visibility.

4.4.11.3.4 onShowHint (inherited)

Definition

string onShowHint(EJSC.Point point, EJSC.Series series, EJSC.Chart chart, string hint_string)

Description

Fired before the displaying the hint, this event allows the current hint string to be overridden. See Text Replacement Options for a list of the automatic substitutions available.

4.4.11.4 Data Formats

XML (EJSC.XMLDataHandler, EJSC.XMLStringDataHandler):

Unused parameters may be omitted

Full:

<graph>

<plot>

<point x="number or string"

high="number" low="number" open="number" close="number" label="string" userdata="string"/>

<point x="number or string"

high="number" low="number" open="number" close= number label="string" userdata="string"/>


</plot>

```
<graph>
       Short:
                     <G>
                                                  <P x="number or string" high="number"
low="number" open="number" close="number" label="string" userdata="string"/>
                                                  <P x="number or string" high="number"
low="number" open="number" close="number" label="string" userdata="string"/>
                                    </L>
                     </G>
       Compact: The values parameter is formatted as CSV
                     <G>
                                    <L values="CSV string"/>
                      </G>
Array (EJSC.ArrayDataHandler):
       [
                     ["x", "high", "low", "open", "close", "label", "userdata"],
                     ["x", "high", "low", "open", "close", "label", "userdata"]
       1
       Null should be used to skip unused parameters:
       [
                     ["x", null, null, "open", "close", null, "userdata"],
                     ["x", null, null, "open", "close", null, "userdata"]
       1
CSV (EJSC.CSVFileDataHandler, EJSC.CSVStringDataHandler):
       "x|high|low|open|close|label|userdata,x|high|low|open|close|label|userdata"
       Null should be used to skip unused parameters
       "x|null|null|open|close|null|userdata,x|null|null|open|close|null|userdata"
JSON (EJSC.JSONFileDataHandler, EJSC.JSONStringDataHandler):
       Unused parameters may be omitted.
       Ε
                     {"x": "number or string", "high": "number", "low": "number",
                    "close":"number", label":"string","userdata":"string"},
"open": "number",
                      {"x":"number or string", "high":"number", "low":"number",
"open": "number", "close": "number", label": "string", "userdata": "string"}
       ]
```

4.4.11.5 Text Replacement Options

String [chart_title] [series_title]	With title of the chart title of the series the selected
	point resides in
[xaxis] [yaxis] [x]	caption of the series x axis caption of the series y axis preformatted X value of the
	point
[high]	preformatted high value of the
	point
[low]	preformatted low value of the
	point
[open]	preformatted open value of
	the point
[close]	preformatted close value of
· · ·-	the point
[label]	label property of the current
	point

4.4.12 EJSC.OverUnderSeries



The OverUnderSeries is drawn as a fill between two LineSeries. Different colors are used to tell which referenced series' Y values are higher at any given X position.

Constructor

```
{\tt EJSC.OverUnderSeries(\ EJSC.Series\ baseSeries,\ EJSC.Series\ compareSeries,\ \{object\ options\}\ )}
```

Example

Defining Properties and Events

OverUnderSeries Series properties may be set individually after the series has been created or in batch using the options parameter during instantiation.

Setting properties individually

```
var mySeries = new EJSC.OverUnderSeries(lineSeries1, lineSeries2);
mySeries.exceed = {visible: false};
mySeries.subcede = {visible: false};
mySeries.title = "New OverUnderSeries Series";
```

Setting properties in batch

4.4.12.1 Properties

4.4.12.1.1 autosort (inherited)

Definition

boolean autosort = true

Description

Defines whether the series applies the appropriate sort to points prior to drawing. Drawing routines are generally optimized to accept data in a certain order and this property eliminates the need for the developer to worry about that order prior to sending data to the series. If set to false, the data must be properly ordered beforehand in order to ensure the series renders correctly.

Note: May not be applicable to all series (i.e. EJSC.PieSeries, EJSC.AnalogGaugeSeries)

4.4.12.1.2 color (inherited)

Definition

string color = undefined

Description

Defines the series color. If left undefined, the color is pulled from the array of default colors stored in the chart.

Note: May not be applicable to all series (i.e. EJSC.PieSeries)

4.4.12.1.3 coloredLegend (inherited)

boolean coloredLegend = true

Description

Determines whether the legend text inherits the series color. Setting to false will allow the legend text to inherit its normal cascaded color. To modify this property after series creation see EJSC.Series.setColoredLegend()

4.4.12.1.4 exceed

Definition

```
object exceed = {
    visible: true,
    color: '#00ff00',
    opacity: 20
}
```

Description

Defines the attributes for drawing the exceedences

Properties

boolean visible color color integer opacity exceedences

- Defines if the exceedences are visible
- The color to drag the text on the exceedences in
- Integer (0-100): The % opacity for the fill of the

4.4.12.1.5 delayLoad (inherited)

EXPERIMENTAL

Definition

boolean delayLoad = true

Description

This property allows a series to force its data handler to begin data retrieval as soon as it is added to a chart. When set to false, the series will initiate data retrieval as soon as it is added to a chart. When true, the data retrieval is initialized when the series first needs to draw.

4.4.12.1.6 hint_string (inherited)

Definition

string hint_string = undefined

Description

This property may be used to define a series specific string to be used when displaying point hints. This string may contain replacement indicators (see Text Replacement Options). When left undefined, a default hint defined by the series type will be displayed.

Example

>> Modify the default hint to include custom text.

4.4.12.1.7 legendlsVisible (inherited)

Definition

boolean legendlsVisible = true

Description

Determines whether the legend item associated with the series appears in the legend window. Use the Series.showLegend and Series.hideLegend methods to control legend item visibility after series creation.

4.4.12.1.8 lineOpacity (inherited)

Definition

integer lineOpacity = 100

Description

Determines the line opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setLineOpacity()

4.4.12.1.9 lineWidth (inherited)

Definition

integer lineWidth = 1

Description

Defines the width of the line connecting series points.

4.4.12.1.10 opacity (inherited)

Definition

integer opacity = 50

Description

Determines the fill opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setOpacity()

4.4.12.1.11 padding (inherited)

Definition

```
object padding = {
    x_axis_min: undefined,
    x_axis_max: undefined,
    y_axis_min: undefined,
    y_axis_max: undefined
}
```

Description

The padding property may be used to override the series default padding. Padding is the amount of pixels added to the min and max series values in order to push the extremes and prevent the series from hitting the edge of the chart.

The amount of default padding is dependant upon the series type and axis configuration and may not be applicable to all series types.

This property is only applicable during series creation. To retrieve or modify the series padding after creation please see Series.getPadding() and Series.setPadding()

Example

>> Remove all padding from the BarSeries

4.4.12.1.12 subsede

Definition

```
object subcede = {
    visible: true,
    color: '#ff0000',
    opacity: 20
}
```

Description

Defines the attributes for drawing the subsedences

Properties

boolean visible — Defines if the subsedences are visible color color — The color to drag the text on the subsedences in integer opacity — Integer (0-100): The % opacity for the fill of the subsedences

4.4.12.1.13 title (inherited)

Definition

string title = "Series <index>"

Description

Defines the series title used in hints and legend display.

Note: The default title of Series <index> (where <index> equals the current position in the series array for its owner chart) is assigned when a series is added to a chart using addSeries. This default title is only applied if the title is blank (i.e. "") at the time the addSeries method is called.

4.4.12.1.14 visible (inherited)

Definition

boolean visible = true

Description

Defines whether the series is visible and can draw on the chart

4.4.12.1.15 x_axis (inherited)

Definition

```
string x_axis = "bottom"
```

Description

Defines the horizontal axis to use for X values. Valid options are "top" or "bottom".

4.4.12.1.16 x_axis_formatter (inherited)

Definition

```
string x_axis_formatter = undefined
```

Description

Defines the formatter that will be used to format hints for the X values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

```
Types: EJSC.DateFormatter EJSC.NumberFormatter
```

4.4.12.1.17 y_axis (inherited)

Definition

```
string y_axis = "left"
```

Description

Defines the vertical axis to use for Y values. Valid options are "left" or "right".

```
4.4.12.1.18 y_axis_formatter (inherited)
```

Definition

```
string y_axis_formatter = undefined
```

Description

Defines the formatter that will be used to format hints for the Y values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

```
Types: EJSC.DateFormatter EJSC.NumberFormatter
```

4.4.12.2 Methods

4.4.12.2.1 findClosestByPixel (inherited)

Definition

Description

Returns the point object closest to the screen pixel coordinates provided. The x and y properties of the point object should be in the same scale as the x and y axes assigned to the series. To locate points based on pixel coordinates, see Series.findClosestByPixel()

4.4.12.2.2 findClosestByPoint (inherited)

Definition

Description

Returns the point object closest to the axis coordinates provided. The x and y properties of the coordinate object should be based on the top left of the viewport and take into account the page scroll.

To locate points based on axis coordinates, see Series.findClosestByPoint()

4.4.12.2.3 getDataHandler (inherited)

Definition

EJSC.DataHandler getDataHandler()

Description

Returns the EJSC.DataHandler descendant currently assigned to the series. This is not applicable to all series and will return null if a data handler has not been defined or is not used.

4.4.12.2.4 getPadding (inherited)

Definition

Description

Returns an object containing the series current padding. If padding has been set either by the Series.setPadding() method of the Series.padding property during construction the result of this method will be adjusted to return the most current padding values.

4.4.12.2.5 getVisibility (inherited)

Definition

boolean getVisibility()

Description

Returns a boolean indicating the series current visible state

4.4.12.2.6 hide (inherited)

Definition

void hide()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already hidden.

4.4.12.2.7 hideLegend (inherited)

Definition

void hideLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already hidden.

4.4.12.2.8 reload (inherited)

Definition

void reload()

Description

Triggers a series reload if the functionality is defined in a child class. This may involve retrieving data again or simply recalculating. While the reload() method exists in the base Series class, implementation of the protected methods triggered by calling reload() is at the discretion of the child class.

4.4.12.2.9 setColor (inherited)

Definition

void setColor(string color)

Description

Changes the series color and causes the chart to redraw.

4.4.12.2.10 setColoredLegend (inherited)

Definition

void **setColoredLegend**(boolean coloredLegend)

Description

Sets the EJSC.Series.coloredLegend property and updates the legend to reflect the change.

4.4.12.2.11 setDataHandler (inherited)

Definition

void setDataHandler(EJSC.DataHandler dataHandler, boolean reload)

Description

Updates the series data handler and triggers a data reload if reload parameter is true. This method

may not be implemented in all child classes.

4.4.12.2.12 setLineOpacity (inherited)

Definition

void setLineOpacity(integer opacity)

Description

Sets the EJSC.Series.lineOpacity property and redraws the series to reflect the change.

4.4.12.2.13 setLineWidth (inherited)

Definition

void setLineWidth(integer width)

Description

Updates the lineWidth property and redraws the chart.

4.4.12.2.14 setOpacity (inherited)

Definition

void setOpacity(integer opacity)

Description

Sets the EJSC.Series.opacity property and redraws the series to reflect the change.

4.4.12.2.15 setPadding (inherited)

Definition

void setPadding(object Padding, boolean Redraw)

The padding object should be defined as when used in the series constructor. See Series.padding.

Description

This method updates the user-defined series padding and optionally recalculates the chart extremes and redraws the chart.

4.4.12.2.16 setTitle (inherited)

Definition

void setTitle(string title)

Description

Changes the series title and update the legend caption (if applicable).

Note: this will not cause updates to a hint which is visible at the time it is called, though the next time a hint is rendered it will show the new property value.

4.4.12.2.17 show (inherited)

Definition

void show()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already visible.

4.4.12.2.18 showLegend (inherited)

Definition

void showLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already visible.

4.4.12.3 Events

4.4.12.3.1 onAfterDataAvailable (inherited)

Definition

boolean onAfterDataAvailable(EJSC.Chart chart, EJSC.Series series)

Description

Fired after the series has processed its data and before the chart is told to redraw. Returning **false** from this event handler will cancel redrawing the chart.

4.4.12.3.2 onAfterVisibilityChange (inherited)

Definition

boolean onAfterVisibilityChange(EJSC.Series series, EJSC.Chart chart, boolean visible)

Description

Fired when the series visibility changes. Sends series which changed, its owner chart and its new visible property value.

Returning false from this event handler will cancel redrawing the chart.

4.4.12.3.3 onBeforeVisibilityChange (inherited)

Definition

boolean onBeforeVisibilityChange(EJSC.Series series, EJSC.Chart chart)

Description

Fired before the series visibility is about to change. Sends series which changed, its owner chart. The current visible state of the series may be checked using the series visible property.

Returning false from this event handler will cancel the change in visibility.

4.4.12.3.4 onShowHint (inherited)

Definition


string onShowHint(EJSC.Point point, EJSC.Series series, EJSC.Chart chart, string hint_string)


Description

Fired before the displaying the hint, this event allows the current hint string to be overridden. See Text Replacement Options for a list of the automatic substitutions available.

4.4.13 EJSC.PieSeries

Emprise JavaScript Charts





The constructor expects an instantiated EJSC.DataHandler descendant and an optional set of object properties.

Constructor

```
EJSC.PieSeries( EJSC.DataHandler dataHandler [, object options] )
```

Example

Defining Properties and Events

PieSeries properties may be set individually after the series has been created or in batch using the options parameter during instantiation.

Setting properties individually

```
var mySeries = new EJSC.PieSeries(new EJSC.ArrayDataHandler([[10,"Label 1"],[20,"Label
2"],[120,"Label 3"]]));
   mySeries.title = "New Pie Series";
```

Setting properties in batch

4.4.13.1 Properties

4.4.13.1.1 defaultColors

Definition

array defaultColors = EJSC.DefaultPieColors

Description

Defines the pool of default colors available for pie pieces.

4.4.13.1.2 delayLoad (inherited)

EXPERIMENTAL

Definition

boolean delayLoad = true

Description

This property allows a series to force its data handler to begin data retrieval as soon as it is added to a chart. When set to false, the series will initiate data retrieval as soon as it is added to a chart. When true, the data retrieval is initialized when the series first needs to draw.

4.4.13.1.3 height

Definition

```
string height = "100%"
```

Description

Defines the total height of the pie series. This may be specified in percent of the chart as shown above as the default value, or in exact pixels by specifying a number (i.e. height = 150).

4.4.13.1.4 hint_string (inherited)

Definition

```
string hint_string = undefined
```

Description

This property may be used to define a series specific string to be used when displaying point hints. This string may contain replacement indicators (see Text Replacement Options). When left undefined, a default hint defined by the series type will be displayed.

Example

>> Modify the default hint to include custom text.

4.4.13.1.5 legendlsVisible (inherited)

Definition

boolean legendlsVisible = true

Description

Determines whether the legend item associated with the series appears in the legend window. Use the Series.showLegend and Series.hideLegend methods to control legend item visibility after series creation.

4.4.13.1.6 lineOpacity (inherited)

Definition

integer lineOpacity = 100

Description

Determines the line opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setLineOpacity()

4.4.13.1.7 lineWidth (inherited)

Definition

integer lineWidth = 1

Description

Defines the width of the line connecting series points.

4.4.13.1.8 opacity (inherited)

Definition

integer opacity = 50

Description

Determines the fill opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setOpacity()

4.4.13.1.9 position

Definition

string **position** = "center"

Description

Defines the quadrant of the chart that the pie will appear in.

Quadrants:

- topLeft
- topCenter
- topRight
- centerLeft
- center
- centerRight
- bottomLeft
- bottomCenter
- bottomRight
- left
- right

4.4.13.1.10 title (inherited)

Definition

string title = "Series <index>"

Description

Defines the series title used in hints and legend display.

Note: The default title of Series <index> (where <index> equals the current position in the series array for its owner chart) is assigned when a series is added to a chart using addSeries. This default title is only applied if the title is blank (i.e. "") at the time the addSeries method is called.

4.4.13.1.11 total_value

Definition

integer total_value = undefined

Description

Defines the total value (sum) of all pie pieces in the series. If left undefined, this value will be calculated automatically by adding all the piece values when the series data is loaded.

This property is only applicable during series creation. To determine or modify the total value once the series has been created use the getTotalValue and setTotalValue methods.

To force the chart to recalculate the total value based on actual series data, use the resetTotalValue method.

4.4.13.1.12 treeLegend

Definition

boolean treeLegend = true

Description

Defines whether to display each pie piece individually in the legend.

4.4.13.1.13 visible (inherited)

Definition

boolean visible = true

Description

Defines whether the series is visible and can draw on the chart

4.4.13.1.14 width

Definition

string width = "100%"

Description

Defines the total width of the pie series. This may be specified in percent of the chart as shown above as the default value, or in exact pixels by specifying a number (i.e. width = 150).

4.4.13.1.15 x_axis_formatter (inherited)

Definition

string x_axis_formatter = undefined

Description

Defines the formatter that will be used to format hints for the X values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

Types: EJSC.DateFormatter EJSC.NumberFormatter

4.4.13.2 Methods

4.4.13.2.1 findCenter

Definition

```
object findCenter( EJSC.PiePoint point )
```

The object returned is formatted as:

```
{
    x: integer,
    y: integer
}
```

Description

This method takes a pie point (see getPoints) and returns an object containing the x and y screen coordinates of the piece's center.

4.4.13.2.2 findCenterOfCurve

Definition

```
object findCenterOfCurve( EJSC.PiePoint point )
```

The object returned is formatted as:

```
{
    x: integer,
    y: integer
}
```

Description

This method takes a pie point (see getPoints) and returns an object containing the x and y screen coordinates of the center of the piece's arc.

4.4.13.2.3 getDataHandler (inherited)

Definition

EJSC.DataHandler getDataHandler()

Description

Returns the EJSC.DataHandler descendant currently assigned to the series. This is not applicable to all series and will return null if a data handler has not been defined or is not used.

4.4.13.2.4 getPoints

Definition

array getPoints()

Description

This method returns an array of all EJSC.PiePoint objects in the series.

4.4.13.2.5 getTotalValue

Definition

integer getTotalValue()

Description

Returns the current total value of the pie series. If the total_value property was set during creation or the setTotalValue has been called, the static value will be returned. If the series is set to calculate the total value based on the series data, the dynamic value will be returned.

4.4.13.2.6 getVisibility (inherited)

Definition

boolean getVisibility()

Description

Returns a boolean indicating the series current visible state

4.4.13.2.7 hide (inherited)

Definition

void hide()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already hidden.

4.4.13.2.8 hideLegend (inherited)

Definition

void hideLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already hidden.

4.4.13.2.9 reload (inherited)

Definition

void reload()

Description

Triggers a series reload if the functionality is defined in a child class. This may involve retrieving data again or simply recalculating. While the reload() method exists in the base Series class, implementation of the protected methods triggered by calling reload() is at the discretion of the child class.

4.4.13.2.10 resetTotalValue

Definition

void resetTotalValue(boolean redraw)

Description

This method causes the series to recalculate its total value based on the actual series data and optionally redraws the series to reflect the change.

To retrieve the total value after this method is called, use getTotalValue.

4.4.13.2.11 setDataHandler (inherited)

Definition

void **setDataHandler**(EJSC.DataHandler dataHandler, boolean reload)

Description

Updates the series data handler and triggers a data reload if reload parameter is **true**. This method may not be implemented in all child classes.

4.4.13.2.12 setDefaultColors

Definition

void setDefaultColors(array colors, boolean reload)

Description

Set the array of default colors available for pie pieces.

If reload = **true** the pie pieces (if loaded) will pull their colors from the given color array and the chart will be redrawn.

If onPieceNeedsColor is assigned, this method will ignore that event and load the colors from the array.

Example

myPieSeries.setDefaultColors(colors, true);

4.4.13.2.13 setLineWidth (inherited)

Definition

void setLineWidth(integer width)

Description

Updates the lineWidth property and redraws the chart.

4.4.13.2.14 setOpacity (inherited)

Definition

void setOpacity(integer opacity)

Description

Sets the EJSC.Series.opacity property and redraws the series to reflect the change.

4.4.13.2.15 setTitle (inherited)

Definition

```
void setTitle( string title )
```

Description

Changes the series title and update the legend caption (if applicable).

Note: this will not cause updates to a hint which is visible at the time it is called, though the next time a hint is rendered it will show the new property value.

4.4.13.2.16 setTotalValue

Definition

void setTotalValue(integer value, boolean redraw)

Description

Sets the total value of the pie series and optionally redraws the series to reflect the change.

To force the chart to calculate its total value based on the actual series data, call resetTotalValue.

4.4.13.2.17 show (inherited)

Definition

void show()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already visible.

4.4.13.2.18 showLegend (inherited)

Definition

void showLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already visible.

4.4.13.3 Events

4.4.13.3.1 onAfterDataAvailable (inherited)

Definition

boolean onAfterDataAvailable(EJSC.Chart chart, EJSC.Series series)

Description

Fired after the series has processed its data and before the chart is told to redraw. Returning **false** from this event handler will cancel redrawing the chart.

4.4.13.3.2 onAfterVisibilityChange (inherited)

Definition

boolean onAfterVisibilityChange(EJSC.Series series, EJSC.Chart chart, boolean visible)

Description

Fired when the series visibility changes. Sends series which changed, its owner chart and its new visible property value.

Returning false from this event handler will cancel redrawing the chart.

4.4.13.3.3 onBeforeVisibilityChange (inherited)

Definition

boolean onBeforeVisibilityChange(EJSC.Series series, EJSC.Chart chart)

Description

Fired before the series visibility is about to change. Sends series which changed, its owner chart. The current visible state of the series may be checked using the series visible property.

Returning false from this event handler will cancel the change in visibility.

4.4.13.3.4 onPieceNeedsColor

Definition

boolean onPieceNeedsColor(EJSC.PiePoint point, EJSC.PieSeries series, EJSC.Chart chart)

Description

If assigned, this event is triggered for each piece in a pie series immediately before it pulls a color from the default colors array. The event provides the EJSC.PiePoint object which represents the piece which needs a color, the EJSC.PieSeries which owns the piece and the EJSC.Chart which owns the series. Return a color string formatted as "rgb(<red value>, <green value>, <blue value>)", i.e. Orange would be "rgb(237,173,0)"

4.4.13.3.5 onShowHint (inherited)

Definition

string onShowHint(EJSC.Point point, EJSC.Series series, EJSC.Chart chart, string hint_string)

Description

Fired before the displaying the hint, this event allows the current hint string to be overridden. See Text Replacement Options for a list of the automatic substitutions available.

4.4.13.4 Data Formats

The x parameter is required, label and userdata are both optional.


XML (EJSC.XMLDataHandler, EJSC.XMLStringDataHandler):

Unused parameters may be omitted


Full:

```
<graph>
                                      <plot>
                                                      <point x="number or string"</pre>
label="string" userdata="string"/>
                                                      <point x="number or string"</pre>
label="string" userdata="string"/>
                                      </plot>
                       <graph>
       Short:
                       <G>
                                      <L>
                                                      <P x="number or string" label="string"
userdata="string"/>
                                                      <P x="number or string" label="string"
userdata="string"/>
                                      </L>
                       </G>
       Compact: The values parameter is formatted as CSV
                       <G>
                                      <L values="CSV string"/>
                       </G>
Array (EJSC.ArrayDataHandler):
       [
                       ["x", "label", "userdata"],
                       ["x", "label", "userdata"]
       1
       Null should be used to skip unused parameters:
       [
                       ["x", null, "userdata"],
                       ["x", null, "userdata"]
       ]
CSV (EJSC.CSVFileDataHandler, EJSC.CSVStringDataHandler):
       "x|label|userdata,x|label|userdata"
       Null should be used to skip unused parameters
       "x|null|userdata,x|null|userdata"
JSON (EJSC.JSONFileDataHandler, EJSC.JSONStringDataHandler):
       Unused parameters may be omitted.
```

4.4.13.5 Text Replacement Options



4.4.14 EJSC.ScatterSeries



ScatterSeries is rendered by drawing a styled point for each x,y coordinate in the dataset.

The constructor expects an instantiated EJSC.DataHandler descendant and an optional set of object properties.

Constructor

```
EJSC.ScatterSeries( EJSC.DataHandler dataHandler [, object options] )
```

Example

```
var mySeries = new EJSC.ScatterSeries(
          new EJSC.ArrayDataHandler([[1,1],[2,2],[3,3],[4,3],[5,2],[6,4]]),
          { title: "New Scatter Series" }
);
```

Defining Properties and Events

ScatterSeries properties may be set individually after the series has been created or in batch using the options parameter during instantiation.

Setting properties individually

```
var mySeries = new EJSC.ScatterSeries(new
EJSC.ArrayDataHandler([[1,1],[2,2],[3,3],[4,3],[5,2],[6,4]]));
   mySeries.pointSize = 3;
   mySeries.pointStyle = "diamond";
   mySeries.title = "New Scatter Series";
```

Setting properties in batch

4.4.14.1 Properties

4.4.14.1.1 autosort (inherited)

Definition

boolean autosort = true

Description

Defines whether the series applies the appropriate sort to points prior to drawing. Drawing routines are generally optimized to accept data in a certain order and this property eliminates the need for the developer to worry about that order prior to sending data to the series. If set to false, the data must be properly ordered beforehand in order to ensure the series renders correctly.

Note: May not be applicable to all series (i.e. EJSC.PieSeries, EJSC.AnalogGaugeSeries)

4.4.14.1.2 color (inherited)

Definition

string color = undefined

Description

Defines the series color. If left undefined, the color is pulled from the array of default colors stored in the chart.

Note: May not be applicable to all series (i.e. EJSC.PieSeries)

4.4.14.1.3 coloredLegend (inherited)

Definition

boolean coloredLegend = true

Description

Determines whether the legend text inherits the series color. Setting to false will allow the legend text to inherit its normal cascaded color. To modify this property after series creation see EJSC.Series.setColoredLegend()

4.4.14.1.4 delayLoad (inherited)

EXPERIMENTAL

Definition

boolean delayLoad = true

Description

This property allows a series to force its data handler to begin data retrieval as soon as it is added to a chart. When set to false, the series will initiate data retrieval as soon as it is added to a chart. When true, the data retrieval is initialized when the series first needs to draw.

4.4.14.1.5 hint_string (inherited)

Definition

string hint_string = undefined

Description

This property may be used to define a series specific string to be used when displaying point hints. This string may contain replacement indicators (see Text Replacement Options). When left undefined, a default hint defined by the series type will be displayed.

Example

>> Modify the default hint to include custom text.

4.4.14.1.6 legendlsVisible (inherited)

Definition

boolean legendls Visible = true

Description

Determines whether the legend item associated with the series appears in the legend window. Use the Series.showLegend and Series.hideLegend methods to control legend item visibility after series

creation.

4.4.14.1.7 lineOpacity (inherited)

Definition

integer lineOpacity = 100

Description

Determines the line opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setLineOpacity()

4.4.14.1.8 lineWidth (inherited)

Definition

integer lineWidth = 1

Description

Defines the width of the line connecting series points.

4.4.14.1.9 opacity (inherited)

Definition

integer opacity = 50

Description

Determines the fill opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setOpacity()

4.4.14.1.10 padding (inherited)

Definition

```
object padding = {
    x_axis_min: undefined,
    x_axis_max: undefined,
    y_axis_min: undefined,
    y_axis_max: undefined
}
```

Description

The padding property may be used to override the series default padding. Padding is the amount of pixels added to the min and max series values in order to push the extremes and prevent the series from hitting the edge of the chart.

The amount of default padding is dependent upon the series type and axis configuration and may not

be applicable to all series types.

This property is only applicable during series creation. To retrieve or modify the series padding after creation please see Series.getPadding() and Series.setPadding()

Example

>> Remove all padding from the BarSeries

4.4.14.1.11 pointSize

Definition

integer pointSize = 4

Description

Defines the size of the point to be drawn. Point size has no effect on point selection. In order to increase the distance from the actual coordinate that a click will select or hover a point, see EJSC.Chart.proximity_snap

4.4.14.1.12 pointStyle

Definition

```
string pointStyle = "triangle"

Styles:
    triangle
    box
    circle
    diamond
```

Description

Defines the shape of the point to be drawn. Point shape has no effect on point selection. In order to increase the distance from the actual coordinate that a click will select or hover a point, see EJSC.Chart.proximity_snap

4.4.14.1.13 title (inherited)

Definition

```
string title = "Series <index>"
```

Description

Defines the series title used in hints and legend display.

Note: The default title of Series <index> (where <index> equals the current position in the series array for its owner chart) is assigned when a series is added to a chart using addSeries. This default title is only applied if the title is blank (i.e. "") at the time the addSeries method is called.

4.4.14.1.14 visible (inherited)

Definition

boolean visible = true

Description

Defines whether the series is visible and can draw on the chart

4.4.14.1.15 x_axis (inherited)

Definition

```
string x_axis = "bottom"
```

Description

Defines the horizontal axis to use for X values. Valid options are "top" or "bottom".

4.4.14.1.16 x_axis_formatter (inherited)

Definition

```
string x_axis_formatter = undefined
```

Description

Defines the formatter that will be used to format hints for the X values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

Types:

EJSC.DateFormatter

EJSC.NumberFormatter

4.4.14.1.17 y_axis (inherited)

Definition

```
string y_axis = "left"
```

Description

Defines the vertical axis to use for Y values. Valid options are "left" or "right".

4.4.14.1.18 y_axis_formatter (inherited)

Definition

string y_axis_formatter = undefined

Description

Defines the formatter that will be used to format hints for the Y values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

```
Types: EJSC.DateFormatter EJSC.NumberFormatter
```

4.4.14.2 Methods

4.4.14.2.1 findClosestByPixel (inherited)

Definition

Description

Returns the point object closest to the screen pixel coordinates provided. The x and y properties of the point object should be in the same scale as the x and y axes assigned to the series. To locate points based on pixel coordinates, see Series.findClosestByPixel()

4.4.14.2.2 findClosestByPoint (inherited)

Definition

Description

Returns the point object closest to the axis coordinates provided. The x and y properties of the coordinate object should be based on the top left of the viewport and take into account the page scroll. To locate points based on axis coordinates, see Series.findClosestByPoint()

4.4.14.2.3 getDataHandler (inherited)

Definition

EJSC.DataHandler getDataHandler()

Description

Returns the EJSC.DataHandler descendant currently assigned to the series. This is not applicable to all series and will return null if a data handler has not been defined or is not used.

4.4.14.2.4 getPadding (inherited)

Definition

Description

Returns an object containing the series current padding. If padding has been set either by the Series.setPadding() method of the Series.padding property during construction the result of this method will be adjusted to return the most current padding values.

4.4.14.2.5 getVisibility (inherited)

Definition

boolean getVisibility()

Description

Returns a boolean indicating the series current visible state

4.4.14.2.6 hide (inherited)

Definition

void hide()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already hidden.

4.4.14.2.7 hideLegend (inherited)

Definition

void hideLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already hidden.

4.4.14.2.8 reload (inherited)

Definition

void reload()

Description

Triggers a series reload if the functionality is defined in a child class. This may involve retrieving data again or simply recalculating. While the reload() method exists in the base Series class, implementation of the protected methods triggered by calling reload() is at the discretion of the child class.

4.4.14.2.9 setColor (inherited)

Definition

void setColor(string color)

Description

Changes the series color and causes the chart to redraw.

4.4.14.2.10 setColoredLegend (inherited)

Definition

void setColoredLegend(boolean coloredLegend)

Description

Sets the EJSC.Series.coloredLegend property and updates the legend to reflect the change.

4.4.14.2.11 setDataHandler (inherited)

Definition

void setDataHandler(EJSC.DataHandler dataHandler, boolean reload)

Description

Updates the series data handler and triggers a data reload if reload parameter is **true**. This method may not be implemented in all child classes.

4.4.14.2.12 setLineOpacity (inherited)

Definition

void **setLineOpacity**(integer opacity)

Description

Sets the EJSC.Series.lineOpacity property and redraws the series to reflect the change.

4.4.14.2.13 setLineWidth (inherited)

Definition

void setLineWidth(integer width)

Description

Updates the lineWidth property and redraws the chart.

4.4.14.2.14 setOpacity (inherited)

Definition

void setOpacity(integer opacity)

Description

Sets the EJSC.Series.opacity property and redraws the series to reflect the change.

4.4.14.2.15 setPadding (inherited)

Definition

void **setPadding**(object Padding, boolean Redraw)

The padding object should be defined as when used in the series constructor. See Series padding.

Description

This method updates the user-defined series padding and optionally recalculates the chart extremes and redraws the chart.

4.4.14.2.16 setPointStyle

Definition

void setPointStyle(integer size, string style)

Description

Updates the pointSize and/or pointStyle and redraws the chart. Size or style update may be avoided by sending undefined.

See EJSC.ScatterSeries.pointStyle for a list of available styles.

Example

>> Update the size and style of scatter series points

mySeries.setPointStyle(5, "diamond");

>> Update only the style of scatter series points

mySeries.setPointStyle(undefined, "box");

4.4.14.2.17 setTitle (inherited)

Definition

void setTitle(string title)

Description

Changes the series title and update the legend caption (if applicable).

Note: this will not cause updates to a hint which is visible at the time it is called, though the next time a hint is rendered it will show the new property value.

4.4.14.2.18 show (inherited)

Definition

void show()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already visible.

4.4.14.2.19 showLegend (inherited)

Definition

void showLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already visible.

4.4.14.3 Events

4.4.14.3.1 onAfterDataAvailable (inherited)

Definition

boolean onAfterDataAvailable(EJSC.Chart chart, EJSC.Series series)

Description

Fired after the series has processed its data and before the chart is told to redraw. Returning **false** from this event handler will cancel redrawing the chart.

4.4.14.3.2 onAfterVisibilityChange (inherited)

Definition

boolean onAfterVisibilityChange(EJSC.Series series, EJSC.Chart chart, boolean visible)

Description

Fired when the series visibility changes. Sends series which changed, its owner chart and its new visible property value.

Returning **false** from this event handler will cancel redrawing the chart.

4.4.14.3.3 onBeforeVisibilityChange (inherited)

Definition

boolean onBeforeVisibilityChange(EJSC.Series series, EJSC.Chart chart)

Description

Fired before the series visibility is about to change. Sends series which changed, its owner chart. The current visible state of the series may be checked using the series visible property.

Returning false from this event handler will cancel the change in visibility.

4.4.14.3.4 onShowHint (inherited)

Definition

string onShowHint(EJSC.Point point, EJSC.Series series, EJSC.Chart chart, string hint_string)

Description

Fired before the displaying the hint, this event allows the current hint string to be overridden. See Text Replacement Options for a list of the automatic substitutions available.

4.4.14.4 Data Formats

The x and y parameters are required, label and userdata are both optional.

XML (EJSC.XMLDataHandler, EJSC.XMLStringDataHandler):

Unused parameters may be omitted

Full:

Short: <G> <L> <P x="number or string" y="number or string" label="string" userdata="string"/> <P x="number or string" y="number or string" label="string" userdata="string"/> </L> </G> **Compact:** The values parameter is formatted as CSV <G> <L values="CSV string"/> </G> Array (EJSC.ArrayDataHandler): [["x", "y", "label", "userdata"], ["x", "y", "label", "userdata"] 1 Null should be used to skip unused parameters: [["x", "y", null, "userdata"], ["x", "y", null, "userdata"] 1 CSV (EJSC.CSVFileDataHandler, EJSC.CSVStringDataHandler): "x|y|label|userdata,x|y|label|userdata" Null should be used to skip unused parameters "x|y|null|userdata,x|y|null|userdata" **JSON** (EJSC.JSONFileDataHandler, EJSC.JSONStringDataHandler): Unused parameters may be omitted.

{"x":"number or string","y":"number or

{"x":"number or string", "y": "number or

string","label":"string","userdata":"string"},

string","label":"string","userdata":"string"}


Ε

1

4.4.14.5 Text Replacement Options

String	With
[chart_title]	title of the chart
[series_title]	title of the series the selected
	point resides in
[xaxis]	caption of the series x axis
[yaxis] [x]	caption of the series y axis
[x]	preformatted X value of the
	point
[y]	preformatted Y value of the
	point
[label]	label property of the current
	point

4.4.15 EJSC.StepSeries



The StepSeries is rendered similar to the LineSeries, but the line "steps" (ie it only changes Y values at the next point's X value).

The constructor expects an instantiated EJSC.DataHandler descendant and an optional set of object properties.

Constructor

```
{\tt EJSC.StepSeries(\ EJSC.DataHandler\ dataHandler,\ \{object\ options\}\ )}
```

Example

Defining Properties and Events

StepSeries properties may be set individually after the series has been created or in batch using the options parameter during instantiation.

Setting properties individually

```
var mySeries = new EJSC.StepSeries(new
EJSC.ArrayDataHandler([[1,1],[2,2],[3,3],[4,3],[5,2],[6,4]]));
   StepSeries.lineWidth = 2;
   StepSeries.title = "New Step Series";
```

Setting properties in batch

4.4.15.1 Properties

4.4.15.1.1 autosort (inherited)

Definition

boolean autosort = true

Description

Defines whether the series applies the appropriate sort to points prior to drawing. Drawing routines are generally optimized to accept data in a certain order and this property eliminates the need for the developer to worry about that order prior to sending data to the series. If set to false, the data must be properly ordered beforehand in order to ensure the series renders correctly.

Note: May not be applicable to all series (i.e. EJSC.PieSeries, EJSC.AnalogGaugeSeries)

4.4.15.1.2 color (inherited)

Definition

string color = undefined

Description

Defines the series color. If left undefined, the color is pulled from the array of default colors stored in the chart.

Note: May not be applicable to all series (i.e. EJSC.PieSeries)

4.4.15.1.3 coloredLegend (inherited)

Definition

boolean coloredLegend = true

Description

Determines whether the legend text inherits the series color. Setting to false will allow the legend text to inherit its normal cascaded color. To modify this property after series creation see EJSC.Series.setColoredLegend()

4.4.15.1.4 drawPoints (inherited)

Definition

boolean drawPoints = false

Description

Determines whether the individual points in the series are visually indicated by round dots on the chart. The size and color of the fill and border are determined by the pointColor, pointSize, pointBorderColor and pointBorderSize properties.

Note: Setting this property to true for series which have a large number of points may impact performance as additional draws are required to render the points.

4.4.15.1.5 hint_string (inherited)

Definition

string hint_string = undefined

Description

This property may be used to define a series specific string to be used when displaying point hints. This string may contain replacement indicators (see Text Replacement Options). When left undefined, a default hint defined by the series type will be displayed.

Example

>> Modify the default hint to include custom text.

4.4.15.1.6 legendlsVisible (inherited)

Definition

boolean legendlsVisible = true

Description

Determines whether the legend item associated with the series appears in the legend window. Use the Series.showLegend and Series.hideLegend methods to control legend item visibility after series creation.

4.4.15.1.7 lineOpacity (inherited)

Definition

integer lineOpacity = 100

Description

Determines the line opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setLineOpacity()

4.4.15.1.8 lineWidth (inherited)

Definition

integer lineWidth = 1

Description

Defines the width of the line connecting series points.

4.4.15.1.9 padding (inherited)

Definition

```
object padding = {
    x_axis_min: undefined,
    x_axis_max: undefined,
    y_axis_min: undefined,
    y_axis_max: undefined
}
```

Description

The padding property may be used to override the series default padding. Padding is the amount of pixels added to the min and max series values in order to push the extremes and prevent the series from hitting the edge of the chart.

The amount of default padding is dependant upon the series type and axis configuration and may not be applicable to all series types.

This property is only applicable during series creation. To retrieve or modify the series padding after creation please see Series.getPadding() and Series.setPadding()

Example

>> Remove all padding from the BarSeries

4.4.15.1.10 pointBorderColor (inherited)

Definition

string **pointBorderColor** = "rgb(255,255,255)"

Description

Defines the color of the border drawn around the points. This property is only applicable when the series drawPoints property is set to true and pointBorderSize is greater than 0.

4.4.15.1.11 pointBorderSize (inherited)

Definition

integer pointBorderSize = 0

Description

Defines the size in pixels of the border drawn around the points. This property is only applicable when the series.drawPoints property is set to true.

To draw points without any border, leave pointBorderSize set to 0.

4.4.15.1.12 pointColor (inherited)

Definition

string pointColor = undefined

Description

Defines the color of the point (circle) drawn at each data point in the series. If left undefined the point will inherit the series color.

This property is only applicable when the series.drawPoints property is set to true.

4.4.15.1.13 pointSize (inherited)

Definition

integer pointSize = undefined

Description

Defines the size of the point (circle) drawn at each data point in the series. If left undefined the point diameter will be twice the line width of the series.

This property is only applicable when the series.drawPoints property is set to true.

4.4.15.1.14 title (inherited)

Definition

string title = "Series <index>"

Description

Defines the series title used in hints and legend display.

Note: The default title of Series <index> (where <index> equals the current position in the series array for its owner chart) is assigned when a series is added to a chart using addSeries. This default title is only applied if the title is blank (i.e. "") at the time the addSeries method is called.

4.4.15.1.15 visible (inherited)

Definition

boolean visible = true

Description

Defines whether the series is visible and can draw on the chart

4.4.15.1.16 x_axis (inherited)

Definition

```
string x_axis = "bottom"
```

Description

Defines the horizontal axis to use for X values. Valid options are "top" or "bottom".

4.4.15.1.17 x_axis_formatter (inherited)

Definition

```
string x_axis_formatter = undefined
```

Description

Defines the formatter that will be used to format hints for the X values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

Types: EJSC.DateFormatter EJSC.NumberFormatter

4.4.15.1.18 y_axis (inherited)

Definition

```
string y_axis = "left"
```

Description

Defines the vertical axis to use for Y values. Valid options are "left" or "right".

4.4.15.1.19 y_axis_formatter (inherited)

Definition

```
string y_axis_formatter = undefined
```

Description

Defines the formatter that will be used to format hints for the Y values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

```
Types: EJSC.DateFormatter EJSC.NumberFormatter
```

4.4.15.2 Methods

4.4.15.2.1 findClosestByPoint (inherited)

Definition

Description

Returns the point object closest to the axis coordinates provided. The x and y properties of the coordinate object should be based on the top left of the viewport and take into account the page scroll. To locate points based on axis coordinates, see Series.findClosestByPoint()

4.4.15.2.2 findClosestByPixel (inherited)

Definition

Description

Returns the point object closest to the screen pixel coordinates provided. The x and y properties of the point object should be in the same scale as the x and y axes assigned to the series. To locate points based on pixel coordinates, see Series.findClosestByPixel()

4.4.15.2.3 getDataHandler (inherited)

Definition

EJSC.DataHandler getDataHandler()

Description

Returns the EJSC.DataHandler descendant currently assigned to the series. This is not applicable to all series and will return null if a data handler has not been defined or is not used.

4.4.15.2.4 getPadding (inherited)

Definition

Description

Returns an object containing the series current padding. If padding has been set either by the Series.setPadding() method of the Series.padding property during construction the result of this method will be adjusted to return the most current padding values.

4.4.15.2.5 getVisibility (inherited)

Definition

boolean getVisibility()

Description

Returns a boolean indicating the series current visible state

4.4.15.2.6 hide (inherited)

Definition

void hide()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already hidden.

4.4.15.2.7 hideLegend (inherited)

Definition

void hideLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already hidden.

4.4.15.2.8 reload (inherited)

Definition

void reload()

Description

Triggers a series reload if the functionality is defined in a child class. This may involve retrieving data again or simply recalculating. While the reload() method exists in the base Series class, implementation of the protected methods triggered by calling reload() is at the discretion of the child class.

4.4.15.2.9 setColor (inherited)

Definition

void setColor(string color)

Description

Changes the series color and causes the chart to redraw.

4.4.15.2.10 setColoredLegend (inherited)

Definition

void **setColoredLegend**(boolean coloredLegend)

Description

Sets the EJSC.Series.coloredLegend property and updates the legend to reflect the change.

4.4.15.2.11 setDataHandler (inherited)

Definition

void **setDataHandler**(EJSC.DataHandler dataHandler, boolean reload)

Description

Updates the series data handler and triggers a data reload if reload parameter is true. This method

may not be implemented in all child classes.

4.4.15.2.12 setLineOpacity (inherited)

Definition

void setLineOpacity(integer opacity)

Description

Sets the EJSC.Series.lineOpacity property and redraws the series to reflect the change.

4.4.15.2.13 setLineWidth (inherited)

Definition

void setLineWidth(integer width)

Description

Updates the lineWidth property and redraws the chart.

4.4.15.2.14 setPadding (inherited)

Definition

void **setPadding**(object Padding, boolean Redraw)

The padding object should be defined as when used in the series constructor. See Series padding.

Description

This method updates the user-defined series padding and optionally recalculates the chart extremes and redraws the chart.

4.4.15.2.15 setTitle (inherited)

Definition

void setTitle(string title)

Description

Changes the series title and update the legend caption (if applicable).

Note: this will not cause updates to a hint which is visible at the time it is called, though the next time a hint is rendered it will show the new property value.

4.4.15.2.16 show (inherited)

Definition

void show()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already visible.

4.4.15.2.17 showLegend (inherited)

Definition

void showLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already visible.

4.4.15.3 Events

4.4.15.3.1 onAfterDataAvailable (inherited)

Definition

boolean onAfterDataAvailable(EJSC.Chart chart, EJSC.Series series)

Description

Fired after the series has processed its data and before the chart is told to redraw. Returning **false** from this event handler will cancel redrawing the chart.

4.4.15.3.2 onAfterVisibilityChange (inherited)

Definition

boolean onAfterVisibilityChange(EJSC.Series series, EJSC.Chart chart, boolean visible)

Description

Fired when the series visibility changes. Sends series which changed, its owner chart and its new visible property value.

Returning **false** from this event handler will cancel redrawing the chart.

4.4.15.3.3 onBeforeVisibilityChange (inherited)

Definition

boolean onBeforeVisibilityChange(EJSC.Series series, EJSC.Chart chart)

Description

Fired before the series visibility is about to change. Sends series which changed, its owner chart. The current visible state of the series may be checked using the series visible property.

Returning false from this event handler will cancel the change in visibility.

4.4.15.3.4 onShowHint (inherited)

Definition

string onShowHint(EJSC.Point point, EJSC.Series series, EJSC.Chart chart, string hint_string)

Description

Fired before the displaying the hint, this event allows the current hint string to be overridden. See Text Replacement Options for a list of the automatic substitutions available.

4.4.15.4 Text Replacement Options

String	with
[chart_title]	title of the chart
[series_title]	title of the series the selected
. – .	point resides in
[xaxis] [yaxis] [x]	caption of the series x axis caption of the series y axis preformatted X value of the
[^]	point
[y]	preformatted Y value of the
[label]	point label property of the current
	point

4.4.15.5 Data Formats

The x and y parameters are required, label and userdata are both optional.


XML (EJSC.XMLDataHandler, EJSC.XMLStringDataHandler):

Unused parameters may be omitted

Full:

```
string" label="string" userdata="string"/>
                      </G>
       Compact: The values parameter is formatted as CSV
                      <G>
                                    <L values="CSV string"/>
                      </G>
Array (EJSC.ArrayDataHandler):
       [
                     ["x", "y", "label", "userdata"],
                     ["x", "y", "label", "userdata"]
       1
       Null should be used to skip unused parameters:
       [
                      ["x", "y", null, "userdata"],
                     ["x", "y", null, "userdata"]
       1
CSV (EJSC.CSVFileDataHandler, EJSC.CSVStringDataHandler):
       "x|y|label|userdata,x|y|label|userdata"
       Null should be used to skip unused parameters
       "x|y|null|userdata,x|y|null|userdata"
JSON (EJSC.JSONFileDataHandler, EJSC.JSONStringDataHandler):
       Unused parameters may be omitted.
       Ε
                      {"x":"number or string","y":"number or
string","label":"string","userdata":"string"},
                      {"x":"number or string","y":"number or
string","label":"string","userdata":"string"}
       1
```

4.4.16 EJSC.StackedBarSeries



StackedBarSeries renders its points as vertical or horizontal bars which are stacked on the previous series.

The constructor expects an instantiated EJSC.DataHandler descendant and an optional set of object properties.

Constructor

```
EJSC.StackedBarSeries( EJSC.DataHandler dataHandler [, object options] )
```

Example

Defining Properties and Events

FloatingBarSeries properties may be set individually after the series has been created or in batch using the options parameter during instantiation.

Setting properties individually

```
var myStackedSeries1 = new EJSC.StackedBarSeries(new EJSC.ArrayDataHandler([[1,1],[2,2],[3,3]
myStackedSeries1.lineWidth = 1;
myStackedSeries1.title = "Bottom Stack";

var myStackedSeries2 = new EJSC.StackedBarSeries(new EJSC.ArrayDataHandler([[1,1],[2,2],[3,3]
myStackedSeries2.lineWidth = 1;
myStackedSeries2.title = "Top Stack";
```

Setting properties in batch

4.4.16.1 Properties

4.4.16.1.1 autosort (inherited)

Definition

boolean autosort = true

Description

Defines whether the series applies the appropriate sort to points prior to drawing. Drawing routines are generally optimized to accept data in a certain order and this property eliminates the need for the developer to worry about that order prior to sending data to the series. If set to false, the data must be properly ordered beforehand in order to ensure the series renders correctly.

Note: May not be applicable to all series (i.e. EJSC.PieSeries, EJSC.AnalogGaugeSeries)

4.4.16.1.2 color (inherited)

Definition

string color = undefined

Description

Defines the series color. If left undefined, the color is pulled from the array of default colors stored in the chart.

Note: May not be applicable to all series (i.e. EJSC.PieSeries)

4.4.16.1.3 coloredLegend (inherited)

Definition

boolean coloredLegend = true

Description

Determines whether the legend text inherits the series color. Setting to false will allow the legend text to inherit its normal cascaded color. To modify this property after series creation see EJSC.Series.setColoredLegend()

4.4.16.1.4 defaultColors (inherited)

Definition

array defaultColors = EJSC.DefaultBarColors

Description

Defines the pool of default colors available for bar series bars.

NOTE: To make use of individually colored bars, the EJSC.BarSeries.useColorArray property must be set to true.

4.4.16.1.5 delayLoad (inherited)

EXPERIMENTAL

Definition

boolean delayLoad = true

Description

This property allows a series to force its data handler to begin data retrieval as soon as it is added to a chart. When set to false, the series will initiate data retrieval as soon as it is added to a chart. When true, the data retrieval is initialized when the series first needs to draw.

4.4.16.1.6 groupedBars (inherited)

Definition

boolean groupedBars = true

Description

Defines whether the bars from different bar series in a single chart are grouped or overlayed.

NOTE: Only the first bar series added to the chart may use this property to affect the grouped/overlay display. To change the style after the first bar series has been added, use the EJSC.BarSeries.setGroupedBars from any bar series in the chart. Currently you cannot mix both overlayed and grouped bars within the same chart.

Example

>> Make the bar series overlay

4.4.16.1.7 hint_string (inherited)

Definition

string hint_string = undefined

Description

This property may be used to define a series specific string to be used when displaying point hints. This string may contain replacement indicators (see Text Replacement Options). When left undefined, a default hint defined by the series type will be displayed.

Example

>> Modify the default hint to include custom text.

4.4.16.1.8 intervalOffset (inherited)

Definition

float intervalOffset = 0.8

Description

Defines the spacing between the bars as a percentage of 1. 1 = bars take up the entire width available, with their sides touching.

Example

>> Make the bars take up 1/2 their available width. (i.e. more space between bars than by default)

```
var chart = new EJSC.Chart("chart");
var bar = chart.addSeries(new EJSC.BarSeries(
    data,
    {
        intervalOffset: 0.5
    }
));
```

4.4.16.1.9 legendlsVisible (inherited)

Definition

boolean legendls Visible = true

Description

Determines whether the legend item associated with the series appears in the legend window. Use the Series.showLegend and Series.hideLegend methods to control legend item visibility after series creation.

4.4.16.1.10 lineOpacity (inherited)

Definition

integer lineOpacity = 100

Description

Determines the line opacity (if applicable) of the series. The range is a percentage and should be

specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setLineOpacity()

4.4.16.1.11 lineWidth (inherited)

Definition

integer lineWidth = 1

Description

Defines the width of the line connecting series points.

4.4.16.1.12 opacity (inherited)

Definition

integer opacity = 50

Description

Determines the fill opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setOpacity()

4.4.16.1.13 orientation (inherited)

Definition

string orientation = "vertical"

Description

This property determines the orientation of the bar series. The supported property values are "vertical" and "horizontal".

Note: Currently this is a creation-time only property and should not be changed after the series has been created.

4.4.16.1.14 padding (inherited)

Definition

```
object padding = {
     x_axis_min: undefined,
     x_axis_max: undefined,
     y_axis_min: undefined,
     y_axis_max: undefined
}
```

Description

The padding property may be used to override the series default padding. Padding is the amount of

pixels added to the min and max series values in order to push the extremes and prevent the series from hitting the edge of the chart.

The amount of default padding is dependant upon the series type and axis configuration and may not be applicable to all series types.

This property is only applicable during series creation. To retrieve or modify the series padding after creation please see Series.getPadding() and Series.setPadding()

Example

>> Remove all padding from the BarSeries

4.4.16.1.15 ranges (inherited)

Definition

```
array ranges = new Array()
```

Description

This property is used to store the ranges for a given bar series. The range objects are used to draw bars in varying styles based on their Y value.

The range objects stored are defined as:

Example

>> Define ranges so that bars with a Y value from 0 to 10 and 90 to 100 are colored red, bars 10 - 90 are colored green

));

4.4.16.1.16 title (inherited)

Definition

string title = "Series <index>"

Description

Defines the series title used in hints and legend display.

Note: The default title of Series <index> (where <index> equals the current position in the series array for its owner chart) is assigned when a series is added to a chart using addSeries. This default title is only applied if the title is blank (i.e. "") at the time the addSeries method is called.

4.4.16.1.17 treeLegend (inherited)

Definition

boolean treeLegend = false

Description

Defines whether to display each bar individually in the legend.

If the useColorArray property is true and treeLegend left at its default (not defined in options), the treeLegend property will automatically be set to true to enable tree-style legend display.

4.4.16.1.18 treeLegendRoot

Definition

boolean treeLegendRoot = false

Description

Defines whether to display the stacked series as a top level node in the legend with each bar series shown as a child below.

4.4.16.1.19 useColorArray (inherited)

Definition

boolean useColorArray = false

Description

Defines whether to make use of the EJSC.BarSeries.defaultColors property

Example

>> Use the color array to make a chart of multi colored bars

```
var chart = new EJSC.Chart("chart");
```

```
var bar = chart.addSeries(new EJSC.BarSeries(
    data,
    {
        useColorArray: true
    }
));
```

4.4.16.1.20 visible (inherited)

Definition

boolean visible = true

Description

Defines whether the series is visible and can draw on the chart

4.4.16.1.21 x_axis (inherited)

Definition

```
string x_axis = "bottom"
```

Description

Defines the horizontal axis to use for X values. Valid options are "top" or "bottom".

4.4.16.1.22 x_axis_formatter (inherited)

Definition

```
string x_axis_formatter = undefined
```

Description

Defines the formatter that will be used to format hints for the X values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

```
Types: EJSC.DateFormatter EJSC.NumberFormatter
```

4.4.16.1.23 y_axis (inherited)

Definition

```
string y_axis = "left"
```

Description

Defines the vertical axis to use for Y values. Valid options are "left" or "right".

4.4.16.1.24 y_axis_formatter (inherited)

Definition

string y_axis_formatter = undefined

Description

Defines the formatter that will be used to format hints for the Y values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

Types: EJSC.DateFormatter EJSC.NumberFormatter

4.4.16.2 Methods

4.4.16.2.1 addRange (inherited)

Definition

void **addRange**(float min, float max, string color, integer opacity, integer lineOpacity, integer lineWidth, boolean redraw)

Description

Adds a new range to the bar series and optionally triggers a redraw.

4.4.16.2.2 addSeries

Definition

EJSC.BarSeries addSeries (EJSC.BarSeries series, boolean redraw)

Description

Adds a new series to the stacked bar series and returns the newly added series (this is useful when creating series inline as shown in the example below). The series must be a EJSC.BarSeries and have the same orientation as the stacked bar series being added to..

If redraw is false, drawing will not occur immediately but will not be entirely prevented. Certain actions such as adding an additional series with redraw = true, or chart dimensions changing may still trigger the series to draw. The default, if redraw is omitted is **true**.

Note: If the series has not defined a title (i.e. Series.title = "") at the time addSeries is called, a default title of "Series <index>" will be assigned (where <index> is the current series index in internal series storage).

Example

>> Add new bar series to an existing stacked bar series.

```
var myChart = new EJSC.Chart("chart");
var myStackedSeries = myChart.addSeries(new EJSC.StackedBarSeries(data, { }));

var myBarSeries1 = myStackedSeries.addSeries(new EJSC.BarSeries(...));
var myBarSeries2 = myStackedSeries.addSeries(new EJSC.BarSeries(...));
var myBarSeries3 = myStackedSeries.addSeries(new EJSC.BarSeries(...));
var myBarSeries4 = myStackedSeries.addSeries(new EJSC.BarSeries(...));
var myBarSeries5 = myStackedSeries.addSeries(new EJSC.BarSeries(...));
```

4.4.16.2.3 clearRanges (inherited)

Definition

void clearRanges (boolean redraw)

Description

Clears all ranges defined for the series and optionally redraws the the chart.

4.4.16.2.4 deleteRange (inherited)

Definition

void deleteRange(float min, float max, boolean redraw)

Description

Deletes the matching range (min and max must exactly match an existing range) and optionally redraws the chart.

4.4.16.2.5 findClosestByPixel (inherited)

Definition

```
EJSC.Point findClosestByPixel( object coordinates )
point = {
            x: screen coordinate,
            y: screen coordinate
}
```

Description

Returns the point object closest to the screen pixel coordinates provided. The x and y properties of the point object should be in the same scale as the x and y axes assigned to the series. To locate points based on pixel coordinates, see Series.findClosestByPixel()

4.4.16.2.6 findClosestByPoint (inherited)

Definition

Description

Returns the point object closest to the axis coordinates provided. The x and y properties of the coordinate object should be based on the top left of the viewport and take into account the page scroll.

To locate points based on axis coordinates, see Series.findClosestByPoint()

4.4.16.2.7 getBarSize (inherited)

Definition

integer getBarSize()

Description

This method returns the size in pixels (width or height depending on orientation) of a single bar.

4.4.16.2.8 getBarSizeInPoints (inherited)

Definition

integer getBarSizeInPoints()

Description

This method returns the size in chart points (width or height depending on orientation) of a single bar.

4.4.16.2.9 getDataHandler (inherited)

Definition

EJSC.DataHandler getDataHandler()

Description

Returns the EJSC.DataHandler descendant currently assigned to the series. This is not applicable to all series and will return null if a data handler has not been defined or is not used.

4.4.16.2.10 getPadding (inherited)

Enter topic text here.

4.4.16.2.11 getPoints (inherited)

Definition

array getPoints()

Description

This method returns an array of all EJSC.BarPoint objects in the series.

4.4.16.2.12 getVisibility (inherited)

Definition

boolean getVisibility()

Description

Returns a boolean indicating the series current visible state

4.4.16.2.13 hide (inherited)

Definition

void hide()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already hidden.

4.4.16.2.14 hideLegend (inherited)

Definition

void hideLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already hidden.

4.4.16.2.15 reload (inherited)

Definition

void reload()

Description

Triggers a series reload if the functionality is defined in a child class. This may involve retrieving data again or simply recalculating. While the reload() method exists in the base Series class, implementation of the protected methods triggered by calling reload() is at the discretion of the child class.

4.4.16.2.16 removeSeries

Definition

void removeSeries (EJSC.BarSeries series, boolean redraw)

Description

Removes the specified series from the stacked bar series and triggers an immediate rescaling and redraw. Send in redraw = false if performing multiple removes and want to delay redrawing until complete.

4.4.16.2.17 setColor (inherited)

Definition

void setColor(string color)

Description

Changes the series color and causes the chart to redraw.

4.4.16.2.18 setColoredLegend (inherited)

Definition

void setColoredLegend(boolean coloredLegend)

Description

Sets the EJSC.Series.coloredLegend property and updates the legend to reflect the change.

4.4.16.2.19 setDataHandler (inherited)

Definition

void setDataHandler(EJSC.DataHandler dataHandler, boolean reload)

Description

Updates the series data handler and triggers a data reload if reload parameter is **true**. This method may not be implemented in all child classes.

4.4.16.2.20 setDefaultColors (inherited)

Definition

void setDefaultColors(array colors, boolean reload)

Description

Set the array of default colors available for bar series bars.

If reload = **true** the bars (if loaded) will pull their colors from the given color array and the chart will be redrawn.

If onBarNeedsColor is assigned, this method will ignore that event and load the colors from the array.

Example

myBarSeries.setDefaultColors(colors, true);

4.4.16.2.21 setGroupedBars (inherited)

Definition

void setGroupedBars(boolean grouped, boolean redraw)

Description

Changes the chart between grouped and overlayed bars and optionally triggers a redraw.

4.4.16.2.22 setIntervalOffset (inherited)

Definition

void setIntervalOffset(float offset, boolean redraw)

Description

Updates the interval offset property (spacing between the bars) and optionally redraws the chart. See EJSC.BarSeries.intervalOffset for additional information.

4.4.16.2.23 setLineOpacity (inherited)

Definition

void setLineOpacity(integer opacity)

Description

Sets the EJSC.Series.lineOpacity property and redraws the series to reflect the change.

4.4.16.2.24 setLineWidth (inherited)

Definition

void setLineWidth(integer width)

Description

Updates the lineWidth property and redraws the chart.

4.4.16.2.25 setOpacity (inherited)

Definition

void **setOpacity**(integer opacity)

Description

Sets the EJSC. Series opacity property and redraws the series to reflect the change.

4.4.16.2.26 setPadding (inherited)

Definition

void **setPadding**(object Padding, boolean Redraw)

The padding object should be defined as when used in the series constructor. See Series.padding.

Description

This method updates the user-defined series padding and optionally recalculates the chart extremes and redraws the chart.

4.4.16.2.27 setTitle (inherited)

Definition

void setTitle(string title)

Description

Changes the series title and update the legend caption (if applicable).

Note: this will not cause updates to a hint which is visible at the time it is called, though the next time a hint is rendered it will show the new property value.

4.4.16.2.28 show (inherited)

Definition

void show()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already visible.

4.4.16.2.29 showLegend (inherited)

Definition

void showLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already visible.

4.4.16.3 Events

4.4.16.3.1 onAfterDataAvailable (inherited)

Definition

boolean onAfterDataAvailable(EJSC.Chart chart, EJSC.Series series)

Description

Fired after the series has processed its data and before the chart is told to redraw. Returning **false** from this event handler will cancel redrawing the chart.

4.4.16.3.2 onAfterVisibilityChange (inherited)

Definition

boolean onAfterVisibilityChange(EJSC.Series series, EJSC.Chart chart, boolean visible)

Description

Fired when the series visibility changes. Sends series which changed, its owner chart and its new visible property value.

Returning false from this event handler will cancel redrawing the chart.

4.4.16.3.3 onBarNeedsColor (inherited)

Definition

string **onBarNeedsColor**(EJSC.BarPoint point, EJSC.Series series, EJSC.Chart chart) object **onBarNeedsColor**(EJSC.BarPoint point, EJSC.Series series, EJSC.Chart chart)

Description

Fired when a bar needs a color. This event may return either a string (i.e. "rgb(0,255,0)") or an object with additional styling properties.

The object returned is expected to be formatted as:

```
{
    color: string, opacity: integer, lineOpacity: integer, lineWidth: integer
}
```

Example

>> Display bars with userdata of "bold" with thicker lines

```
var chart = new EJSC.Chart("chart");
var bar = chart.addSeries(new EJSC.BarSeries( data, {
          lineOpacity: 80,
          lineWidth: 1,
          onBarNeedsColor: function(point, series, chart) {
```

```
if (point.userdata == "bold") {
             return {
                color: "rgb(0,0,0)",
                opacity: 100, lineOpacity: 100,
                 lineWidth: 100
             };
          } else {
             return "rgb(128,128,128)";
} ));
```

4.4.16.3.4 onBeforeVisibilityChange (inherited)

Definition

boolean onBeforeVisibilityChange(EJSC.Series series, EJSC.Chart chart)

Description

Fired before the series visibility is about to change. Sends series which changed, its owner chart. The current visible state of the series may be checked using the series.visible property.

Returning false from this event handler will cancel the change in visibility.

4.4.16.3.5 onShowHint (inherited)

Definition

string onShowHint(EJSC.Point point, EJSC.Series series, EJSC.Chart chart, string hint_string)


Description

Fired before the displaying the hint, this event allows the current hint string to be overridden. See Text Replacement Options for a list of the automatic substitutions available.

4.4.16.4 Text Replacement Options

String [chart_title]	With title of the chart
[series_title]	title of the series the selected
	point resides in
[xaxis]	caption of the series x axis
[yaxis]	caption of the series y axis
[x]	preformatted X value of the
	point
[y]	preformatted Y value of the
	point
[label]	label property of the current
•	point
	•

4.4.17 EJSC.TrendSeries



The TrendSeries is rendered as a line based on the results of a function applied to the related series' data points.

The constructor expects a reference series, a trendType and an optional set of object properties.

The trend series then "trends" the data in that referenceSeries according to the trendType into a function, and plots the function in the visible area of the chart.

Constructor

EJSC.TrendSeries (EJSC.Series referenceSeries, string trendType, {object options})

Valid options for trendType:

"linear"

"power"

"exponential"

"logarithmic"

Example

Defining Properties and Events

TrendSeries properties may be set individually after the series has been created or in batch using the options parameter during instantiation.

Setting properties individually

```
var mySeries = new EJSC.TrendSeries(myDataSeries, "linear");
```

```
mySeries.lineWidth = 2;
mySeries.title = "New Trend Series";
```

Setting properties in batch

4.4.17.1 Properties

4.4.17.1.1 color (inherited)

Definition

string color = undefined

Description

Defines the series color. If left undefined, the color is pulled from the array of default colors stored in the chart.

Note: May not be applicable to all series (i.e. EJSC.PieSeries)

4.4.17.1.2 coloredLegend (inherited)

Definition

boolean coloredLegend = true

Description

Determines whether the legend text inherits the series color. Setting to false will allow the legend text to inherit its normal cascaded color. To modify this property after series creation see EJSC.Series.setColoredLegend()

4.4.17.1.3 hint_string (inherited)

Definition

string hint_string = undefined

Description

This property may be used to define a series specific string to be used when displaying point hints. This string may contain replacement indicators (see Text Replacement Options). When left undefined, a default hint defined by the series type will be displayed.

Example

>> Modify the default hint to include custom text.

```
} );
```

4.4.17.1.4 legendlsVisible (inherited)

Definition

boolean legendlsVisible = true

Description

Determines whether the legend item associated with the series appears in the legend window. Use the Series.showLegend and Series.hideLegend methods to control legend item visibility after series creation.

4.4.17.1.5 lineOpacity (inherited)

Definition

integer lineOpacity = 100

Description

Determines the line opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setLineOpacity()

4.4.17.1.6 lineWidth (inherited)

Definition

integer lineWidth = 1

Description

Defines the width of the line connecting series points.

4.4.17.1.7 padding (inherited)

Definition

```
object padding = {
    x_axis_min: undefined,
    x_axis_max: undefined,
    y_axis_min: undefined,
    y_axis_max: undefined
}
```

Description

The padding property may be used to override the series default padding. Padding is the amount of pixels added to the min and max series values in order to push the extremes and prevent the series from hitting the edge of the chart.

The amount of default padding is dependant upon the series type and axis configuration and may not be applicable to all series types.

This property is only applicable during series creation. To retrieve or modify the series padding after creation please see Series.getPadding() and Series.setPadding()

Example

>> Remove all padding from the BarSeries

4.4.17.1.8 title (inherited)

Definition

string title = "Series <index>"

Description

Defines the series title used in hints and legend display.

Note: The default title of Series <index> (where <index> equals the current position in the series array for its owner chart) is assigned when a series is added to a chart using addSeries. This default title is only applied if the title is blank (i.e. "") at the time the addSeries method is called.

4.4.17.1.9 visible (inherited)

Definition

boolean visible = true

Description

Defines whether the series is visible and can draw on the chart

4.4.17.1.10 x_axis (inherited)

Definition

```
string x_axis = "bottom"
```

Description

Defines the horizontal axis to use for X values. Valid options are "top" or "bottom".

4.4.17.1.11 x_axis_formatter (inherited)

Definition

string x_axis_formatter = undefined

Description

Defines the formatter that will be used to format hints for the X values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

```
Types: EJSC.DateFormatter EJSC.NumberFormatter
```

4.4.17.1.12 y_axis (inherited)

Definition

```
string y_axis = "left"
```

Description

Defines the vertical axis to use for Y values. Valid options are "left" or "right".

4.4.17.1.13 y_axis_formatter (inherited)

Definition

```
string y_axis_formatter = undefined
```

Description

Defines the formatter that will be used to format hints for the Y values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

```
Types: EJSC.DateFormatter EJSC.NumberFormatter
```

4.4.17.2 Methods

4.4.17.2.1 findClosestByPixel (inherited)

Definition

Description

Returns the point object closest to the screen pixel coordinates provided. The x and y properties of the point object should be in the same scale as the x and y axes assigned to the series. To locate points based on pixel coordinates, see Series.findClosestByPixel()

4.4.17.2.2 findClosestByPoint (inherited)

Definition

Description

Returns the point object closest to the axis coordinates provided. The x and y properties of the coordinate object should be based on the top left of the viewport and take into account the page scroll. To locate points based on axis coordinates, see Series.findClosestByPoint()

4.4.17.2.3 getPadding (inherited)

Definition

Description

Returns an object containing the series current padding. If padding has been set either by the Series.setPadding() method of the Series.padding property during construction the result of this method will be adjusted to return the most current padding values.

4.4.17.2.4 getVisibility (inherited)

Definition

boolean getVisibility()

Description

Returns a boolean indicating the series current visible state

4.4.17.2.5 hide (inherited)

Definition

void hide()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already hidden.

4.4.17.2.6 hideLegend (inherited)

Definition

void hideLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already hidden.

4.4.17.2.7 reload (inherited)

Definition

void reload()

Description

Triggers a series reload if the functionality is defined in a child class. This may involve retrieving data again or simply recalculating. While the reload() method exists in the base Series class, implementation of the protected methods triggered by calling reload() is at the discretion of the child class.

4.4.17.2.8 setColor (inherited)

Definition

void setColor(string color)

Description

Changes the series color and causes the chart to redraw.

4.4.17.2.9 setColoredLegend (inherited)

Definition

void setColoredLegend(boolean coloredLegend)

Description

Sets the EJSC.Series.coloredLegend property and updates the legend to reflect the change.

4.4.17.2.10 setLineWidth (inherited)

Definition

void setLineWidth(integer width)

Description

Updates the lineWidth property and redraws the chart.

4.4.17.2.11 setPadding (inherited)

Definition

void setPadding(object Padding, boolean Redraw)

The padding object should be defined as when used in the series constructor. See Series.padding.

Description

This method updates the user-defined series padding and optionally recalculates the chart extremes and redraws the chart.

4.4.17.2.12 setTitle (inherited)

Definition

void setTitle(string title)

Description

Changes the series title and update the legend caption (if applicable).

Note: this will not cause updates to a hint which is visible at the time it is called, though the next time a hint is rendered it will show the new property value.

4.4.17.2.13 show (inherited)

Definition

void show()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already visible.

4.4.17.2.14 showLegend (inherited)

Definition

void showLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already visible.

4.4.17.3 Events

4.4.17.3.1 onAfterVisibilityChange (inherited)

Definition

boolean onAfterVisibilityChange(EJSC.Series series, EJSC.Chart chart, boolean visible)

Description

Fired when the series visibility changes. Sends series which changed, its owner chart and its new visible property value.

Returning **false** from this event handler will cancel redrawing the chart.

4.4.17.3.2 onBeforeVisibilityChange (inherited)

Definition

boolean onBeforeVisibilityChange(EJSC.Series series, EJSC.Chart chart)

Description

Fired before the series visibility is about to change. Sends series which changed, its owner chart. The current visible state of the series may be checked using the series visible property.

Returning **false** from this event handler will cancel the change in visibility.

4.4.17.3.3 onShowHint (inherited)

Definition

string onShowHint(EJSC.Point point, EJSC.Series series, EJSC.Chart chart, string hint_string)

Description

Fired before the displaying the hint, this event allows the current hint string to be overridden. See Text Replacement Options for a list of the automatic substitutions available.

4.4.17.4 Text Replacement Options

String [chart_title]	With title of the chart
[series_title]	title of the series the selected
	point resides in
[xaxis]	caption of the series x axis
[yaxis]	caption of the series y axis
[x]	preformatted X value of the
	point
[y]	preformatted Y value of the
., .	point
[label]	label property of the current
	point
	L

4.5 Data Handlers

4.5.1 EJSC.ArrayDataHandler

ArrayDataHandler converts the JavaScript array of points into a format that the Series classes can manipulate.

The constructor expects a multi-dimensional array of data and an optional set of object properties.

Constructor

4.5.1.1 Methods

4.5.1.1.1 getArray

Definition

array getArray()

Description

Returns the data array currently stored in the ArrayDataHandler.

4.5.1.1.2 loadData (inherited)

Definition

void loadData()

Description

Placeholder method which should be used to clear (if stored) and reload data. This method must be overridden in all descendant classes.

4.5.1.1.3 setArray

Definition

void setArray(array data)

Description

Updates the data array stored in the ArrayDataHandler.

Note: This will not cause the data to be refreshed, see EJSC.Series.reload() for more information.

4.5.1.2 Events

4.5.1.2.1 onDataAvailable (inherited)

Definition

void onDataAvailable()

Description

Placeholder for storing an event to fire after the a descendant class has loaded and processed its data.

Important: This event should be assigned by the EJSC.Series object.

4.5.2 EJSC.CSVFileDataHandler

CSVFileDataHandler loads the requested csv file and extracts the data points into a format that the Series classes can manipulate.

The constructor expects the URL to the csv data file and an optional set of object properties.

Constructor

```
EJSC.CSVFileDataHandler( string url [, object options] )
```

Example

4.5.2.1 Properties

4.5.2.1.1 requestType (inherited)

Definition

```
string requestType = "GET"
```

Description

Defines the type of HTTP request to be made. Valid options are "GET" and "POST"

4.5.2.1.2 url (inherited)

Definition

string url = null

Description

Defines the url currently being used to retrieve data. Descendants of AjaxDataHandler generally allow this to be set in the constructor method. To modify this value after creation, call the setUrl method which allows the data to be reloaded immediately.

4.5.2.1.3 urlData (inherited)

Definition

string urlData = null

Description

Defines the data to be included for both POST and GET requests. When performing a GET request, this data (if defined) will be appended to the URL before the request is made. For POST requests, this data will be sent as the body of the request.

NOTE: For GET requests you must include the proper syntax for appending the url stored in the url property. Example:

```
url = "http://localhost/getData"
urlData = "?param1=30"
or
url = "http://localhost/getData?param1=30"
urlData = "&extra=1"
```

4.5.2.2 Methods

4.5.2.2.1 getUrl (inherited)

Definition

string getUrl()

Description

Returns the url string currently stored in the AjaxDataHandler descendant.

DEPRECATED, see EJSC.AjaxDataHandler.url

4.5.2.2.2 loadData (inherited)

Definition

void loadData()

Description

Placeholder method which should be used to clear (if stored) and reload data. This method must be overridden in all descendant classes.

4.5.2.2.3 setRequestType (inherited)

Definition

void setRequestType(string requestType, boolean reload)

Description

Updates the requestType stored in the AjaxDataHandler descendant and optionally reloads / reprocesses the data source and updates the series.

Valid options for requestType are "GET" and "POST"

Note: If the reload parameter is omitted or false, the data will not reload automatically and must be done manually via EJSC.Series.reload()

4.5.2.2.4 setUrl (inherited)

Definition

void setUrl(string url, boolean reload)

Description

Updates the url string stored in the AjaxDataHandler descendant and optionally reloads the data immediately.

Note: If the reload parameter is omitted or false, the data will not reload automatically and must be done manually via EJSC.Series.reload()

4.5.2.2.5 setUrlData (inherited)

Definition

void setUrlData(string urlData, boolean reload)

Description

Updates the urlData stored in the AjaxDataHandler descendant and optionally reloads / reprocesses the data source and updates the series.

Note: If the reload parameter is omitted or false, the data will not reload automatically and must be done manually via EJSC.Series.reload()

4.5.2.2.6 setXMLData (inherited)

Definition

void setXMLData(XMLHttpRequest request)

Description

This method allows passing of an already retrieved XMLHttpRequest object to an AjaxDataHandler descendant. When used in conjunction with the onNeedsData event, this method allows interaction

with pre-existing 3rd party Ajax libraries instead of the request pool built into the chart library.

If the data handler is not currently in the loading state (i.e. onNeedsData was triggered), calling this method will have no effect.

4.5.2.3 Events

4.5.2.3.1 onDataAvailable (inherited)

Definition

void onDataAvailable()

Description

Placeholder for storing an event to fire after the a descendant class has loaded and processed its data.

Important: This event should be assigned by the EJSC. Series object.

4.5.2.3.2 onDataReady (inherited)

Definition

boolean **onDataReady**(XMLHttpRequest response, EJSC.AjaxDataHandler data_handler, EJSC.Series series, EJSC.Chart chart)

Description

This event is fired when data has arrived completely and is ready for processing by the data handler. Returning true from this event will cause the data handler to process its data normally, returning false will cause processing to be canceled.

4.5.2.3.3 onNeedsData (inherited)

Definition

boolean **onNeedsData**(EJSC.AjaxDataHandler dataHandler, EJSC.Series series, EJSC.Chart chart) XMLHttpRequest **onNeedsData**(EJSC.AjaxDataHandler dataHandler, EJSC.Series series, EJSC.Chart chart)

Description

This event allows for additional control over when and how data is retrieved by the data handler. If assigned, the event will be triggered whenever the its owner series has requested the data handler retrieve its data. The event passes a reference to the current data handler, its owner series and the owner chart.

The result of this event is expected to be either a boolean value or an XMLHttpRequest object which has already been retrieved (responseXML is a valid, well-formed chart xml document).

RESULT:

true: The data handler will ignore other properties such as url and requestType and hold itself
in a loading state and wait for its setXMLData method to be called and provided a valid

XMLHttpRequest object. In this manner, a separate Ajax library may be used to retrieve data.

- **false:** The data handler will ignore other properties such as url and requestType and cancel its loading process.
- XMLHttpRequest: The data handler will ignore other properties such as url and requestType and immediately begin processing the data stored in responseXML.

4.5.3 EJSC.CSVStringDataHandler

CSVStringDataHandler converts the csv string provided into a format that the Series classes can manipulate.

The constructor expects a properly formatted string and an optional set of object properties.

Constructor

```
EJSC.CSVStringDataHandler( string data [, object options] )
```

Example

4.5.3.1 Methods

4.5.3.1.1 getCSV

Definition

```
string getCSV()
```

Description

Returns the csv string currently stored in the CSVStringDataHandler.

4.5.3.1.2 loadData (inherited)

Definition

void loadData()

Description

Placeholder method which should be used to clear (if stored) and reload data. This method must be overridden in all descendant classes.

4.5.3.1.3 setCSV

Definition

```
void setCSV( string csv )
```

Description

Updates the csv string stored in the CSVStringDataHandler.

Note: This will not cause the data to be refreshed, see EJSC.Series.reload() for more information.

4.5.3.2 Events

4.5.3.2.1 onDataAvailable (inherited)

Definition

void onDataAvailable()

Description

Placeholder for storing an event to fire after the a descendant class has loaded and processed its data.

Important: This event should be assigned by the EJSC. Series object.

4.5.4 EJSC.JSONFileDataHandler

JSONFileDataHandler loads the requested JSON file and extracts the data points into a format that the Series classes can manipulate.

The constructor expects the URL to the JSON data file and an optional set of object properties.

Constructor

```
EJSC.JSONFileDataHandler( string url [, object options] )
```

Example

See Data Formats for additional information.

4.5.4.1 Properties

4.5.4.1.1 requestType (inherited)

Definition

```
string requestType = "GET"
```

Description

Defines the type of HTTP request to be made. Valid options are "GET" and "POST"

4.5.4.1.2 url (inherited)

Definition

```
string url = null
```

Description

Defines the url currently being used to retrieve data. Descendants of AjaxDataHandler generally allow this to be set in the constructor method. To modify this value after creation, call the setUrl method which allows the data to be reloaded immediately.

4.5.4.1.3 urlData (inherited)

Definition

```
string urlData = null
```

Description

Defines the data to be included for both POST and GET requests. When performing a GET request, this data (if defined) will be appended to the URL before the request is made. For POST requests, this data will be sent as the body of the request.

NOTE: For GET requests you must include the proper syntax for appending the url stored in the url property. Example:

```
url = "http://localhost/getData"
urlData = "?param1=30"
or
url = "http://localhost/getData?param1=30"
urlData = "&extra=1"
```

4.5.4.2 Methods

4.5.4.2.1 getUrl (inherited)

Definition

string getUrl()

Description

Returns the url string currently stored in the AjaxDataHandler descendant.

DEPRECATED, see EJSC.AjaxDataHandler.url

4.5.4.2.2 loadData (inherited)

Definition

void loadData()

Description

Placeholder method which should be used to clear (if stored) and reload data. This method must be

overridden in all descendant classes.

4.5.4.2.3 setRequestType (inherited)

Definition

void setRequestType(string requestType, boolean reload)

Description

Updates the requestType stored in the AjaxDataHandler descendant and optionally reloads / reprocesses the data source and updates the series.

Valid options for requestType are "GET" and "POST"

Note: If the reload parameter is omitted or false, the data will not reload automatically and must be done manually via EJSC.Series.reload()

4.5.4.2.4 setUrl (inherited)

Definition

void setUrl(string url, boolean reload)

Description

Updates the url string stored in the AjaxDataHandler descendant and optionally reloads the data immediately.

Note: If the reload parameter is omitted or false, the data will not reload automatically and must be done manually via EJSC.Series.reload()

4.5.4.2.5 setUrlData (inherited)

Definition

void setUrlData(string urlData, boolean reload)

Description

Updates the urlData stored in the AjaxDataHandler descendant and optionally reloads / reprocesses the data source and updates the series.

Note: If the reload parameter is omitted or false, the data will not reload automatically and must be done manually via EJSC.Series.reload()

4.5.4.2.6 setXMLData (inherited)

Definition

void setXMLData(XMLHttpRequest request)

Description

This method allows passing of an already retrieved XMLHttpRequest object to an AjaxDataHandler

descendant. When used in conjunction with the onNeedsData event, this method allows interaction with pre-existing 3rd party Ajax libraries instead of the request pool built into the chart library.

If the data handler is not currently in the loading state (i.e. onNeedsData was triggered), calling this method will have no effect.

4.5.4.3 Events

4.5.4.3.1 onDataAvailable (inherited)

Definition

void onDataAvailable()

Description

Placeholder for storing an event to fire after the a descendant class has loaded and processed its

Important: This event should be assigned by the EJSC. Series object.

4.5.4.3.2 onDataReady (inherited)

Definition

boolean **onDataReady**(XMLHttpRequest response, EJSC.AjaxDataHandler data_handler, EJSC.Series series, EJSC.Chart chart)

Description

This event is fired when data has arrived completely and is ready for processing by the data handler. Returning true from this event will cause the data handler to process its data normally, returning false will cause processing to be canceled.

4.5.4.3.3 onNeedsData (inherited)

Definition

boolean **onNeedsData**(EJSC.AjaxDataHandler dataHandler, EJSC.Series series, EJSC.Chart chart) XMLHttpRequest **onNeedsData**(EJSC.AjaxDataHandler dataHandler, EJSC.Series series, EJSC.Chart chart)

Description

This event allows for additional control over when and how data is retrieved by the data handler. If assigned, the event will be triggered whenever the its owner series has requested the data handler retrieve its data. The event passes a reference to the current data handler, its owner series and the owner chart.

The result of this event is expected to be either a boolean value or an XMLHttpRequest object which has already been retrieved (responseXML is a valid, well-formed chart xml document).

RESULT:

• true: The data handler will ignore other properties such as url and requestType and hold itself

in a loading state and wait for its setXMLData method to be called and provided a valid XMLHttpRequest object. In this manner, a separate Ajax library may be used to retrieve data.

- **false:** The data handler will ignore other properties such as url and requestType and cancel its loading process.
- XMLHttpRequest: The data handler will ignore other properties such as url and requestType
 and immediately begin processing the data stored in responseXML.

4.5.5 EJSC.JSONStringDataHandler

JSONStringDataHandler converts the JSON string provided into a format that the Series classes can manipulate.

The constructor expects a properly formatted string and an optional set of object properties.

Constructor

```
EJSC.JSONStringDataHandler( string data [, object options] )
```

Example

4.5.5.1 Methods

4.5.5.1.1 getJSON

Definition

string getJSON()

Description

Returns the JSON string currently stored in the JSONStringDataHandler.

4.5.5.1.2 loadData (inherited)

Definition

void loadData()

Description

Placeholder method which should be used to clear (if stored) and reload data. This method must be overridden in all descendant classes.

4.5.5.1.3 setJSON

Definition

void setJSON(string JSON)

Description

Updates the JSON string stored in the JSONStringDataHandler.

Note: This will not cause the data to be refreshed, see EJSC.Series.reload() for more information.

4.5.5.2 Events

4.5.5.2.1 onDataAvailable (inherited)

Definition

void onDataAvailable()

Description

Placeholder for storing an event to fire after the a descendant class has loaded and processed its

Important: This event should be assigned by the EJSC. Series object.

4.5.6 EJSC.XMLDataHandler

XMLDataHandler loads the requested XML file, determines the format (Full, Short or Compact) and extracts the data points into a format that the Series classes can manipulate.

The constructor expects the URL to the XML data file and an optional set of object properties.

Constructor

```
EJSC.XMLDataHandler( string url [, object options] )
```

Example

Formats:

The XMLDataHandler supports three formats:

- Full
- Short
- Compact

4.5.6.1 Properties

4.5.6.1.1 requestType (inherited)

Definition

```
string requestType = "GET"
```

Description

Defines the type of HTTP request to be made. Valid options are "GET" and "POST"

4.5.6.1.2 url (inherited)

Definition

string url = null

Description

Defines the url currently being used to retrieve data. Descendants of AjaxDataHandler generally allow this to be set in the constructor method. To modify this value after creation, call the setUrl method which allows the data to be reloaded immediately.

4.5.6.1.3 urlData (inherited)

Definition

string urlData = null

Description

Defines the data to be included for both POST and GET requests. When performing a GET request, this data (if defined) will be appended to the URL before the request is made. For POST requests, this data will be sent as the body of the request.

NOTE: For GET requests you must include the proper syntax for appending the url stored in the url property. Example:

```
url = "http://localhost/getData"
urlData = "?param1=30"
or
url = "http://localhost/getData?param1=30"
urlData = "&extra=1"
```

4.5.6.2 Methods

4.5.6.2.1 getUrl (inherited)

Definition

string getUrl()

Description

Returns the url string currently stored in the AjaxDataHandler descendant.

DEPRECATED, see EJSC.AjaxDataHandler.url

4.5.6.2.2 loadData (inherited)

Definition

void loadData()

Description

Placeholder method which should be used to clear (if stored) and reload data. This method must be overridden in all descendant classes.

4.5.6.2.3 setRequestType (inherited)

Definition

void setRequestType(string requestType, boolean reload)

Description

Updates the requestType stored in the AjaxDataHandler descendant and optionally reloads / reprocesses the data source and updates the series.

Valid options for requestType are "GET" and "POST"

Note: If the reload parameter is omitted or false, the data will not reload automatically and must be done manually via EJSC.Series.reload()

4.5.6.2.4 setUrl (inherited)

Definition

void **setUrl**(string url, boolean reload)

Description

Updates the url string stored in the AjaxDataHandler descendant and optionally reloads the data immediately.

Note: If the reload parameter is omitted or false, the data will not reload automatically and must be done manually via EJSC.Series.reload()

4.5.6.2.5 setUrlData (inherited)

Definition

void setUrlData(string urlData, boolean reload)

Description

Updates the urlData stored in the AjaxDataHandler descendant and optionally reloads / reprocesses the data source and updates the series.

Note: If the reload parameter is omitted or false, the data will not reload automatically and must be done manually via EJSC.Series.reload()

4.5.6.2.6 setXMLData (inherited)

Definition

void setXMLData(XMLHttpRequest request)

Description

This method allows passing of an already retrieved XMLHttpRequest object to an AjaxDataHandler descendant. When used in conjunction with the onNeedsData event, this method allows interaction with pre-existing 3rd party Ajax libraries instead of the request pool built into the chart library.

If the data handler is not currently in the loading state (i.e. onNeedsData was triggered), calling this method will have no effect.

4.5.6.3 Events

4.5.6.3.1 onDataAvailable (inherited)

Definition

void onDataAvailable()

Description

Placeholder for storing an event to fire after the a descendant class has loaded and processed its data.

Important: This event should be assigned by the EJSC. Series object.

4.5.6.3.2 onDataReady (inherited)

Definition

boolean **onDataReady**(XMLHttpRequest response, EJSC.AjaxDataHandler data_handler, EJSC.Series series, EJSC.Chart chart)

Description

This event is fired when data has arrived completely and is ready for processing by the data handler. Returning true from this event will cause the data handler to process its data normally, returning false will cause processing to be canceled.

4.5.6.3.3 onNeedsData (inherited)

Definition

boolean **onNeedsData**(EJSC.AjaxDataHandler dataHandler, EJSC.Series series, EJSC.Chart chart) XMLHttpRequest **onNeedsData**(EJSC.AjaxDataHandler dataHandler, EJSC.Series series, EJSC.Chart chart)

Description

This event allows for additional control over when and how data is retrieved by the data handler. If assigned, the event will be triggered whenever the its owner series has requested the data handler

retrieve its data. The event passes a reference to the current data handler, its owner series and the owner chart.

The result of this event is expected to be either a boolean value or an XMLHttpRequest object which has already been retrieved (responseXML is a valid, well-formed chart xml document).

RESULT:

- **true:** The data handler will ignore other properties such as url and requestType and hold itself in a loading state and wait for its setXMLData method to be called and provided a valid XMLHttpRequest object. In this manner, a separate Ajax library may be used to retrieve data.
- false: The data handler will ignore other properties such as url and requestType and cancel its loading process.
- XMLHttpRequest: The data handler will ignore other properties such as url and requestType and immediately begin processing the data stored in responseXML.

4.5.7 EJSC.XMLStringDataHandler

XMLStringDataHandler processes the provided xml-formatted string, determines the format (Full, Short or Compact) and extracts the data points into a format that the Series classes can manipulate.

The constructor expects a properly formatted string containing XML data and an optional set of object properties.

Constructor

```
EJSC.XMLStringDataHandler( string xml [, object options] )
```

Example

Formats:

The XMLStringDataHandler supports three formats:

- Full
- Short
- Compact

4.5.7.1 Methods

4.5.7.1.1 getXML

Definition

string getXML()

Description

Returns the xml string currently stored in the XMLStringDataHandler.

4.5.7.1.2 loadData (inherited)

Definition

void loadData()

Description

Placeholder method which should be used to clear (if stored) and reload data. This method must be overridden in all descendant classes.

4.5.7.1.3 setXML

Definition

void setXML(string xml)

Description

Updates the xml string stored in the XMLStringDataHandler.

Note: This will not cause the data to be refreshed, see EJSC.Series.reload() for more information.

4.5.7.2 Events

4.5.7.2.1 onDataAvailable (inherited)

Definition

void onDataAvailable()

Description

Placeholder for storing an event to fire after the a descendant class has loaded and processed its data.

Important: This event should be assigned by the EJSC. Series object.

4.6 Label Formatters

4.6.1 EJSC.DateFormatter

Use this formatter when you want to display date values in your charts. It can be applied to the chart axis, series hints and cursor position labels by assigning the appropriate formatter property.

Dates are supported in UTC format by specifying a JavaScript date (i.e. number of milliseconds since midnight January 01, 1970) for a point value.

See the format_string property for information on supported date formatting options.

Constructor

EJSC.DateFormatter([options])

Example

4.6.1.1 Properties

4.6.1.1.1 format_string

Definition

```
string format_string = ""
```

Description

The following format options are available:

```
Format
                                                     (4) digit year (i.e. 2007)
(2) digit year (i.e. 07)
month name (i.e. January)
month name (i.e. Jan)
YYYY
YY
MMMM
MMM
                                                      (2) digit month of the year
MM
                                            with leading zeros (i.e. 01)
                                                      of the year without leading
Μ
                                            zeros
                                                     day of the week (i.e. Monday) day of the week (i.e. Mon)
DDDD
DDD
DD
                                                      (2) digit day of the month with
                                            leading zeros (i.e. 04)
D
                                                      of the month without leading
                                            zeros
HH
                                                      of the day in 24-hour format
                                            with leading zeros
Н
                                                      of the day in 24-hour format
                                            without leading zeros
                                                      of the day in 12-hour format
hh
                                            with leading zeros
h
                                                      of the day in 12-hour format
                                            without leading zeros
NN
                                                      with leading zeros
Ν
                                                      without leading zeros
SS
                                                      with leading zeros
S
ZZZ
                                                      without leading zeros
                                                      (3 places) with leading zeros (2 places) with leading zeros
ZΖ
Ζ
                                                     without leading zeros
AA
                                                     /PM notation
                                                     /P notation
Α
aa
                                                     /pm notation
                                                     /p notation
а
```

4.6.1.1.2 timezoneOffset

Definition

integer timezoneOffset = undefined

Description

Used in conjunction with useUTC, this property may be used to display dates in the specified time zone. The timezoneOffset property is set by specifying the number of minutes (positive or negative) to offset the given time.

Example

>> Display times in Eastern Standard Time (EST)

```
var chart = new EJSC.Chart("myChart");
    chart.axis_bottom.formatter = new EJSC.DateFormatter({
        format_string: "HH:NN:SS",
        useUTC: true,
        timezoneOffset: -300
    });
```

4.6.1.1.3 useUTC

Definition

boolean useUTC = true

Description

Set this property to false to use the workstation local time to calculate dates. This may be useful when passing in dates generated by JavaScript on the client machine to indicate current time.

4.6.1.2 Methods

4.6.1.2.1 format (inherited)

Definition

string format(float value, integer precision)

Description

Format is called when a value needs to be formatted for display in the axis, hint, cursor position, etc.

The behavior of the format method is to round a numeric value to the precision specified. Descendants do not need to implement the precision parameter.

4.6.2 EJSC.NumberFormatter

Use this formatter when you want more control over the display of numeric values in your charts. It can be applied to the chart axis as well as series hints.

Constructor

EJSC.NumberFormatter([options])

Example

4.6.2.1 Properties

4.6.2.1.1 currency_align

Definition

```
string currency_align = "left"
```

Description

Valid options are "left" and "right".

4.6.2.1.2 currency_position

Definition

```
string currency_position = "inner"
```

Description

Valid options are "inner" and "outer".

4.6.2.1.3 currency_symbol

Definition

```
string currency_symbol = ""
```

Description

Specifies the symbol used to indicate currency.

Note: If blank "" then no currency marker is used.

4.6.2.1.4 decimal_separator

Definition

```
string decimal_separator = "."
```

Description

Specifies the symbol used to separate the whole number part from the fractional part.

Common values are "." or ","

4.6.2.1.5 forced_decimals

Definition

integer forced_decimals = undefined

Description

Specifies the number of decimal places which MUST be displayed (0's are appended if necessary).

4.6.2.1.6 negative_symbol

Definition

```
string negative_symbol = "-"
```

Description

Specifies the formatting of negative numbers.

Valid options are "-" and "()"

4.6.2.1.7 thousand_separator

Definition

```
string thousand_separator = ","
```

Description

Specifies the symbol used to separate thousands groupings.

Common values are:

- "," renders as 1,000,000
 "." renders as 1.000.000
 "" renders as 1000000

4.6.2.1.8 variable_decimals

Definition

string variable_decimals = undefined

Description

Specifies the number of decimal places which MAY be displayed (values are truncated to this length)

If left undefined, values are not truncated.

4.6.2.2 Methods

4.6.2.2.1 format (inherited)

Definition

string **format**(float value, integer precision)

Description

Format is called when a value needs to be formatted for display in the axis, hint, cursor position, etc.

The behavior of the format method is to round a numeric value to the precision specified. Descendants do not need to implement the precision parameter.

4.6.3 EJSC.StringFormatter

Use this formatter when you want to prefix or append data to the value being displayed in your charts. It can be applied to the chart axis, series hints and cursor position labels by assigning the appropriate formatter property.

Constructor

EJSC.StringFormatter([options])

Example

4.6.3.1 Properties

4.6.3.1.1 append

Definition

```
string append = undefined
```

Description

The string stored in the append property will be applied to every value processed by the formatter.

4.6.3.1.2 prefix

Definition

```
string prefix = undefined
```

Description

The string stored in the prefix property will be applied to every value processed by the formatter.

4.6.3.2 Methods

4.6.3.2.1 format (inherited)

Definition

string format(float value, integer precision)

Description

Format is called when a value needs to be formatted for display in the axis, hint, cursor position, etc.

The behavior of the format method is to round a numeric value to the precision specified. Descendants do not need to implement the precision parameter.

4.6.3.3 Events

4.6.3.3.1 onNeedsFormat

Definition

string onNeedsFormat(number value, EJSC.StringFormatter)

Description

This event (when assigned) will fire every time the formatter needs to process a value. The string returned from this event will be displayed in place of the value in the chart.

Example

>> Adjust all values by 100

```
var chart = new EJSC.Chart("myChart");
  chart.x_axis_formatter = new EJSC.StringFormatter({
      onNeedsFormat: function(value, formatter) {
            return value + 100;
      }
  });
```

4.7 Base Classes

4.7.1 EJSC.Inheritable

Base class from which all EJSC classes descend. There are no public properties, methods or events for this class at this time.

Constructor

none

4.7.2 EJSC.AjaxDataHandler

Base data handler class for all Ajax data handlers (i.e. EJSC.XMLDataHandler, EJSC.CSVFileDataHandler, EJSC.JSONFileDataHandler). This base class defines common properties, methods and events but does not implement any data processing. This class should not be used directly.

Constructor

none

4.7.2.1 Properties

4.7.2.1.1 requestType

Definition

string requestType = "GET"

Description

Defines the type of HTTP request to be made. Valid options are "GET" and "POST"

4.7.2.1.2 url

Definition

string **url** = null

Description

Defines the url currently being used to retrieve data. Descendants of AjaxDataHandler generally allow this to be set in the constructor method. To modify this value after creation, call the setUrl method which allows the data to be reloaded immediately.

4.7.2.1.3 urlData

Definition

string urlData = null

Description

Defines the data to be included for both POST and GET requests. When performing a GET request, this data (if defined) will be appended to the URL before the request is made. For POST requests, this data will be sent as the body of the request.

NOTE: For GET requests you must include the proper syntax for appending the url stored in the url property. Example:

```
url = "http://localhost/getData"
urlData = "?param1=30"
```

or

url = "http://localhost/getData?param1=30"
urlData = "&extra=1"

4.7.2.2 Methods

4.7.2.2.1 getUrl

Definition

string getUrl()

Description

Returns the url string currently stored in the AjaxDataHandler descendant.

DEPRECATED, see EJSC.AjaxDataHandler.url

4.7.2.2.2 loadData (inherited)

Definition

void loadData()

Description

Placeholder method which should be used to clear (if stored) and reload data. This method must be overridden in all descendant classes.

4.7.2.2.3 setRequestType

Definition

void setRequestType(string requestType, boolean reload)

Description

Updates the requestType stored in the AjaxDataHandler descendant and optionally reloads / reprocesses the data source and updates the series.

Valid options for requestType are "GET" and "POST"

Note: If the reload parameter is omitted or false, the data will not reload automatically and must be done manually via EJSC.Series.reload()

4.7.2.2.4 setUrl

Definition

void setUrl(string url, boolean reload)

Description

Updates the url string stored in the AjaxDataHandler descendant and optionally reloads the data

immediately.

Note: If the reload parameter is omitted or false, the data will not reload automatically and must be done manually via EJSC.Series.reload()

4.7.2.2.5 setUrlData

Definition

void setUrlData(string urlData, boolean reload)

Description

Updates the urlData stored in the AjaxDataHandler descendant and optionally reloads / reprocesses the data source and updates the series.

Note: If the reload parameter is omitted or false, the data will not reload automatically and must be done manually via EJSC.Series.reload()

4.7.2.2.6 setXMLData

Definition

void setXMLData(XMLHttpRequest request)

Description

This method allows passing of an already retrieved XMLHttpRequest object to an AjaxDataHandler descendant. When used in conjunction with the onNeedsData event, this method allows interaction with pre-existing 3rd party Ajax libraries instead of the request pool built into the chart library.

If the data handler is not currently in the loading state (i.e. onNeedsData was triggered), calling this method will have no effect.

4.7.2.3 Events

4.7.2.3.1 onDataAvailable (inherited)

Definition

void onDataAvailable()

Description

Placeholder for storing an event to fire after the a descendant class has loaded and processed its data.

Important: This event should be assigned by the EJSC. Series object.

4.7.2.3.2 onDataReady

Definition

boolean **onDataReady**(XMLHttpRequest response, EJSC.AjaxDataHandler data_handler, EJSC.Series series, EJSC.Chart chart)

Description

This event is fired when data has arrived completely and is ready for processing by the data handler. Returning true from this event will cause the data handler to process its data normally, returning false will cause processing to be canceled.

4.7.2.3.3 onNeedsData

Definition

boolean **onNeedsData**(EJSC.AjaxDataHandler dataHandler, EJSC.Series series, EJSC.Chart chart) XMLHttpRequest **onNeedsData**(EJSC.AjaxDataHandler dataHandler, EJSC.Series series, EJSC.Chart chart)

Description

This event allows for additional control over when and how data is retrieved by the data handler. If assigned, the event will be triggered whenever the its owner series has requested the data handler retrieve its data. The event passes a reference to the current data handler, its owner series and the owner chart.

The result of this event is expected to be either a boolean value or an XMLHttpRequest object which has already been retrieved (responseXML is a valid, well-formed chart xml document).

RESULT:

- true: The data handler will ignore other properties such as url and requestType and hold itself
 in a loading state and wait for its setXMLData method to be called and provided a valid
 XMLHttpRequest object. In this manner, a separate Ajax library may be used to retrieve data.
- **false:** The data handler will ignore other properties such as url and requestType and cancel its loading process.
- **XMLHttpRequest**: The data handler will ignore other properties such as url and requestType and immediately begin processing the data stored in responseXML.

4.7.3 EJSC.Axis

Base class for all Axis classes (i.e. EJSC.LinearAxis, EJSC.LogarithmicAxis). This base class defines common properties, methods and events but does not implement any drawing or calculation routines. This class should not be used directly.

Constructor

none

4.7.3.1 Properties

4.7.3.1.1 background

Definition

```
object background = { color: "#fff",
```

```
opacity: 0,
includeTitle: false
};
```

Description

Defines the color and opacity of the axis area background. Setting the includeTitle property to true will fill the axis caption area as well as the ticks. If opacity is set to 0, no fill will occur.

4.7.3.1.2 border

Definition

Description

Defines the appearance of the axis side bordering the chart area. By default the border color inherits the axis color property (EJSC.Axis.color)

Example

>> Provide a 2 pixel tall green border on the bottom axis.

```
string caption = "Axis"
```

Description

Definition

Defines the text to be displayed below or beside the axis.

For styling the caption, see EJSC.Axis.caption class

Example

>> Customize the bottom axis caption.

```
var chart = new EJSC.Chart( "chart", {
          axis_bottom: { caption: "Year" }
} );
```

4.7.3.1.4 caption_class

Definition

```
string caption_class = ""
```

Description

Defines the CSS className to assign to the axis caption.

For styling the tick labels, see EJSC.Axis.label_class

Example

>> Style the axis caption bold.

4.7.3.1.5 color

Definition

```
string color = "#FFF"
```

Description

Defines the default color of the axis border and tick marks. If the sub properties such as minor_ticks.color, major_ticks.color, border.color are left undefined, they inherit the value set here.

Example

>> Color the axis border and tick marks red

```
var chart = new EJSC.Chart( "chart", {
         axis_bottom: { color: "#F00" }
} );
```

4.7.3.1.6 crosshair

Definition

```
object crosshair = {
            show: false,
            color: "#F00"
}
```

Description

Defines if crosshair should be shown on the chart at the current mouse coordinates as they relate to the given axis. May be enabled and disabled for each axis independently. This is automatically disabled for all axes if EJSC.Chart.allow_interactivity is set to false.

Example

>> Show crosshair based on the bottom axis mouse position.

4.7.3.1.7 cursor_position

Definition

```
object cursor_position = {
    show: false,
    color: "#F00",
    textColor: "#FFF",
    formatter: undefined,
    caption: undefined,
    className: undefined}
```

Description

Defines the display properties of the cursor position feature for an axis. These properties may be used to turn the cursor position indicator on and off as well as configure the styling and color.

show: determines whether or not to display the cursor position while the mouse is within the chart area

color: sets the background and line color

textColor: sets the text color

formatter: defines a formatter to use when displaying coordinates, if left undefined it will use the axis formatter

caption: defines text to use as a prefix to the current coordinate **className**: a CSS class name to be used for additional styling

Example

>> Turn on cursor position for the bottom axis and configure to display a related label

4.7.3.1.8 extremes_ticks

Definition

boolean extremes_ticks = false

Description

Defines if the min and max values should be forced to land on the next tick mark.

Example

>> Force tick marks at the min and max coordinates of the bottom axis (left and right sides of the chart)

```
var chart = new EJSC.Chart( "chart", {
          axis_bottom: { extremes_ticks: true }
} );
```

4.7.3.1.9 force_static_points

Definition

boolean force_static_points = false

Description

Defines if the chart should force ticks to match up to every point by converting the data to strings.

Example

>> Display every bottom axis data point, essentially disable auto axis scaling.

4.7.3.1.10 formatter

Definition

EJSC.Formatter = EJSC.Formatter

Description

Defines the formatter that will be used to format the tick marks on the axis before displaying them.

```
Types:
EJSC.DateFormatter
EJSC.NumberFormatter
EJSC.StringFormatter
```

Example

>> Display bottom axis tick labels as \$0.00

4.7.3.1.11 grid

Definition

```
object grid = {
    thickness: 1,
    color: "rgb(230,230,230)",
    opacity: 100,
    show: true
}
```

Description

Defines the appearance and visibility of the grid drawn in the background.

Example

>> Do not draw the background grid for the top and right axes.

4.7.3.1.12 hint_caption

Definition

```
string hint_caption = "Value:"
```

Description

Defines the text to display in front of the axis-related value in the hint (leave blank to hide the value when displaying the hint).

Example

>> Customize the value label in the hint window

4.7.3.1.13 label_class

Definition

```
string label_class = ""
```

Description

Defines the CSS className to assign to the axis tick labels. Used in conjunction with

EJSC.Axis.stagger_ticks and EJSC.Axis.size, this property allows for greater control over the size and staggering of tick labels on the top and bottom axes.

For styling the caption, see EJSC.Axis.caption_class

Example

>> Style the axis tick labels grey, make them 24 pixels high to enable text wrapping and enable two levels of tick staggering.

4.7.3.1.14 max_extreme

Definition

float max extreme = undefined

Description

Defines the maximum value of the the axis. This will only affect the axis when set during chart creation and may be used to extend or truncate the value range displayed. To retrieve and set this value after the chart has been created, see EJSC.Axis.getExtremes and EJSC.Axis.setExtremes

Example

>> Force the axis range to extend beyond the data it contains

4.7.3.1.15 major_ticks

Definition

```
object major_ticks = {
    thickness: 1,
    size: 4,
    color: undefined,
    opacity: 100,
    show: true,
    count: undefined,
    offset: 0,
    min_interval: undefined,
    max_interval: undefined
}
```

Description

This set of properties defines the characteristics of the major ticks for a given axis.

thickness: the height or width (depending on axis orientation) of the tick mark

size: the amount the tick mark extends from the axis border, may be specified as a number or a string containing % for a percentage

color: the color of the tick marks, if left undefined this property inherits its value from EJSC.Axis.color

opacity: the opacity of the tick marks

show: specifies whether to draw the tick marks

count: the number of tick marks to draw, if left undefined the axis will determine the proper amount of ticks to draw automatically based on the range of data available to the axis

Note: This property is not compatible with text labels (i.e. x axis values are "Gizmos", "Widgets", instead of numbers)

offset: distance in pixels or percent from the axis border to begin drawing the tick marks, min_interval: Defines the minimum interval between major tick marks / labels. This will override the auto generation of ticks to cap the interval to the value when defined.

max_interval: Defines the maximum interval between major tick marks / labels. This will override the auto generation of ticks to cap the interval to the value when defined.

4.7.3.1.16 minor_ticks

Definition

```
object minor_ticks = {
    show: false,
    color: "rgb(0,0,0)",
    opacity: 20
    thickness: 1,
    count: 7,
    size: 4,
    offset: 0
}
```

Description

Defines the properties of the minor tick marks to be drawn on the axis. The color, opacity and thickness (width of ticks in pixels) properties define the style of the tick marks. The count property defines the number of tick marks to be drawn between each major tick mark. The size property defines the height of the ticks (in pixels or percent). The offset property defines the distance away from the axis the minor tick marks begin drawing.

Example

>> Display red minor tick marks on the bottom axis

4.7.3.1.17 min_extreme

Definition

float min = undefined

Description

Defines the minimum value of the the axis. This will only affect the axis when set during chart creation and may be used to extend or truncate the value range displayed. To retrieve and set this value after the chart has been created, see EJSC.Axis.getExtremes and EJSC.Axis.setExtremes

Example

>> Force the axis range to extend beyond the data it contains

4.7.3.1.18 size

Definition

integer size = 20

Description

Defines the height of horizontal axes or width of vertical axes (in pixels) of the tick area. To fully enable staggered ticks on horizontal axes, set this property to a multiple of 20 (or axis tick height), i.e. two levels = 40, three levels = 60.

For additional control over the format of the labels, see the EJSC.Axis.label_class property.

Example

>> Make axis tick area twice as tall, enabling staggered ticks (default tick label height is 20 pixels)

```
var chart = new EJSC.Chart( "chart", {
          axis_bottom: { size: 40 }
} );
```

4.7.3.1.19 stagger_ticks

Definition

boolean stagger_ticks = true

Description

Determines whether the axis tick labels are staggered.

NOTE: This property is only applicable to horizontal axes (i.e. EJSC.Chart.axis_top and

EJSC.Chart.axis_bottom)

Example

>> Disable tick staggering for the bottom axis

Definition

boolean visible = true

Description

Defines if the axis (containing axis caption and tick labels) should be displayed.

Example

>> Remove the bottom axis from the chart to allow additional room for data

Definition

```
object zero_plane = {
    color: "rgb(0,0,0)",
    show: false,
    opacity: 100,
    thickness: 1,
    coordinate: 0
}
```

Description

Defines the properties of the zero plane line to be drawn at 0 (or whatever the coordinate property is set to). It is used to specify if the line should be shown as well as its color, thickness and opacity. The coordinate property allows the base of EJSC.BarSeries, EJSC.StackedBarSeries and EJSC.AreaSeries changed.

Example

>> Display a 2 pixel thick dark green line on the zero plane of the left axis

4.7.3.2 Methods

4.7.3.2.1 addBin

Definition

void addBin(String label, boolean redraw)

Description

Adds a new static label to the axis and sets the appropriate flags if necessary to force the chart to draw using static labels (as opposed to a dynamic range based on series data).

This method is useful if there is a need to include bins which may not be part of any series added (i.e. chart labels should be "Apples", "Oranges", "Pears" but the series data only contains data pertaining to Apples and Pears).

If redraw is false, drawing will not occur immediately but will not be entirely prevented. Certain actions such as adding an additional series with redraw = true, or chart dimensions changing may still trigger the chart to draw. The default, if redraw is omitted is **true**.

Note:

Manually added bins may only be removed if there are no series currently utilizing them.

Example

>> Add bins in a specific order to ensure they appear the same each time the chart is loaded, regardless of the order in which they appear in the data.

4.7.3.2.2 getExtremes

Definition

```
object getExtremes()

RETURNS:
{ min: float, max: float }
```

Description

Returns the current axis extreme values.

To set the extreme values, see EJSC.Axis.setExtremes

4.7.3.2.3 getZoom

Definition

```
object getZoom()
```

RETURNS:

{ min: float, max: float }

Description

Returns the current zoom coordinates for a given axis in chart units.

To set the zoom coordinates, see EJSC.Axis.setZoom

4.7.3.2.4 getZoomBoxCoordinates

Definition

void getZoomBoxCoordinates()

```
RETURNS:
```

{ min: float, max: float }

Description

Returns the min and max values for a given axis of the current zoom box. These values are in chart coordinates, not pixels.

4.7.3.2.5 hide

Definition

void hide()

Description

Hides the axis, resizes the chart area and redraws all visible series.

No effect if the axis is already hidden.

4.7.3.2.6 hideGrid

Definition

void hideGrid(boolean redraw)

Description

Hides the background grid for a given axis and if redraw is omitted or true, redraws the chart

No effect if the grid is already hidden.

4.7.3.2.7 resetZoom

Definition

void resetZoom()

Description

Resets the zoom for a given axis to use its extreme values for min and max (as if a user had double-clicked the chart or drawn the zoom rectangle anywhere but down and right)

4.7.3.2.8 pixelToPoint

Definition

float pixelToPoint(integer Pixel)

Description

Converts the pixel coordinate into chart units based on an axis. The result will be undefined if the pixel location is outside of the chart area.

4.7.3.2.9 pointToPixel

Definition

Description

Converts the chart coordinates based on axis data into the appropriate pixel position for that point (x or y depending on the orientation of the axis)

When ignoreBounds is not specified or specified as undefined, the result will be NaN if the coordinate provided is outside the currently displayed range.

4.7.3.2.10 removeBin

Definition

void removeBin(String label, boolean redraw)

Description

Removes a bin (static text label) from the axis.

If redraw is false, drawing will not occur immediately but will not be entirely prevented. Certain actions such as adding an additional series with redraw = true, or chart dimensions changing may still trigger the chart to draw. The default, if redraw is omitted is **true**.

Note:

Bins may only be removed using this method if they were added using EJSC.Axis.addBin and no

series are currently utilizing them.

4.7.3.2.11 setCaption

Definition

void setCaption(string caption)

Description

Updates the axis caption. This method must be used to change the caption once the chart has been rendered. To set a default caption on creation, see EJSC.Axis.caption.

4.7.3.2.12 setCrosshair

Definition

void setCrosshair(boolean visible, float coordinate, boolean fireEvent)

Description

This method may be used to hide, show and position the cursor position indicator. If the fireEvent parameter is set to true or left undefined the EJSC.Axis.onShowCrosshair or EJSC.Axis.onHideCrosshair events will fire.

4.7.3.2.13 setExtremes

Definition

void setExtremes(float min, float max)

Description

Updates the manual extremes for the axis. Use this method if the series data does not span the range to be displayed on the chart or to limit 100% zoom to a range smaller than the series data.

Example

>> Series data only spans 18 hours on the bottom axis but the chart needs to display an entire day

```
var myChart = new EJSC.Chart( "chart" );
myChart.axis_bottom.setExtremes( 0, 86400000 );
```

4.7.3.2.14 setZoom

Definition:

void setZoom(float min, float max)

Description

Sets the current zoom of the axis to the specified coordinates.

4.7.3.2.15 show

Definition

void show()

Description

Shows the axis, resizes the chart area and redraws all visible series.

No effect if the axis is already visible.

4.7.3.2.16 showGrid

Definition

void **showGrid**(boolean redraw)

Description

Shows the background grid for the axis and if redraw is omitted or true, redraws the chart.

No effect if the grid is already visible.

4.7.3.3 Events

4.7.3.3.1 onHideCrosshair

Definition

void onHideCrosshair(EJSC.Axis axis, EJSC.Chart chart)

Description

Called when the axis crosshair is hidden by the chart. This can occur when the user moves their mouse outside of the chart area or when EJSC.Axis.setCrosshair is called, sending false for the visible parameter and true for the fireEvent parameter.

4.7.3.3.2 onHideCursorPosition

Definition

void onHideCursorPosition(EJSC.Axis axis, EJSC.Chart chart)

Description

This event is fired when the cursor position indicator for an axis is hidden. This will occur when the user's mouse leaves the chart area.

4.7.3.3.3 onNeedsTicks

Definition

array onNeedsTicks(float min, float max, EJSC.Axis axis, EJSC.Chart chart)

Description

This event is triggered whenever the axis ticks need to be redrawn / recalculated. It expects an array of [float y, string label] to be returned which defines exactly where to put the tick marks and labels. In addition, null may be returned in order to skip custom ticks for the current draw and use the chart's build in tick controls.

min: The current minimum value visible on the chart for the axis.

max: The current maximum y value visible on the chart for the axis.

axis: The axis which needs ticks.

chart: The chart that triggered the event.

Notes

- To use the label formatter already assigned to the axis, set label to null (i.e. [min, null])
- To use on an axis with bins (text instead of numbers), simply send in the bin (i.e. ["First Bin", null])

Example

A typical event handler may look like the following:

```
function doBottomAxisNeedsTicks(min, max, axis, chart) {
    // Display 3 tick marks, one at min, one at max and one directly in between
    var result = new Array();

    result.push( [min, null] );
    result.push( [min + ((max - min) / 2), null] );
    result.push( [max, null] );

    // Given a chart with a min and max of 0 and 100, the resulting array looks like:
    // [
        // [0, null],
        // [50, null],
        // [100, null]
        // ]
        return result;
}
```

4.7.3.3.4 onShowCrosshair

Definition

void onShowCrosshair(float coordinate, EJSC.Axis axis, EJSC.Chart chart)

Description

Called when the axis crosshair is shown by the chart. This can occur when the user moves their mouse into the chart area or when EJSC.Axis.setCrosshair is called, sending true for the visible parameter and true for the fireEvent parameter.

4.7.3.3.5 onShowCursorPosition

Definition

void onShowCursorPosition(float coordinate, EJSC.Axis axis, EJSC.Chart chart)

Description

Called when the cursor position indicator becomes visible or changes position on a given axis. This will occur when the user enters the chart area or moves their mouse within the chart area.

4.7.4 EJSC.DataHandler

Base data handler class that defines properties, methods and events common to all data handler descendants. This class does not implement any actual data loading and should not be instantiated. All data handlers should descend from DataHandler or one of its descendants in order to function properly with the EJSC.Series descendants.

Constructor

none

4.7.4.1 Methods

4.7.4.1.1 loadData

Definition

void loadData()

Description

Placeholder method which should be used to clear (if stored) and reload data. This method must be overridden in all descendant classes.

4.7.4.2 Events

4.7.4.2.1 onDataAvailable

Definition

void onDataAvailable()

Description

Placeholder for storing an event to fire after the a descendant class has loaded and processed its data.

Important: This event should be assigned by the EJSC. Series object.

4.7.5 EJSC.GaugeSeries

Base series class that holds all the generic information for each gauge series that is being created. All gauge type series should descend from this class or one of its descendants in order to function properly with the EJSC.Chart class.

Constructor

none

4.7.5.1 Properties

4.7.5.1.1 color (inherited)

Definition

string color = undefined

Description

Defines the series color. If left undefined, the color is pulled from the array of default colors stored in the chart.

Note: May not be applicable to all series (i.e. EJSC.PieSeries)

4.7.5.1.2 coloredLegend (inherited)

Definition

boolean coloredLegend = true

Description

Determines whether the legend text inherits the series color. Setting to false will allow the legend text to inherit its normal cascaded color. To modify this property after series creation see EJSC.Series.setColoredLegend()

4.7.5.1.3 delayLoad (inherited)

EXPERIMENTAL

Definition

boolean delayLoad = true

Description

This property allows a series to force its data handler to begin data retrieval as soon as it is added to a chart. When set to false, the series will initiate data retrieval as soon as it is added to a chart. When true, the data retrieval is initialized when the series first needs to draw.

4.7.5.1.4 legendIsVisible (inherited)

Definition

boolean legendlsVisible = true

Description

Determines whether the legend item associated with the series appears in the legend window. Use the Series.showLegend and Series.hideLegend methods to control legend item visibility after series creation.

4.7.5.1.5 lineOpacity (inherited)

Definition

integer lineOpacity = 100

Description

Determines the line opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setLineOpacity()

4.7.5.1.6 lineWidth (inherited)

Definition

integer lineWidth = 1

Description

Defines the width of the line connecting series points.

4.7.5.1.7 opacity (inherited)

Definition

integer opacity = 50

Description

Determines the fill opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setOpacity()

4.7.5.1.8 title (inherited)

Definition

```
string title = "Series <index>"
```

Description

Defines the series title used in hints and legend display.

Note: The default title of Series <index> (where <index> equals the current position in the series array for its owner chart) is assigned when a series is added to a chart using addSeries. This default title is only applied if the title is blank (i.e. "") at the time the addSeries method is called.

4.7.5.1.9 visible (inherited)

Definition

boolean visible = true

Description

Defines whether the series is visible and can draw on the chart

4.7.5.1.10 x_axis_formatter (inherited)

Definition

string x_axis_formatter = undefined

Description

Defines the formatter that will be used to format hints for the X values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

Types:

EJSC.DateFormatter

EJSC.NumberFormatter

4.7.5.2 Methods

4.7.5.2.1 getDataHandler (inherited)

Definition

EJSC.DataHandler getDataHandler()

Description

Returns the EJSC.DataHandler descendant currently assigned to the series. This is not applicable to all series and will return null if a data handler has not been defined or is not used.

4.7.5.2.2 getVisibility (inherited)

Definition

boolean getVisibility()

Description

Returns a boolean indicating the series current visible state

4.7.5.2.3 hide (inherited)

Definition

void hide()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already hidden.

4.7.5.2.4 hideLegend (inherited)

Definition

void hideLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already hidden.

4.7.5.2.5 reload (inherited)

Definition

void reload()

Description

Triggers a series reload if the functionality is defined in a child class. This may involve retrieving data again or simply recalculating. While the reload() method exists in the base Series class, implementation of the protected methods triggered by calling reload() is at the discretion of the child class.

4.7.5.2.6 setColor (inherited)

Definition

void setColor(string color)

Description

Changes the series color and causes the chart to redraw.

4.7.5.2.7 setColoredLegend (inherited)

Definition

void **setColoredLegend**(boolean coloredLegend)

Description

Sets the EJSC.Series.coloredLegend property and updates the legend to reflect the change.

4.7.5.2.8 setDataHandler (inherited)

Definition

void **setDataHandler**(EJSC.DataHandler dataHandler, boolean reload)

Description

Updates the series data handler and triggers a data reload if reload parameter is true. This method

may not be implemented in all child classes.

4.7.5.2.9 setLineOpacity (inherited)

Definition

void setLineOpacity(integer opacity)

Description

Sets the EJSC.Series.lineOpacity property and redraws the series to reflect the change.

4.7.5.2.10 setLineWidth (inherited)

Definition

void setLineWidth(integer width)

Description

Updates the lineWidth property and redraws the chart.

4.7.5.2.11 setOpacity (inherited)

Definition

void setOpacity(integer opacity)

Description

Sets the EJSC.Series.opacity property and redraws the series to reflect the change.

4.7.5.2.12 setTitle (inherited)

Definition

void setTitle(string title)

Description

Changes the series title and update the legend caption (if applicable).

Note: this will not cause updates to a hint which is visible at the time it is called, though the next time a hint is rendered it will show the new property value.

4.7.5.2.13 show (inherited)

Definition

void show()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already visible.

4.7.5.2.14 showLegend (inherited)

Definition

void showLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already visible.

4.7.5.3 Events

4.7.5.3.1 onAfterDataAvailable (inherited)

Definition

boolean onAfterDataAvailable(EJSC.Chart chart, EJSC.Series series)

Description

Fired after the series has processed its data and before the chart is told to redraw. Returning **false** from this event handler will cancel redrawing the chart.

4.7.5.3.2 onAfterVisibilityChange (inherited)

Definition

boolean onAfterVisibilityChange(EJSC.Series series, EJSC.Chart chart, boolean visible)

Description

Fired when the series visibility changes. Sends series which changed, its owner chart and its new visible property value.

Returning false from this event handler will cancel redrawing the chart.

4.7.5.3.3 onBeforeVisibilityChange (inherited)

Definition

boolean onBeforeVisibilityChange(EJSC.Series series, EJSC.Chart chart)

Description

Fired before the series visibility is about to change. Sends series which changed, its owner chart. The current visible state of the series may be checked using the series visible property.

Returning false from this event handler will cancel the change in visibility.

4.7.6 EJSC.Formatter

The top level Formatter class is used as a base for all label formatters. It defines a format_string property as a guide for descendants. The format method is required to be overridden in all descendant classes in order to function properly when used with the chart classes.

Constructor

EJSC.Formatter()

4.7.6.1 Properties

4.7.6.1.1 format_string

Definition

string format_string = undefined

Description

Defines the format string. Classes that descend from EJSC.Formatter may use this property to store their custom format strings.

4.7.6.2 Methods

4.7.6.2.1 format

Definition

string format(float value, integer precision)

Description

Format is called when a value needs to be formatted for display in the axis, hint, cursor position, etc.

The behavior of the format method is to round a numeric value to the precision specified. Descendants do not need to implement the precision parameter.

4.7.7 EJSC.Point

Base point class that holds all the generic information for each point that is being created. All points should descend from this class or one of its descendants in order to function properly with the EJSC.Chart and EJSC.Series (and descendant) classes.

Constructor

none

4.7.7.1 Properties

4.7.7.1.1 label

Definition

string label = null

Description

Defines the point label. Currently this is only implemented in EJSC.PieSeries EJSC.PiePoint objects.

4.7.7.1.2 userdata

Definition

string userdata = null

Description

Stores a user-defined string related to the point. This may be used to hold information such as database id values, drill down urls or any other related data. Currently only supported by the EJSC.XMLDataHandler (full and short formats).

4.7.7.1.3 x

Definition

float x = null

Description

Defines the point X value. This may be mapped to a text label automatically by the data handler in instances where the point data is not numeric.

4.7.7.1.4 y

Definition

float y = null

Description

Defines point Y value.

4.7.8 EJSC.Series

Base series class that holds all the generic information for each series that is being created. All series should descend from this class or one of its descendants in order to function properly with the EJSC.Chart class.

Constructor

none

4.7.8.1 Properties

4.7.8.1.1 autosort

Definition

boolean autosort = true

Description

Defines whether the series applies the appropriate sort to points prior to drawing. Drawing routines are generally optimized to accept data in a certain order and this property eliminates the need for the developer to worry about that order prior to sending data to the series. If set to false, the data must be properly ordered beforehand in order to ensure the series renders correctly.

Note: May not be applicable to all series (i.e. EJSC.PieSeries, EJSC.AnalogGaugeSeries)

4.7.8.1.2 color

Definition

string color = undefined

Description

Defines the series color. If left undefined, the color is pulled from the array of default colors stored in the chart.

Note: May not be applicable to all series (i.e. EJSC.PieSeries)

4.7.8.1.3 coloredLegend

Definition

boolean coloredLegend = true

Description

Determines whether the legend text inherits the series color. Setting to false will allow the legend text to inherit its normal cascaded color. To modify this property after series creation see EJSC.Series.setColoredLegend()

4.7.8.1.4 delayLoad

EXPERIMENTAL

Definition

boolean delayLoad = true

Description

This property allows a series to force its data handler to begin data retrieval as soon as it is added to a

chart. When set to false, the series will initiate data retrieval as soon as it is added to a chart. When true, the data retrieval is initialized when the series first needs to draw.

4.7.8.1.5 hint_string

Definition

string hint_string = undefined

Description

This property may be used to define a series specific string to be used when displaying point hints. This string may contain replacement indicators (see Text Replacement Options). When left undefined, a default hint defined by the series type will be displayed.

Example

>> Modify the default hint to include custom text.

4.7.8.1.6 legendIsVisible

Definition

boolean legendlsVisible = true

Description

Determines whether the legend item associated with the series appears in the legend window. Use the Series.showLegend and Series.hideLegend methods to control legend item visibility after series creation.

4.7.8.1.7 lineOpacity

Definition

integer lineOpacity = 100

Description

Determines the line opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setLineOpacity()

4.7.8.1.8 lineWidth

Definition

integer lineWidth = 1

Description

Defines the width of the line connecting series points.

4.7.8.1.9 opacity

Definition

```
integer opacity = 50
```

Description

Determines the fill opacity (if applicable) of the series. The range is a percentage and should be specified as an integer between 0 and 100. To modify this property after series creation see EJSC.Series.setOpacity()

4.7.8.1.10 padding

Definition

```
object padding = {
    x_axis_min: undefined,
    x_axis_max: undefined,
    y_axis_min: undefined,
    y_axis_max: undefined
}
```

Description

The padding property may be used to override the series default padding. Padding is the amount of pixels added to the min and max series values in order to push the extremes and prevent the series from hitting the edge of the chart.

The amount of default padding is dependant upon the series type and axis configuration and may not be applicable to all series types.

This property is only applicable during series creation. To retrieve or modify the series padding after creation please see Series.getPadding() and Series.setPadding()

Example

>> Remove all padding from the BarSeries

Definition

```
string title = "Series <index>"
```

Description

Defines the series title used in hints and legend display.

Note: The default title of Series <index> (where <index> equals the current position in the series array for its owner chart) is assigned when a series is added to a chart using addSeries. This default title is only applied if the title is blank (i.e. "") at the time the addSeries method is called.

4.7.8.1.12 visible

Definition

boolean visible = true

Description

Defines whether the series is visible and can draw on the chart

4.7.8.1.13 x_axis

Definition

```
string x_axis = "bottom"
```

Description

Defines the horizontal axis to use for X values. Valid options are "top" or "bottom".

4.7.8.1.14 x_axis_formatter

Definition

```
string x_axis_formatter = undefined
```

Description

Defines the formatter that will be used to format hints for the X values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

```
Types:
EJSC.DateFormatter
EJSC.NumberFormatter
```

4.7.8.1.15 y_axis

Definition

```
string y_axis = "left"
```

Description

Defines the vertical axis to use for Y values. Valid options are "left" or "right".

4.7.8.1.16 y_axis_formatter

Definition

```
string y_axis_formatter = undefined
```

Description

Defines the formatter that will be used to format hints for the Y values before displaying them. If left undefined, the series will inherit the axis formatter of its parent chart.

```
Types: EJSC.DateFormatter EJSC.NumberFormatter
```

4.7.8.2 Methods

4.7.8.2.1 findClosestByPixel

Definition

Description

Returns the point object closest to the screen pixel coordinates provided. The x and y properties of the point object should be in the same scale as the x and y axes assigned to the series. To locate points based on pixel coordinates, see Series.findClosestByPixel()

4.7.8.2.2 findClosestByPoint

Definition

Description

Returns the point object closest to the axis coordinates provided. The x and y properties of the coordinate object should be based on the top left of the viewport and take into account the page scroll. To locate points based on axis coordinates, see Series.findClosestByPoint()

4.7.8.2.3 getDataHandler

Definition

EJSC.DataHandler getDataHandler()

Description

Returns the EJSC.DataHandler descendant currently assigned to the series. This is not applicable to all series and will return null if a data handler has not been defined or is not used.

4.7.8.2.4 getPadding

Definition

Description

Returns an object containing the series current padding. If padding has been set either by the Series.setPadding() method of the Series.padding property during construction the result of this method will be adjusted to return the most current padding values.

4.7.8.2.5 getVisibility

Definition

boolean getVisibility()

Description

Returns a boolean indicating the series current visible state

4.7.8.2.6 hide

Definition

void hide()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already hidden.

4.7.8.2.7 hideLegend

Definition

void hideLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already hidden.

4.7.8.2.8 reload

Definition

void reload()

Description

Triggers a series reload if the functionality is defined in a child class. This may involve retrieving data again or simply recalculating. While the reload() method exists in the base Series class, implementation of the protected methods triggered by calling reload() is at the discretion of the child class.

4.7.8.2.9 setColor

Definition

void setColor(string color)

Description

Changes the series color and causes the chart to redraw.

4.7.8.2.10 setColoredLegend

Definition

void setColoredLegend(boolean coloredLegend)

Description

Sets the EJSC.Series.coloredLegend property and updates the legend to reflect the change.

4.7.8.2.11 setDataHandler

Definition

void setDataHandler(EJSC.DataHandler dataHandler, boolean reload)

Description

Updates the series data handler and triggers a data reload if reload parameter is true. This method

may not be implemented in all child classes.

4.7.8.2.12 setLineOpacity

Definition

void setLineOpacity(integer opacity)

Description

Sets the EJSC.Series.lineOpacity property and redraws the series to reflect the change.

4.7.8.2.13 setLineWidth

Definition

void setLineWidth(integer width)

Description

Updates the lineWidth property and redraws the chart.

4.7.8.2.14 setOpacity

Definition

void setOpacity(integer opacity)

Description

Sets the EJSC.Series.opacity property and redraws the series to reflect the change.

4.7.8.2.15 setPadding

Definition

void setPadding(object Padding, boolean Redraw)

The padding object should be defined as when used in the series constructor. See Series.padding.

Description

This method updates the user-defined series padding and optionally recalculates the chart extremes and redraws the chart.

4.7.8.2.16 setTitle

Definition

void setTitle(string title)

Description

Changes the series title and update the legend caption (if applicable).

Note: this will not cause updates to a hint which is visible at the time it is called, though the next time a hint is rendered it will show the new property value.

4.7.8.2.17 show

Definition

void show()

Description

Changes the series visible state, updates the legend (if applicable) and redraws the owner chart

No effect if the series is already visible.

4.7.8.2.18 showLegend

Definition

void showLegend()

Description

Changes the series legend item visible state.

No effect if the series legend item is already visible.

4.7.8.3 Events

4.7.8.3.1 onAfterDataAvailable

Definition

boolean onAfterDataAvailable(EJSC.Chart chart, EJSC.Series series)

Description

Fired after the series has processed its data and before the chart is told to redraw. Returning **false** from this event handler will cancel redrawing the chart.

4.7.8.3.2 onAfterVisibilityChange

Definition

boolean on After Visibility Change (EJSC. Series series, EJSC. Chart chart, boolean visible)

Description

Fired when the series visibility changes. Sends series which changed, its owner chart and its new visible property value.

Returning false from this event handler will cancel redrawing the chart.

4.7.8.3.3 onBeforeVisibilityChange

Definition

boolean onBeforeVisibilityChange(EJSC.Series series, EJSC.Chart chart)

Description

Fired before the series visibility is about to change. Sends series which changed, its owner chart. The current visible state of the series may be checked using the series.visible property.

Returning false from this event handler will cancel the change in visibility.

4.7.8.3.4 onShowHint

Definition

string onShowHint(EJSC.Point point, EJSC.Series series, EJSC.Chart chart, string hint_string)

Description

Fired before the displaying the hint, this event allows the current hint string to be overridden. See Text Replacement Options for a list of the automatic substitutions available.

4.8 Other Classes

4.8.1 EJSC.BarPoint

BarPoint is used to store an X,Y point value (and optionally a label and/or user defined data). This is used in the EJSC.BarSeries class to store data for each bar to be drawn on the chart. This object is created automatically once data is made available via a EJSC.DataHandler descendant. BarPoint objects should generally not be created manually.

The constructor expects the X and Y value as well as the EJSC.BarSeries which owns the point and optionally (leave null if not used) a label and a userdata string value.

Constructor

```
EJSC.BarPoint( float x, float y, string label, string userdata, EJSC.BarSeries owner )
```

4.8.1.1 Properties

4.8.1.1.1 label (inherited)

Definition

string label = null

Description

Defines the point label. Currently this is only implemented in EJSC.PieSeries EJSC.PiePoint objects.

4.8.1.1.2 userdata (inherited)

Definition

string userdata = null

Description

Stores a user-defined string related to the point. This may be used to hold information such as database id values, drill down urls or any other related data. Currently only supported by the EJSC.XMLDataHandler (full and short formats).

4.8.1.1.3 x (inherited)

Definition

float x = null

Description

Defines the point X value. This may be mapped to a text label automatically by the data handler in instances where the point data is not numeric.

4.8.1.1.4 y (inherited)

Definition

float y = null

Description

Defines point Y value.

4.8.2 EJSC.FloatingBarPoint

FloatingBarPoint is used to store X and min and max Y, or Y and min and max X values for use with a EJSC.FloatingBarSeries. This information is used by the EJSC.FloatingBarSeries class to store data for each bar to be drawn on the chart. This object is created automatically once data is made available via a EJSC.DataHandler descendant. FloatingBarPoint objects should generally not be created manually.

The constructor expects the X, Y, min and max values as well as the EJSC.BarSeries which owns the point and optionally (leave null if not used) a label and a userdata string value.

Constructor

 ${\tt EJSC.FloatingBarPoint(\ float\ x,\ float\ y,\ float\ min,\ float\ max,\ string\ label,\ string\ userdata,\ {\tt EJSC.FloatingBarSeries\ owner\)}}$

4.8.2.1 Properties

4.8.2.1.1 label (inherited)

Definition

string label = null

Description

Defines the point label. Currently this is only implemented in EJSC.PieSeries EJSC.PiePoint objects.

4.8.2.1.2 max

Definition

float max = null

Description

Defines point max value (x or y depending on the series orientation).

4.8.2.1.3 min

Definition

float min = null

Description

Defines point min value (x or y depending on the series orientation).

4.8.2.1.4 userdata (inherited)

Definition

string userdata = null

Description

Stores a user-defined string related to the point. This may be used to hold information such as database id values, drill down urls or any other related data. Currently only supported by the EJSC.XMLDataHandler (full and short formats).

4.8.2.1.5 x (inherited)

Definition

float x = null

Description

Defines the point X value. This may be mapped to a text label automatically by the data handler in instances where the point data is not numeric.

4.8.2.1.6 y (inherited)

Definition

float y = null

Description

Defines point Y value.

4.8.3 EJSC.GaugePoint

GaugePoint is used to store an X point value (and optionally a label). This is used in the EJSC.GaugeSeries class to store data the gauge indicator. This object is created automatically once data is made available via a EJSC.DataHandler descendant. GaugePoint objects should generally not be created manually.

The constructor expects the X value as well as the EJSC.GaugeSeries which owns the point and optionally (leave null if not used) a label string value.

Constructor

```
EJSC.GaugePoint( float x, string label, EJSC.GaugeSeries owner )
```

4.8.3.1 Properties

4.8.3.1.1 label (inherited)

Definition

string label = null

Description

Defines the point label. Currently this is only implemented in EJSC.PieSeries EJSC.PiePoint objects.

4.8.3.1.2 userdata (inherited)

Definition

string userdata = null

Description

Stores a user-defined string related to the point. This may be used to hold information such as database id values, drill down urls or any other related data. Currently only supported by the EJSC.XMLDataHandler (full and short formats).

4.8.3.1.3 x (inherited)

Definition

float x = null

Description

Defines the point X value. This may be mapped to a text label automatically by the data handler in instances where the point data is not numeric.

4.8.4 EJSC.PiePoint

PiePoint is used to store an X point value (and optionally a label value). This is used in the EJSC.PieSeries class store data for each pie piece to be drawn on the chart. This object is created automatically by once data is made available via a EJSC.DataHandler descendant. PiePoint objects should generally not be created manually.

The constructor expects the X value as well as the EJSC.PieSeries which owns the point and optionally (leave null if not used) label and userdata string values.

Constructor

EJSC.PiePoint(number x, string label, string userdata, EJSC.PieSeries owner)

4.8.4.1 Properties

4.8.4.1.1 label (inherited)

Definition

string label = null

Description

Defines the point label. Currently this is only implemented in EJSC.PieSeries EJSC.PiePoint objects.

4.8.4.1.2 userdata (inherited)

Definition

string userdata = null

Description

Stores a user-defined string related to the point. This may be used to hold information such as database id values, drill down urls or any other related data. Currently only supported by the EJSC.XMLDataHandler (full and short formats).

4.8.4.1.3 x (inherited)

Definition

float x = null

Description

Defines the point X value. This may be mapped to a text label automatically by the data handler in instances where the point data is not numeric.

4.8.5 EJSC.StockPoint

StockPoint is used to store the data necessary to display stock-related series such as EJSC.CandlestickSeries and EJSC.OpenHighLowCloseseries. The standard properties are an X point value which defines where along the horizontal axis the point will appear, and the open, close, high and low values used to render the series in the chart. In addition to the standard properties, each point can also store a label and user defined data which may be utilized later during user interaction with the series. StockPoint objects should generally not be created manually.

The constructor expects the X value as well as the open, close, high, and low values, a series which owns the point and optionally (leave null if not used) a label and a userdata string value.

Constructor

```
{\tt EJSC.StockPoint(\ float\ x,\ float\ high,\ float\ low,\ float\ open,\ float\ close,\ string\ label,\ string\ userdata,\ {\tt EJSC.Series\ owner\ )}}
```

4.8.5.1 Properties

4.8.5.1.1 close

Definition

Description

4.8.5.1.2 high

Definition

Description

4.8.5.1.3 label (inherited)

Definition

string label = null

Description

Defines the point label. Currently this is only implemented in EJSC.PieSeries EJSC.PiePoint objects.

4.8.5.1.4 low

Definition

Description

4.8.5.1.5 open

Definition

Description

4.8.5.1.6 userdata (inherited)

Definition

string userdata = null

Description

Stores a user-defined string related to the point. This may be used to hold information such as database id values, drill down urls or any other related data. Currently only supported by the EJSC.XMLDataHandler (full and short formats).

4.8.5.1.7 x (inherited)

Definition

float x = null

Description

Defines the point X value. This may be mapped to a text label automatically by the data handler in instances where the point data is not numeric.

4.8.6 EJSC.XYPoint

XYPoint is used to store a X,Y point value. This is used in series such as EJSC.LineSeries, EJSC.AreaSeries, EJSC.ScatterSeries and EJSC.BarSeries to store each point to be drawn on the chart. This object is created automatically by each series once data is made available via a EJSC.DataHandler descendant. XYPoint objects should generally not be created manually.

The constructor expects the X and Y values as well as the EJSC. Series which owns the point and an optional (leave null if not used) userdata string value.

Constructor

EJSC.XYPoint(number x, number y, string userdata, EJSC.Series owner)

4.8.6.1 Properties

4.8.6.1.1 label (inherited)

Definition

string label = null

Description

Defines the point label. Currently this is only implemented in EJSC.PieSeries EJSC.PiePoint objects.

4.8.6.1.2 userdata (inherited)

Definition

string userdata = null

Description

Stores a user-defined string related to the point. This may be used to hold information such as database id values, drill down urls or any other related data. Currently only supported by the EJSC.XMLDataHandler (full and short formats).

4.8.6.1.3 x (inherited)

Definition

float x = null

Description

Defines the point X value. This may be mapped to a text label automatically by the data handler in instances where the point data is not numeric.

4.8.6.1.4 y (inherited)

Definition

float y = null

Description

Defines point Y value.

4.9 Exporting To SVG

Including SVG Export Functionality

To add the SVG Export functionality to your current implementation, simply include the file immediately after the EJSChart.js

```
<head>
```

</head>

```
<script type="text/javascript" src="/EJSChart/EJSChart.js"></script>
<script type="text/javascript" src="/EJSChart/EJSChart_SVGExport.js"></script>
```

Exporting SVG

Exporting SVG from your chart is as simple as making a single JavaScript call. The following example

shows how to call the exportSVG method and obtain the resulting SVG. The default configuration will produce complete SVG including headers and sized to match the dimensions of source chart. If additional customization is needed, the options parameter allows for settings to be changed at the time of export.

<script type="text/javascript">

</script>

<button onclick="buttonClick();">Export SVG</button>

4.10 META Tag Configuration

META tags must be included in the page header (between <head></head>), should be placed before the <script> tag which imports the EJSChart.js library and are formatted as follows:

<meta name="OPTION-NAME" content="OPTION-VALUE"/>

The options described below affect the loading/initialization stage of the library.

ejsc-src-path

Specifies the base path of the EJSChart.js and other library files. Setting this option is sometimes necessary when the library cannot find the <script> tag in the page header due to dynamic loading or inclusion in the <body> of the page.

META "content" attribute: Path to directory containing EJSChart files, i.e. content="/EJSChart/"

ejsc-auto-load-support-files

Specifies whether the library should automatically load its supporting .js and .css files. This option can be turned off to allow for manual inclusion of the necessary files when site organization necessitates the placing of all .css, .js and images in separate files.

META "content" attribute: true or false, i.e. content="false"

The default, if this tag is not included, is true.

We recommend keeping all EJSChart related files in their original directory structure as version upgrades will be much less work.

ejsc-v1-compatibility

Automatically loads the compatibility file.

META "content" attribute: true or false, i.e. content="true"

The default, if this tag is not included, is false.

4.11 Text Replacement Options

Each series has its own set of text replacement options.

4.12 Using Colors

Using Colors

Colors may be specified in any of the following formats:

5 Getting Support

There are a wide variety of technical support options available for Emprise software products. For users who have purchased the Developer or Enterprise editions, and customers with maintenance plans, support options may include Priority E-mail Support and our Technical Support Hotline. Technical support documents, help files and access to our support forums are available to all users of Emprise software products.

Documentation

Emprise JavaScript Charts documentation is available in several formats:

• Online Web Documentation (Searchable)

Downloadable Formats:

- PDF Manual
- Windows HTML Help (.chm)

• Classic Windows Help (.hlp)

Example Charts

Our website contains a wide variety of example charts to assist you in creating and customizing your own. All examples include full JavaScript and data descriptions as well as links to the relevant help files for each property used.

- Line Chart
- Area Chart
- Bar Chart
- Pie Chart
- More...

Support Forums

Share questions, suggestions, and information about your Emprise software products with other users and the Emprise support and development staff in our Support Forums.

Contact Us

If you cannot find an answer to your question from the resources listed above, send our support department a message and we will get back to you as soon as we can.

General Information & Questions

info@ejschart.com

Sales Related Inquiries

sales@ejschart.com

Technical Support

support@ejschart.com

Phone

Sales: +1 (860) 464-8555

Support: (See support contract)

Mailing Address:

PO Box 129

Ledyard, CT 06339

USA