## Zaawansowana Analiza Statyczna

TODO

Wstęp

Hashe

## Wstęp

## **Table Of Contents**

- Zaawansowana Analiza Statyczna
  - Wstęp
  - Table Of Contents
  - Hashe
  - Struct Cheatsheet
    - if statement
    - Nested if statement
    - for loop
  - Laboratorium 4.1
    - Adres DllMain
    - Adres gethostbyname
    - Wywołania gethostbyname
    - DNS Request
    - Zmienne lokalne 10001656h
    - Parametry 10001656h
    - Adres \cmd.exe /c
    - Co się dzieje w otoczeniu tego adresu
    - Zmienna dword\_1008E5C4
    - Adres 1000FF58h
    - Eksport PLIST
    - sub\_10004E79
    - DllMain
    - Sleep
    - Socket
    - in
    - Adres 1001D988h
  - Laboratorium 4.2
  - Laboratorium 4.3

## Hashe

Plik	SHA-256	VirusTotal
Lab04-01.dll		
Lab04-01.py		

Plik	SHA-256	VirusTotal
Lab05-01.exe		
Lab05-02.exe		
Lab05-03.exe		
Lab05-04.exe		
Lab05-05.exe		

## Struct Cheatsheet

#### if statement

Prosta struktura - porównywanie dwóch wartości, a następnie skok warunkowy

```
mov eax sth1
cmp eax sth2
jnz loc
```

#### Nested if statement

2 zagnieżdżone ify dają 4 różne ścieżki:

- Oba będą prawdziwe
- Tylko pierwszy będzie prawdziwy
- Tylko drugi będzie prawdziwy
- Żaden nie będzie prawdziwy

Komplikuje to strukturę kodu, lecz pojawi się sporo porównań i skoków warunkowych np.

```
cmp ... ...
jnz loc_1
cmp ... ...
jnz loc_2
...
jmp loc_4

loc_1:
...
loc_2:
...
...
loc_4:
*code continnues*
```

#### for loop

Pętla for inicjuje wartość początkową i dopóki nie spełni się określowy warunek kod będzie skakał do tego samego miejsca (jak w pętli 😛)

#### Przykład:

```
mov [ebp+var_ini], 0 ; [] oznacza lokalizację w pamięci
jmp loc_1

loc_2: ; inkrementacja
mov eax, [ebp+var_ini]
add eax, 1
mov [ebp+var_ini], eax

loc_1: ; kod w pętli
cmp [ebp+var], 20h ; wartość końcowa
jge loc_3
...
jmp loc_2
```


## Laboratorium 4.1

#### Adres DllMain

IDA Free nie potrafi rozpoznać funnkcji **DliMain** a jedynie **DliEntryPoint** Adres **DliMain** znajduje się na pozycji *00000001001516Dh* 

Aby odnaleźć **DllMain** trzeba załadować plik FLIRT, a dokładniej vc32rtf

Po sprawdzeniu zakładki *Function Calls* widać kilka funkcji z czego tylko 2 rzeczy nie są *library function dword\_10092E58* jest tylko pointerem, więc DIIMain musi być funkcja *sub\_1000D02E*, która znajduje się właśnie pod tym adresem



```
        Address
        Called function

        .text:1001519F
        call eax; dword_10092E58

        .text:100151A8
        call __CRT_INIT@12; _CRT_INIT(x,x,x)

        .text:100151B8
        call sub_1000D02E

        .text:100151CC
        call __CRT_INIT@12; _CRT_INIT(x,x,x)

        .text:100151DD
        call __CRT_INIT@12; _CRT_INIT(x,x,x)

        .text:100151FB
        call eax; dword_10092E58
```

Po zmianie nazwy funkcji wygląda ona teraz tak:

```
.text:1000D02E
.text:1000D02E
.text:1000D02E
.text:1000D02E ; BOOL stdcall DllMain(HINSTANCE hinstDLL, DWORD fdwReason, LPVOID lpvReserved)
.text:1000D02E DllMain proc near
.text:1000D02E
.text:1000D02E hinstDLL= dword ptr 4
.text:1000D02E fdwReason= dword ptr
.text:1000D02E lpvReserved= dword ptr
.text:1000D02E
                       eax, [esp+fdwReason]
.text:1000D02E mov
.text:1000D032 dec
                       eax
.text:1000D033 jnz
                       loc 1000D107
```


#### Adres gethostbyname

Funkcja **gethostbyname** znajduje się pod adresem 0000000100163CCh



#### Wywołania gethostbyname

Funkcja **gethostbyname** została wywołana 18 razy



## **DNS Request**

Przed wykonaniem funkcji do rejestru jest zapisana zmienna [This is RDO]pics.practicalmalwareanalysis.com, a następnie została przesunięta o 0Dh znaków, czyli 13 co daje pics.practicalmalwareanalysis.com

#### Zmienne lokalne 10001656h

IDA rozpoznała dla funkcji *sub\_10001656* **23** zmienne lokalne (offset ujemny, ponieważ są znajdują się pod EBP. Zmienne lokalne zapisywane są na stacku po zmianie EBP przy wywołaniu funkcji więc znajdują się wyżej)

# **Trace of a Simple Example 9**



```
Low memory
int add3(int a, int b, int c) {
                                                    ESP •
                                                                 12
  int d;
                                                              Old EDI
  d = a + b + c;
  return d;
                                                              Old ESI
                                                              Old EBX
                                                    EBP \longrightarrow
                                                              Old EBP
# Save old EBP
                                                              Old EIP
pushl %ebp
                                                                  3
# Change EBP
movl %esp, %ebp
                                                                  4
# Save caller-save registers if necessary
                                                                  5
pushl %ebx
                                                              Old EDX
pushl %esi
pushl %edi
                                                              Old ECX
# Allocate space for local variable
                                                              Old EAX
subl $4, %esp
                             Access params as positive
# Perform the addition
                             offsets relative to EBP
movl 8(%ebp), %eax
addl 12(%ebp), %eax
                             Access local vars as negative
addl 16(%ebp), %eax
                             offsets relative to EBP
movl %eax, -16(%ebp)
                                                                          55
                                             High memory
```

Parametry 10001656h

Funkcja *sub\_10001656* posiada **jeden** parametr (offset dodatni)

```
.text:10001656 sub_10001656 proc near
.text:10001656
.text:10001656 var_675 = byte ptr -675h
.text:10001656 var_674 = dword ptr -674h
.text:10001656 hModule = dword ptr -670h
.text:10001656 timeout = timeval ptr -66Ch
.text:10001656 name = sockaddr ptr -664h
.text:10001656 in = in_addr ptr -650h
.text:10001656 in = in_addr ptr -650h
.text:10001656 var_640 = byte ptr -640h
.text:10001656 Var_640 = byte ptr -63Fh
.text:10001656 Str = byte ptr -63Dh
.text:10001656 Var_638 = byte ptr -63Dh
.text:10001656 var_637 = byte ptr -637h
.text:10001656 var_637 = byte ptr -637h
.text:10001656 var_544 = byte ptr -50Ch
.text:10001656 var_500 = dword ptr -50Ch
.text:10001656 var_500 = byte ptr -50Ch
.text:10001656 var_500 = byte ptr -3B8h
.text:10001656 buf = byte ptr -3B8h
.text:10001656 var_144 = dword ptr -3B0h
.text:10001656 var_144 = dword ptr -104h
.text:10001656 var_194 = dword ptr -194h
.text:10001656 lpThreadParameter= dword ptr 4
.text:10001656
.text:10001656 sep, 678h
```

#### Adres \cmd.exe /c

String \cmd.exe /c znajduje się pod adresem 10095B34

Co się dzieje w otoczeniu tego adresu

Przeglądając graf na samym początku tej funkcji znajduje się duży string, który zawiera wiadomość. Znajdują się w niej informacje o *szyfrowaniu magicznego numeru (Encrypt Magic Number)* oraz *Remote Shell Session* 


```
aHiMasterDDDDDD db 'Hi, Master [%d/%d/%d %d:%d]',0Dh,0Ah
; DATA XREF: sub_1000FF58+145↑o
db 'WelCome Back...Are You Enjoying Today?',0Dh,0Ah
db 0Dh,0Ah
db 'Machine UpTime [%-.2d Days %-.2d Hours %-.2d Minutes %-.2d Secon'
db 'ds]',0Dh,0Ah
db 'Machine IdleTime [%-.2d Days %-.2d Hours %-.2d Minutes %-.2d Seco'
db 'nds]',0Dh,0Ah
db 0Dh,0Ah
db 'Encrypt Magic Number For This Remote Shell Session [0x%02x]',0Dh,0Ah
db 0Dh,0Ah,0
```

Program porównuje wersje systemu i w zależności od niej wywołuje \cmd.exe /c lub /command.exe /c

```
📕 🚄 🚟
.text:10003695
.text:10003695
.text:10003695 ; Attributes: bp-based frame
.text:10003695
.text:10003695 sub_10003695 proc near
.text:10003695
.text:10003695 VersionInformation= _OSVERSIONINFOA ptr -94h
.text:10003695
.text:10003695 push ebp
.text:10003696 mov
                       ebp, esp
.text:1000369E lea eax, [ebp+VersionInformation]
.text:100036A4 mov [ebp+VersionInformation.dwOSVersionInfoSize], 94h; '"'
.text:100036AE push eax ; lpVersionInformation
.text:100036AE = 11
.text:100036AF call ds:GetVersionExA
                        eax, eax
.text:100036B5 xor
                         [ebp+VersionInformation.dwPlatformId], 2
.text:100036B7 cmp
.text:100036BE setz
                           al
.text:100036C1 leave
.text:100036C2 retn
.text:100036C2 sub_10003695 endp
.text:100036C2
```

dwPlatformId równe 2 oznacza VER\_PLATFORM\_WIN32\_NT co oznacza, że system jest Windows NT lub nowszy

Pola		
MacOSX	6	System operacyjny to Macintosh. Ta wartość została zwrócona przez program Silverlight. Na platformie .NET Core jego zastąpienie to Unix.
Other	7	Dowolny inny system operacyjny. Obejmuje to przeglądarkę (WASM).
Unix	4	System operacyjny to Unix.
Win32NT	2	System operacyjny jest Windows NT lub nowszy.
Win32S	0	System operacyjny to Win32s. Ta wartość nie jest już używana.
Win32Windows	1	System operacyjny jest Windows 95 lub Windows 98. Ta wartość nie jest już używana.
WinCE	3	System operacyjny jest Windows CE. Ta wartość nie jest już używana.
Xbox	5	Platforma deweloperów to Xbox 360. Ta wartość nie jest już używana.



/c jako opcja oznacza, że wykona się komenda podana w stringu Program łączy stringi za pomocą funkcji **strcat** 

```
🛮 🚄 🚟
.text:100101DC
.text:100101DC loc 100101DC:
.text:100101DC lea
                       eax, [ebp+Destination]
                                        ; Destination
.text:100101E2 push
                       eax
.text:100101E3 call
                       strcat
.text:100101E8 pop
                       ecx
                       eax, [ebp+Buf1]
.text:100101E9 lea
.text:100101EF pop
                       ecx
                                        ; Size
.text:100101F0 push
                       0FFh
                                        ; Val
.text:100101F5 push
                       ebx
                                        ; void *
.text:100101F6 push
                       eax
.text:100101F7 call
                       memset
.text:100101FC add
                       esp, 0Ch
```

Dalej w funkcji znajdują się stringi takie jak:

- quit
- exit
- cd
- enmagic
- language
- install
- host
- inject

Najprawdopodbniej są to komendy, ze wzglęgu na wcześniejszą wiadomość z Remote Shell Session

Zmienna dword\_1008E5C4

Zmienna dword\_1008E5C4 została opisana powyżej

## Adres 1000FF58h

Jeżeli porównanie 'robotwork' zwróci zero (eax będzie miało tą samą wartość) skok warunkowy nie wykona się i program będzie wykonywał się dalej (w tym przypadku pójdzie ścieżką czerwoną w lewo)

```
.text:10010444
.text:10010444 loc_10010444:
                                        ; Size
.text:10010444 push
.text:10010446 lea
                       eax, [ebp+Buf1]
.text:1001044C push
                       offset aRobotwork; "robotwork"
.text:10010451 push
                       eax
                                        ; Buf1
.text:10010452 call
                       memcmp
.text:10010457 add
                       esp, 0Ch
.text:1001045A test
                       eax, eax
.text:1001045C jnz
                       short loc 10010468
```

Wykona się tam funkcja sub100052A2, która przyjmuje socket jako argument

```
.text:1001045E push [ebp+s] ; s
.text:10010461 call sub_100052A2
.text:10010466 jmp short loc_100103F6
```

Funkcja ta wykonuje następujące operacje:

- Otwiera rejestr HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion
- Następnie klucz Worktime/Worktimes
- Z tego klucza wyciąga informacje i wysyła je zdalnemu hostowi za pomocą funkcji sub\_100038EE


```
.text:100052DC lea
                       eax, [ebp+phkResult]
.text:100052DF push
                                        ; phkResult
                       eax
.text:100052E0 push
                       0F003Fh
                                        ; samDesired
.text:100052E5 push
                       0
                                        ; ulOptions
                       offset aSoftwareMicros; "SOFTWARE\\Microsoft\\Windows\\CurrentVe"...
.text:100052E7 push
                       80000002h
.text:100052EC push
                                        ; hKey
.text:100052F1 call
                       ds:RegOpenKeyExA
.text:100052F7 test
                       eax, eax
                       short loc 10005309
.text:100052F9 jz
```

```
🛮 🚄 🚾
.text:1000533C lea
                        eax, [ebp+Data]
.text:10005342 push
                                        ; String
                        eax
.text:10005343 call
                        edi ; atoi
.text:10005345 push
                        eax, [ebp+Buffer]
.text:10005346 lea
                       offset aRobotWorktimeD; "\r\n\r\n[Robot WorkTime :] %d\r\n\r'
.text:1000534C push
                                        ; Buffer
.text:10005351 push
                       eax
.text:10005352 call
                       esi; sprintf
.text:10005354 add
                       esp, 10h
.text:10005357 lea
                        eax, [ebp+Buffer]
.text:1000535D push
                                        ; Str
.text:1000535F push
                       eax
.text:10005360 call
                        strlen
.text:10005365 pop
                        ecx
.text:10005366 push
                       eax
                                          len
                       eax, [ebp+Buffer]
.text:10005367 lea
                                        ; int
.text:1000536D push
                        eax
.text:1000536E push
                        [ebp+s]
                                        ; 5
.text:10005371 call
                       sub 100038EE
.text:10005376 add
                       esp, 10h
```

#### **Eksport PLIST**

Na początku funkcja sprawdza wersję systemu, lecz tym razem sprawdzając czy Majorversion jest większa niż 5 (czyli wersja nowsza lub równa Windows 2000)

```
📕 🚄 🖼
.text:10007025 ; Exported entry 4. PSLIST
.text:10007025
.text:10007025
.text:10007025
.text:10007025 ; int stdcall PSLIST(int, int, char *Str, int)
.text:10007025 public PSLIST
.text:10007025 PSLIST proc near
.text:10007025
.text:10007025 Str= dword ptr 0Ch
.text:10007025
.text:10007025 mov
                     dword 1008E5BC, 1
.text:1000702F call sub 100036C3
.text:10007034 test eax, eax
.text:10007036 jz
                     short loc 1000705B
```




W tym miejscu funkcja sprawdza, czy jako parametr został podany string. W obu przypadkach obie funkcje enumerują Wszystkie atywne procesy. Na początku wykonuje snapshot procesów za pomocą

#### CreateToolhelp32Snapshot,

```
.text:10006558 call CreateToolhelp32Snapshot
```

Process32First, aby wyciągnąć ze snapshota pierwszy proces, a następnie w pętli while Process32Next.



Funkcja pozyskuje również informacje o tym do jakiego pliku należy dany proces za pomocą **GetModuleFileNameEx**, wszystko w czytelnym formacie

```
iProce db ODh,OAh ; DATA XREF: sub_10006518+69↑o ; sub_1000664C:loc_100066DF↑o db ODh,OAh db 'ProcessID ProcessName ThreadNumber',ODh,OAh,O align 4
```

#### sub\_10004E79

Funkcja wywołuje funkcję **GetSystemDefaultLangID**, która zwraca ID domyślnie ustawionego języka systemowego, a następnie go wysyła zdalnemu hostowi

```
.text:10004E79 push
                     ebp
.text:10004E7A mov
                   ebp, esp
.text:10004E7C sub
                    esp, 400h
.text:10004E82 and
                    [ebp+Buffer], 0
.text:10004E89 push
                     edi
.text:10004E8A mov
                     ecx, 0FFh
.text:10004E8F xor
                     eax, eax
.text:10004E91 lea edi, [ebp+var_3FF]
.text:10004E97 rep stosd
.text:10004E99 stosw
.text:10004E9B stosb
.text:10004E9C call
                   ds:GetSystemDefaultLangID
.text:10004EA2 movzx eax, ax
                    eax
eax, [ebp+Buffer]
.text:10004EA5 push
.text:10004EA6 lea
.text:10004EAC push offset aLanguageId0xX ; "\r\n\r\n[Language:] id:0x%x\r\n\r\n"
.text:10004EB1 push eax
                                    ; Buffer
.text:10004EB2 call ds:sprintf
.text:10004EB8 add
                    esp, 0Ch
                   eax, [ebp+Buffer]
.text:10004EBB lea
                   0
.text:10004EC1 push
                   eax
.text:10004EC3 push
                                     ; Str
.text:10004EC4 call
                     strlen
.text:10004EC9 pop
                     ecx
                                     ; len
.text:10004ECA push
                     eax
                     eax, [ebp+Buffer]
.text:10004ECB lea
.text:10004ED1 push
                     eax
                                   ; int
.text:10004ED2 push
                      [ebp+s]
.text:10004ED5 call
                     Send
.text:10004EDA add
                     esp, 10h
.text:10004EDD pop
                     edi
.text:10004EDE leave
```


Wszystkie ID są rozpisane przez Microsoft tutaj

Dla przykładu język polski ma przypisane ID **0x0015** lub **0x0415**, a angielski **0x0009**, **0x0409** (odmiana amerykańska) lub **0x0809** (odmiana brytyjska) itd.


Funkcja mogłaby przyjąć nazwę **SendDefaultLangID** bądź **RetrieveDefaultLangID** 

#### DIIMain


Aby dowiedzieć się ile wywołań ma *DllMain* najlepszym rozwiązaniem jest stworzenie grafu np. z takimi ustawieniami:



DllMain używa bezpośrednio 7 funkcji:



Używając głębokości 2 (Jeżeli nie popełniłem błędu w liczeniu) używa 66 funkcji:



## Sleep

Przed wywołaniem funkcji najpierw musi ona przyjąć parametry. Dzieje się to za pomocą *push*. Musimy w takim razie sprawdzić jaką wartość będzie miał rejestr **eax**.

Zaczyna się od tego, że do rejestru eax zapisana jest offset stringa "[This is CTI]30".

Do offsetu następnie jest dodana wartość 0Dh (13 base 10) co sprawia, że string to teraz "30".

push eax wrzuca eax na stack, gdzie następnie jest wywołana funkcja *atoi*, która w języku c++ zamienia string na liczbę. Tak więc funckja zwraca wartość 30. Według poniższej tabelki eax jest pierwszym rejestrem, który przychowuje pierwszą zwróconą wartość.

Figure 3.4: Register Usage

Register   Usage   function calls			Preserved across
passes information about the number of vector registers used; 1st return register callee-saved register used to pass 4th integer argument to functions vector used to pass 3rd argument to functions; 2nd return register stack pointer stack pointer callee-saved register; optionally used as frame pointer used to pass 2nd argument to functions register stack pointer callee-saved register; optionally used as frame pointer used to pass 2nd argument to functions vector as used to pass 5th argument to functions vector as used to pass 5th argument to functions vector as used to pass 6th argument to functions vector as used to pass 6th argument to functions vector as used to pass 6th argument to functions vector as used to pass 6th argument to functions vector as used to pass in a function's vector as the property register, used for passing a function's vector allee-saved register; optionally used as GOT vector allee-saved register; optionally used as GOT vector as pointer vector as the property register and return floating point arguments vector as pointer vector as the property registers vector as the property register and the property registers vector as the property registers vector as the property register and the property registers vector as the property register and the property registers vector as the property register and property register and property register and property re	Register	Usage	function calls
registers used; 1st return register callee-saved register used to pass 4th integer argument to functions verdx used to pass 3rd argument to functions; 2nd return register stack pointer callee-saved register; optionally used as frame pointer used to pass 2nd argument to functions register used to pass 2nd argument to functions used to pass 2nd argument to functions verdi used to pass 5th argument to functions verdi used to pass 5th argument to functions verdi used to pass 6th argument to functions verdi ve	%rax	temporary register; with variable arguments	No
%rbxcallee-saved registerYes%rcxused to pass 4th integer argument to functionsNo%rdxused to pass 3rd argument to functions; 2nd return registerNo%rspstack pointerYes%rbpcallee-saved register; optionally used as frame pointerYes%rsiused to pass 2nd argument to functionsNo%rdiused to pass 2nd argument to functionsNo%r8used to pass 5th argument to functionsNo%r9used to pass 6th argument to functionsNo%r10temporary register, used for passing a function's static chain pointerNo%r11temporary registerYes%r15callee-saved registersYesbase pointerused to pass and return floating point argumentsNo%xmm0-%xmm1used to pass floating point argumentsNo%xmm8-%xmm15temporary registersNo%mmx0-%mmx7temporary registersNo%st0,%st1temporary registers; used to return long double argumentsNo%st2-%st7temporary registersNo%fsReserved for system (as thread specific data register)NomxcsrSSE2 control and status wordpartialx87 SWx87 status wordNo		passes information about the number of vector	
#rcx used to pass 4th integer argument to functions used to pass 3rd argument to functions; 2nd return register  #rsp stack pointer  #rsp stack pointer  #rsi used to pass 2nd argument to functions  #rdi used to pass 2nd argument to functions  #rdi used to pass 1st argument to functions  #rsi used to pass 5th argument to functions  #rsi used to pass 6th argument to functions  #rsi used to pass for passing a function's  #rsi temporary register  #rsi used to passing a function's  #rsi temporary registers  #rsi callee-saved register; optionally used as GOT yes  #rsi used to pass for passing a function's  #rsi temporary registers  #rsi used to pass for passing a function's  #rsi temporary registers  #rsi used to pass for passing a function's  #rsi temporary registers  #rsi used to pass for passing a function's  #rsi temporary registers  #rsi used to pass for passing a function's  #rsi temporary registers  #rsi used to pass for passing a function's  #rsi temporary registers  #rsi used to pass for passing a function's  #rsi temporary registers  #rsi used to pass for passing a function's  #rsi used to pass		registers used; 1st return register	
#rdx used to pass 3rd argument to functions; 2nd return register  #rsp stack pointer  callee-saved register; optionally used as frame pointer  used to pass 2nd argument to functions  register  #rsi used to pass 2nd argument to functions  used to pass 1st argument to functions  no used to pass 5th argument to functions  no used to pass 5th argument to functions  no used to pass 6th argument to functions  register, used for passing a function's static chain pointer  temporary register, used for passing a function's static chain pointer  temporary registers  callee-saved register; optionally used as GOT yes  base pointer  used to pass and return floating point arguments  used to pass floating point arguments  temporary registers  temporary registers  temporary registers; used to return long double arguments  temporary registers  temporary registers  temporary registers  set 2-%st7  #fs  Reserved for system (as thread specific data register)  SSE2 control and status word  x87 status word	%rbx	callee-saved register	Yes
register stack pointer callee-saved register; optionally used as frame pointer used to pass 2 <sup>nd</sup> argument to functions register used to pass 2 <sup>nd</sup> argument to functions register used to pass 1 <sup>st</sup> argument to functions register used to pass 1 <sup>st</sup> argument to functions register used to pass 5 <sup>th</sup> argument to functions register used to pass 5 <sup>th</sup> argument to functions register used to pass 6 <sup>th</sup> argument to functions register regist	%rcx	used to pass 4 <sup>th</sup> integer argument to functions	No
%rspstack pointerYes%rbpcallee-saved register; optionally used as frame pointerYes%rsiused to pass 2nd argument to functionsNo%rdiused to pass 1st argument to functionsNo%r8used to pass 5th argument to functionsNo%r9used to pass 6th argument to functionsNo%r10temporary register, used for passing a function's static chain pointerNo%r11temporary registerNo%r15callee-saved registers; optionally used as GOT base pointerYes%xmm0-%xmm1used to pass and return floating point argumentsNo%xmm2-%xmm7used to pass floating point argumentsNo%xmm8-%xmm15NoNo%mmx0-%mmx7temporary registersNo%st0,%st1temporary registers; used to return long double argumentsNo%st2-%st7temporary registersNo%fsReserved for system (as thread specific data register)NomxcsrSSE2 control and status wordpartialx87 SWx87 status wordNo	%rdx	used to pass 3 <sup>rd</sup> argument to functions; 2 <sup>nd</sup> return	No
callee-saved register; optionally used as frame pointer  used to pass 2 <sup>nd</sup> argument to functions  used to pass 1 <sup>st</sup> argument to functions  vused to pass 5 <sup>th</sup> argument to functions  used to pass 5 <sup>th</sup> argument to functions  vused to pass 6 <sup>th</sup> argument to functions  vused to pass function's static chain pointer  temporary register, used for passing a function's  vused to allee-saved registers  callee-saved register; optionally used as GOT base pointer  vused to pass and return floating point arguments  vused to pass floating point arguments  vused t		register	
pointer used to pass 2 <sup>nd</sup> argument to functions No srdi used to pass 1 <sup>st</sup> argument to functions No used to pass 5 <sup>th</sup> argument to functions No sr9 used to pass 6 <sup>th</sup> argument to functions No temporary register, used for passing a function's static chain pointer temporary register callee-saved registers callee-saved register; optionally used as GOT base pointer used to pass and return floating point arguments used to pass and return floating point arguments vamm2-%xmm1 sxmm2-%xmm7 sxmm8-%xmm15 mmx0-%mmx7 temporary registers temporary registers temporary registers temporary registers temporary registers; used to return long double arguments temporary registers Reserved for system (as thread specific data register)  mxcsr SSE2 control and status word x87 status word No	%rsp	stack pointer	Yes
#rsi used to pass 2nd argument to functions used to pass 1st argument to functions No used to pass 5th argument to functions No used to pass 6th argument to functions No used to pass 6th argument to functions No temporary register, used for passing a function's static chain pointer temporary register No waster callee-saved registers and return floating point arguments No used to pass and return floating point arguments No waster temporary registers used to return long double arguments temporary registers No waster was	%rbp	callee-saved register; optionally used as frame	Yes
#rdi used to pass 1st argument to functions   well to pass 5th argument to functions		pointer	
% r 8used to pass 5th argument to functionsNo% r 9used to pass 6th argument to functionsNo% r 10temporary register, used for passing a function's static chain pointerNo% r 11temporary registerNo% r 12-r 14callee-saved registersYes% r 15callee-saved register; optionally used as GOT base pointerYes% xmm0-% xmm1used to pass and return floating point argumentsNo% xmm2-% xmm7used to pass floating point argumentsNo% xmm8-% xmm15temporary registersNo% st0,% st1temporary registers; used to return long double argumentsNo% st2-% st7temporary registersNo% fsReserved for system (as thread specific data register)NomxcsrSSE2 control and status wordpartialx87 SWx87 status wordNo	%rsi	used to pass 2 <sup>nd</sup> argument to functions	No
%r9used to pass 6th argument to functionsNo%r10temporary register, used for passing a function's static chain pointerNo%r11temporary registerNo%r12-r14callee-saved registersYes%r15callee-saved register; optionally used as GOT base pointerYes%xmm0-%xmm1used to pass and return floating point argumentsNo%xmm2-%xmm7used to pass floating point argumentsNo%xmm8-%xmm15temporary registersNo%st0,%st1temporary registers; used to return long double argumentsNo%st2-%st7temporary registersNo%fsReserved for system (as thread specific data register)NomxcsrSSE2 control and status wordpartialx87 SWx87 status wordNo	%rdi		No
temporary register, used for passing a function's static chain pointer temporary register temporary register callee-saved registers callee-saved register; optionally used as GOT base pointer used to pass and return floating point arguments used to pass floating point arguments No temporary registers No temporary registers temporary registers temporary registers; used to return long double arguments temporary registers; used to return long double arguments temporary registers  %st2-%st7 temporary registers No Reserved for system (as thread specific data register)  mxcsr SSE2 control and status word x87 status word No	%r8	used to pass 5 <sup>th</sup> argument to functions	No
static chain pointer temporary register callee-saved registers; optionally used as GOT base pointer sxmm0-%xmm1 %xmm2-%xmm7 sxmm8-%xmm15 mmx0-%mmx7 temporary registers temporary registers temporary registers temporary registers temporary registers temporary registers temporary registers; used to return long double arguments %st2-%st7 temporary registers Reserved for system (as thread specific data register)  mxcsr SSE2 control and status word x87 SW  static chain pointer No Yes No Yes No Yes No No No No Temporary registers No	%r9	used to pass 6 <sup>th</sup> argument to functions	No
%r11temporary registerNo%r12-r14callee-saved registersYes%r15callee-saved register; optionally used as GOT base pointerYes%xmm0-%xmm1used to pass and return floating point argumentsNo%xmm2-%xmm7used to pass floating point argumentsNo%xmm8-%xmm15temporary registersNo%mmx0-%mmx7temporary registersNo%st0,%st1temporary registers; used to return long double argumentsNo%st2-%st7temporary registersNo%fsReserved for system (as thread specific data register)NoSSE2 control and status wordpartialx87 SWx87 status wordNo	%r10	temporary register, used for passing a function's	No
%r12-r14callee-saved registersYes%r15callee-saved register; optionally used as GOT base pointerYes%xmm0-%xmm1used to pass and return floating point arguments used to pass floating point argumentsNo%xmm2-%xmm7used to pass floating point argumentsNo%xmm8-%xmm15temporary registersNo%st0,%st1temporary registers; used to return long double argumentsNo%st2-%st7temporary registersNo%fsReserved for system (as thread specific data register)NomxcsrSSE2 control and status wordpartialx87 SWx87 status wordNo		static chain pointer	
callee-saved register; optionally used as GOT base pointer used to pass and return floating point arguments No used to pass floating point arguments No weed to pass floating point arguments No temporary registers No temporary registers No temporary registers; used to return long double arguments temporary registers No No Reserved for system (as thread specific data register)  mxcsr SSE2 control and status word x87 status word No	%r11	temporary register	No
base pointer  "sxmm0-%xmm1  "sxmm2-%xmm7  "sxmm8-%xmm15  "mmx0-%mmx7  "st0,%st1  "st2-%st7  "sfs  "mxcsr  "x87 SW  "sxmm8 pointer  used to pass and return floating point arguments  No  No  No  temporary registers  temporary registers; used to return long double arguments  temporary registers  No  No  No  No  SSE2 control and status word  x87 status word  No  No  No  No  No  No  No  No  No  N	%r12-r14	callee-saved registers	Yes
%xmm0-%xmm1used to pass and return floating point argumentsNo%xmm2-%xmm7used to pass floating point argumentsNo%xmm8-%xmm15temporary registersNo%mmx0-%mmx7temporary registersNo%st0,%st1temporary registers; used to return long double argumentsNo%st2-%st7temporary registersNo%fsReserved for system (as thread specific data register)NomxcsrSSE2 control and status wordpartialx87 SWx87 status wordNo	%r15	callee-saved register; optionally used as GOT	Yes
%xmm2-%xmm7used to pass floating point argumentsNo%xmm8-%xmm15temporary registersNo%mmx0-%mmx7temporary registersNo%st0,%st1temporary registers; used to return long double argumentsNo%st2-%st7temporary registersNo%fsReserved for system (as thread specific data register)NomxcsrSSE2 control and status wordpartialx87 SWx87 status wordNo		base pointer	
%xmm8-%xmm15temporary registersNo%mmx0-%mmx7temporary registersNo%st0,%st1temporary registers; used to return long double argumentsNo%st2-%st7temporary registersNo%fsReserved for system (as thread specific data register)NomxcsrSSE2 control and status wordpartialx87 SWx87 status wordNo	xmm0-xmm1	used to pass and return floating point arguments	No
%mmx0-%mmx7temporary registersNo%st0,%st1temporary registers; used to return long double arguments%st2-%st7temporary registersNo%fsReserved for system (as thread specific data register)NomxcsrSSE2 control and status wordpartialx87 SWx87 status wordNo	%xmm2-%xmm7	used to pass floating point arguments	No
%st0,%st1       temporary registers; used to return long double arguments       No         %st2-%st7       temporary registers       No         %fs       Reserved for system (as thread specific data register)       No         mxcsr       SSE2 control and status word       partial         x87 SW       x87 status word       No	%xmm8-%xmm15	temporary registers	No
double arguments temporary registers Reserved for system (as thread specific data register)  mxcsr x87 SW SSE2 control and status word x87 status word No	%mmx0-%mmx7	temporary registers	No
*st2-*st7 temporary registers Reserved for system (as thread specific data register)  mxcsr x87 SW SSE2 control and status word x87 status word No	%st0,%st1	temporary registers; used to return long	No
Reserved for system (as thread specific data register)  mxcsr x87 SW  Reserved for system (as thread specific data register) SSE2 control and status word x87 status word No		double arguments	
ister)  SSE2 control and status word  x87 SW x87 status word No	%st2-%st7	temporary registers	No
mxcsr SSE2 control and status word partial No	%fs	Reserved for system (as thread specific data reg-	No
x87 SW x87 status word No		ister)	
	mxcsr	SSE2 control and status word	partial
x87 CW x87 control word Yes	x87 SW	x87 status word	No
	x87 CW	x87 control word	Yes

21

AMD64 ABI Draft 0.99.7 - November 17, 2014 - 15:08

Następnie wartość zostaje pomnożona przez 3E8h (3 \* 16^2 + 14 \* 16 + 8) czyli 1000.

Ta wartość jest przyjmowana jako parametr przez funckcję sleep, która przyjmuje czas w milisekundach. To oznacza, że program śpi przez **30 sekund** 

#### Socket

Funkcja Socek przyjmuje 3 parametry:

- int af
- int type
- int protocol

Według dokumentacji Microsoft

af oznacza address family type oznacza typ socketa protocol oznacza użyty protokół

W tym miejscu odwołanie w pseudo C/C++ wyglądało by tak:

```
socket(2, 1, 6)
```

Co oznacza utworzony socket z address family AF\_INET (Adres IPv4), type SOCK\_STREAM (Two way connection, przy AF\_INET TCP) i protokołem IPPROTO\_TCP

in

Po wyszukaniu każdej linii zawierającej EDh znalazłem tylko jeden adres w którym została użyta funkcja in

.rdata:1001661E		dq 60000.0
.text:100061DB	sub_10006196	in eax, dx
.text:10005305	sub_100052A2	jmp loc_100053F6

Funckcja in używa dwóch rejestrów: eax (Magic Value) oraz dx (port)

Po kliknięciu na wartość 564D5868h i kliknięciu klawisza R ukazuje nam się string VMXh, a w edx VX.


Po instrukcji in jest instrukcja cmp ebx, 'VMXh', która sprawdza czy otrzymano odpowiedź od portu VMware.

Program jest zatem w stanie wykryć obecność w maszynie wirtualnej

Po wykonaniu funkcji znajduje się też string Found Virtual Machine, Install Cancel.

#### Adres 1001D988h

Pod tym adresem znajdują się losowe dane. Jednak w książce odpowiednik tego zadania wskazuje na użycie skryptu w pythonie. Niestety w IDA Free nie da się używać takich skryptów. Skrypt jedyne co robi to xoruje każdy znak z 55h, więc zrobiłem to ręcznie używając Cyberchef



## Laboratorium 4.2

## Laboratorium 4.3