2.5D rendering in Context

"2.5D rendering is used to extrude polygons from their surrounding features, creating an illusion of depth in your map"

In this module we will examine the 2.5D renderer in QGIS and understand the basic options that can be used to specify how extrusion should take place.

You try:

Goal: *To learn basic workflows behind working with the 2.5D renderer*

You need to do the following tasks to achieve results like the example above :

Add the places layer
Buffer the layer
Select the '2.5D' renderer for the buffer layer
Use an expression to set the height
Experiment with roof, wall colours

Check your results:

✔ Your map looks similar to the image above

Name	Value
Linear scaling	scale_linear("pop_max" , 4645, 19028000, 2, 10)
Exponential scaling	scale_exp("pop_max" , 4645, 19028000, 2, 10, 1.1)

More about 2.5D rendering

In order to simulate perspective for extruded objects, an algorithm is used to compute the distance of each object from the top of the map. This distance is then used to render the objects, starting with those closest to the top of the map, ending with those closest to the bottom. You can view (and modify) this formula in the 'control feature rendering order' expression editor.

2.5D renderer uses a special symbol layer style called '**geometry_generator**' to compute the extruded geometry for the 'walls' and 'roof' of the extruded polygon. You can use the geometry generator to do other cool stuff like buffering geometries on the fly.

If you change the renderer to **single symbol renderer** QGIS will create a number of symbol layers and preserve the 2.5D renderered style. You can use these symbol layers to manipulate the 2.5D rendering in fine grained detail. You can also add additional geometry generator symbol layers to create effects like this:

An extra ring added to the 'roof' : 'buffer(translate($geometry, cos(radians(eval(@qgis_25d_angle))) * eval(@qgis_25d_height), sin(radians(eval(@qgis_25d_angle))) * eval(@qgis_25d_height)), 0.5)

One other important thing to note: 2.5D renderer uses two special **layer variables** to store the **qgis_25d_angle** and **qgis_25d_height**. If you try to copy the style from one layer to another, these values will NOT be copied, so you need to manually set them on the destination layer if needed.

Check your knowledge:

1. **2.5D renderer can be used with these feature types:**
a) point layer
b) line layer
c) polygon layer

Answer: 1c

Further reading:

http://www.xyht.com/spatial-itgis/qgis-2-5d-functionality/
http://www.opengis.ch/2015/11/02/qgis-crowdfunding-2-5d-rendering/

http://qgis.org