Operating Systems CSCI 3150

Lecture 12: Memory Management Part III: Swapping

Hong Xu


https://github.com/henryhxu/CSCI3150

Overview

- Mechanisms
- Policies


Beyond Physical Memory: Mechanisms

- Use part of disk as memory
 - OS needs a place to stash away portions of address space that currently aren't in great demand.
 - In modern systems, this role is usually served by a hard disk drive.



Swap Space

- Reserve some space on the disk for moving pages back and forth.
- OS needs to remember the swap space, in page-sized unit.



Physical Memory and Swap Space

Present Bit

- Add some machinery higher up in the system in order to support swapping the pages to and from the disk.
 - When the hardware looks in the PTE, it may find that the page is not present in physical memory.

| Value | Meaning | | |
|-------|---|--|--|
| 1 | page is present in physical memory | | |
| 0 | The page is not in memory but rather on disk. | | |

Concepts

Page fault

- Accessing page that is not in physical memory.
- If a page is not present and has been swapped to disk, the OS needs to swap the page back into memory in order to service the page fault.

Page replacement


- The OS likes to page out some pages to make room for the new ones it is about to bring in
- The process of picking a page to evict (or replace) is known as pagereplacement policy.

When to Perform Page Replacement

- Lazy approach...
 - OS waits until memory is full to start replacing pages.
 - This is clearly unrealistic... Do not procrastinate!
- Swap Daemon, Page Daemon
 - When there are fewer than LW (low watermark) pages available, a background thread that is responsible for freeing memory runs.
 - The thread evicts pages until there are HW (high watermark) pages available.

Page Fault Control Flow

PTE used for data such as the PFN of the page for a disk address.



Page Fault Control Flow – Hardware

```
1:
        VPN = (VirtualAddress & VPN MASK) >> SHIFT
2:
         (Success, TlbEntry) = TLB Lookup(VPN)
        if (Success == True) // TLB Hit
3:
4:
           if (CanAccess(TlbEntry.ProtectBits) == True)
5:
                 Offset = VirtualAddress & OFFSET MASK
6:
                 PhysAddr = (TlbEntry.PFN << SHIFT) | Offset
7:
                 Register = AccessMemory(PhysAddr)
8:
           else RaiseException(PROTECTION FAULT)
        else // TLB Miss
9:
10:
            PTEAddr = PTBR + (VPN * sizeof(PTE))
11:
           PTE = AccessMemory (PTEAddr)
           if (PTE.Valid == False)
12:
13:
                 RaiseException (SEGMENTATION FAULT)
14:
     else
15:
              if (CanAccess(PTE.ProtectBits) == False)
16:
                 RaiseException (PROTECTION FAULT)
              else if (PTE.Present == True)
17:
                  // assuming hardware-managed TLB
18:
19:
                 TLB Insert (VPN, PTE.PFN, PTE.ProtectBits)
20:
                RetryInstruction()
21:
              else if (PTE.Present == False)
                 RaiseException(PAGE FAULT)
22:
```

Page Fault Control Flow – Software

```
1: PFN = FindFreePhysicalPage()
2: if (PFN == -1) // no free page found
3: PFN = EvictPage() // run replacement algorithm
4: DiskRead(PTE.DiskAddr, pfn) // sleep (waiting for I/O)
5: PTE.present = True // update page table with present
6: PTE.PFN = PFN // bit and translation (PFN)
7: RetryInstruction() // retry instruction
```

- The OS must find a physical frame for the soon-be-faulted-in page to reside within.
- If there is no such page, waiting for the replacement algorithm to run


Summary

- Swapping: making the part of disk as memory
- Present bit required



Goal of Cache Management

- To minimize cache misses
- To improve average memory access time (AMAT)



| Notation | Meaning | |
|------------|--|--|
| T_{M} | The cost of accessing memory | |
| T_D | The cost of accessing disk | |
| P_{Hit} | The probability of finding the data item in the cache(a hit) | |
| P_{Miss} | The probability of not finding the data in the cache(a miss) | |

The Optimal Replacement Policy

- Lead to the fewest number of misses overall.
 - Replace the page that will be accessed <u>furthest in the future.</u>
 - Result in the fewest possible cache misses.
- Serve only as a comparison point, to know how close we are to perfection.

Tracing the Optimal Policy

Reference Row
0 1 2 0 1 3 0 3 1 2 1

| Access | Hit/Miss? | Evict | Resulting Cache State |
|--------|-----------|-------|-----------------------|
| 0 | Miss | | 0 |
| 1 | Miss | | 0,1 |
| 2 | Miss | | 0,1,2 |
| 0 | Hit | | 0,1,2 |
| 1 | Hit | | 0,1,2 |
| 3 | Miss | 2 | 0,1,3 |
| 0 | Hit | | 0,1,3 |
| 3 | Hit | | 0,1,3 |
| 1 | Hit | | 0,1,3 |
| 2 | Miss | 3 | 0,1,2 |
| 1 | Hit | | 0,1,2 |

Hit rate is $\frac{Hits}{Hits+Misses} = 54.6\%$

Future is unknown!

A Simple Policy: FIFO

- Pages were placed in a queue when they enter the system.
- When a replacement occurs, the page on the head of the queue (the "<u>first-in</u>" page) is evicted.
 - Simple to implement
 - Agnostic to the importance of pages

Tracing the FIFO Policy

Reference Row
0 1 2 0 1 3 0 3 1 2 1


| Access | Hit/Miss? | Evict | Resulting Cache State |
|--------|-----------|-------|-----------------------|
| 0 | Miss | | 0 |
| 1 | Miss | | 0,1 |
| 2 | Miss | | 0,1,2 |
| 0 | Hit | | 0,1,2 |
| 1 | Hit | | 0,1,2 |
| 3 | Miss | 0 | 1,2,3 |
| 0 | Miss | 1 | 2,3,0 |
| 3 | Hit | | 2,3,0 |
| 1 | Miss | | 3,0,1 |
| 2 | Miss | 3 | 0,1,2 |
| 1 | Hit | | 0,1,2 |

Hit rate is $\frac{Hits}{Hits+Misses} = 36.4\%$

Even though page 0 had been accessed a number of times, FIFO still kicks it out.

Belady's Anomaly

We would expect the cache hit rate to increase when the cache gets larger. But in this case, with FIFO, it gets worse.



Another Simple Policy: Random

- Picks a random page to replace under memory pressure.
 - It doesn't really try to be too intelligent in picking which page to evict
 - Random does depends entirely upon how lucky <u>Random</u> gets in its choice.

| Access | Hit/Miss? | Evict | Resulting Cache State |
|--------|-----------|-------|-----------------------|
| 0 | Miss | | 0 |
| 1 | Miss | | 0,1 |
| 2 | Miss | | 0,1,2 |
| 0 | Hit | | 0,1,2 |
| 1 | Hit | | 0,1,2 |
| 3 | Miss | 0 | 1,2,3 |
| 0 | Miss | 1 | 2,3,0 |
| 3 | Hit | | 2,3,0 |
| 1 | Miss | 3 | 2,0,1 |
| 2 | Hit | | 2,0,1 |
| 1 | Hit | | 2,0,1 |

Using History

- Learn on the past and use **history**.
 - Two types of historical information.

| Historical Information | Meaning | Algorithms |
|---------------------------|--|------------|
| Recency | The more recently a page has been accessed, the more likely it will be accessed again | LRU |
| Frequency | If a page has been accessed many times, It should not be replaced as it clearly has some value | LFU |

Using History: LRU

Replace the least-recently-used page.


Reference Row

0 1 2 0 1 3 0 3 1 2 1

| Access | Hit/Miss? | Evict | Resulting Cache State |
|--------|-----------|-------|-----------------------|
| 0 | Miss | | 0 |
| 1 | Miss | | 0,1 |
| 2 | Miss | | 0,1,2 |
| 0 | Hit | | 1,2,0 |
| 1 | Hit | | 2,0,1 |
| 3 | Miss | 2 | 0,1,3 |
| 0 | Hit | | 1,3,0 |
| 3 | Hit | | 1,0,3 |
| 1 | Hit | | 0,3,1 |
| 2 | Miss | 0 | 3,1,2 |
| 1 | Hit | | 3,2,1 |


Workload Example: The No-Locality Workload

- Each reference is to a random page in a set of 100 pages
 - Workload has 100 accesses over time.
 - Choosing the next page to refer to at random




Workload Example: The 80-20 Workload

- Exhibits locality: 80% of the reference are made to 20% of the page
- The remaining 20% of the reference are made to the remaining 80% of the pages.




Workload Example : The Looping Sequential

- Refer to 50 pages in sequence.
 - Starting at 0, then 1, ... up to page 49, and then we loop, repeating those accesses, for total of 10,000 accesses to 50 unique pages.




Approximating LRU: Clock Algorithm

- Require hardware support: <u>use bit</u>
 - Whenever a page is referenced, the use bit is set by hardware to 1.
 - Hardware never clears the bit, though; that is the responsibility of the OS
- Clock Algorithm
 - All pages of the system arranges in a circular list.
 - A clock hand points to a page to begin with.
 - The algorithm continues until it finds a use bit that is set to 0.



Workload with Clock Algorithm

Clock algorithm doesn't do as well as perfect LRU; it does better then approach that don't consider history at all.




Considering Dirty Pages


- □ The hardware includes a **modified bit** (a.k.a **dirty bit**)
 - Page has been **modified** and is thus **dirty**, it must be written back to disk to evict it.
 - Page has not been modified; the eviction is free.

Prefetching

The OS guesses that a page is about to be used, and thus bring it in ahead of time.




Physical Memory



Page 2 likely soon be accessed and thus should be brought into memory too


Clustering, Grouping

- Collect a number of pending writes together in memory and write them to disk in one write.
 - Perform a <u>single large write</u> more efficiently than <u>many small ones</u>.



Thrashing

- Memory is oversubscribed and the memory demands of the set of running processes exceeds the available physical memory.
 - Decide not to run a subset of processes.
 - Reduced set of processes working sets fit in memory.



Summary

- Swapping: use part of disk as memory
- Page replacement (page/swap out, page/swap in)
 - LRU, LFU, Random, FIFO
- Approximation to LRU: Clock
- Batching the disk IO
 - Clustering
 - Grouping
 - Prefetching