1.智能指针

在C<u>11之后尽量不要再用new 和 delete,用智能指针; C</u>11 之前可以用boost智能指针,大部分新标准都来源于boost;

智能指针分类:

1. std::shared_ptr (boost::shared_ptr) 这个用的最多,就是可以共享所有权,每增加一个所有这,智能指针计数加1,放弃所有权,计数减1;计数为0释放:

```
#include <iostream>
#include <memory>
#include <thread>
#include <chrono>
#include <mutex>
struct Base
    Base() { std::cout << " Base::Base()\n"; }</pre>
    // 注意: 此处非虚析构函数 OK
    ~Base() { std::cout << " Base::~Base()\n"; }
};
struct Derived: public Base
    Derived() { std::cout << " Derived::Derived()\n"; }</pre>
    ~Derived() { std::cout << " Derived::~Derived()\n"; }
};
void thr(std::shared_ptr<Base> p)
    std::this_thread::sleep_for(std::chrono::seconds(1));
    std::shared_ptr<Base> lp = p; // 线程安全, 虽然自增共享的 use_count
        static std::mutex io_mutex;
        std::lock guard<std::mutex> lk(io mutex);
        std::cout << "local pointer in a thread:\n"</pre>
                 << " lp.get() = " << lp.get()
                 << ", lp.use_count() = " << lp.use_count() << '\n';</pre>
    }
}
int main()
```

std::unique_ptr (boost::unique_ptr)
 独享,可以传递所有权,A传递给B,A必须失去所有权std::move(p);

```
// 消费 unique ptr 的函数能以值或以右值引用接收它
std::unique_ptr<D> pass_through(std::unique_ptr<D> p)
{
   p->bar();
   return p;
}
void close_file(std::FILE* fp) { std::fclose(fp); }
int main()
 std::cout << "unique ownership semantics demo\n";</pre>
 {
     auto p = std::make_unique<D>(); // p 是占有 D 的 unique_ptr
     auto q = pass_through(std::move(p)); //交给其他人了
     assert(!p); // 现在 p 不占有任何内容并保有空指针
     q->bar(); // 而 q 占有 D 对象
 } // ~D 调用于此
}
```

3. std::weak_ptr (boost::weak_ptr) shared_ptr的伴生指针,不能独立存在;从 shared_ptr中构造,但是不影响shared_ptr的引用计数;在需要使用的时候,需要升级为shared_ptr、避免被释放;

```
#include <iostream>
#include <memory>
std::weak_ptr<int> gw;
void f()
    if (auto spt = gw.lock()) { // 使用之前必须复制到 shared_ptr
    std::cout << *spt << "\n";</pre>
    }
    else {
       std::cout << "gw is expired\n";</pre>
    }
}
int main()
{
        auto sp = std::make_shared<int>(42);
    gw = sp;
   f();
   f();
}
```

4. boost::scope_ptr 和std::unique_ptr类似,但是不可以转移所有权,必须持有到释放;

```
#include <boost/scoped_ptr.hpp>
#include <iostream>
```

```
struct Shoe { ~Shoe() { std::cout << "Buckle my shoe\n"; } };

class MyClass {
   boost::scoped_ptr<int> ptr;
   public:
       MyClass() : ptr(new int) { *ptr = 0; }
       int add_one() { return ++*ptr; }
};

int main()
{
       {
            boost::scoped_ptr<Shoe> x(new Shoe);
       } // 此处会释放
       MyClass my_instance;
       std::cout << my_instance.add_one() << '\n';
       std::cout << my_instance.add_one() << '\n';
}</pre>
```

5. std::auto_ptr 这是个设计缺陷,任何时候都不要用。