A. Definition by columns

1. General commands

To insert an instruction, press enter on the cell. Press delete to remove it.

2. Line number

This shows the line number:



3. Note



Keys:

- Enter to set a new note
    - Letter key (for example, C for a C note)
    - Number key (to select the number in the note name (for example, if you have C-0, press 2 to obtain C-2).
        - **Note:** The octave must allow the notes (explained in the section for octave)
    - Sharp key / S key to make a sharp note. Use S if the Sharp key doesn't work.
    - Dash key / M key to remove the sharp from the note. Use M if the Dash key doesn't work.
    - Space to insert a break

- Insert to insert a Silent Line

. The silent is useful order of other instruction on the line is important. By default, everything on the line is done from left to right (except the note, it is done after all the instructions on the line). For example, Volume Command is executed before the Instrument Command. If Instrument Command would need to be done first for a reason, make a Silent Line with the Instrument Command then on the next line make the Volume Command:

4. Vol. – Ins.

Volume and Instrument

Press any number digit to set them. Values are in hexadecimal, so letter A B C D E F can be used.

Volume is maxed at 0F.

Instrument are ID that refers to instruments in the engine. They can't be changed, so trying them to understanding them is the way to go. To edit the second digit, hold shift while pressing a number.

5. Oct.

Octave set determine which note can be played on the current line and all the following up to the next Octave command. Here are the playable notes with an octave of 0:

```
C-0
C#0
D-0
D#0
E-0
F-0
F#0
G-0
G#0
A-0
A#0
B-0

C-1
C#1
D-1
D#1
E-1
F-1
F#1
G-1
G#1
A-1
A#1
B-1

C-2
C#2
D-2
D#2
E-2
F-2
F#2
```

For every increment that is made to the octave, every note in the list can be incremented by 1.

6. Lgt. - Ptc. - Sld.

Those values are edited the same way as the Instrument.

Lgt. is for Tone Length: Set Note hold length (Time of Key off)

Ptc. is for Tune Pitch: Default: 00. 01 to 7F is higher. FF to 80 is lower

Sld. is for Note Slide: Can be used to set the transition speed for the portamento slide. Values range from: 00(slowest) to FF(fastest)

It can be used in combination with Con. (Connect) to make the note slides sound smoother.

7. Dty Cyc

Value is edited the same way as the Instrument.

Dty Cyc is for Duty Cycle: Press enter to toggle between the possible values.

8. Spd

Spd is for speed. It has 4 digits (which are split in 2 box of 2 digits).

Value is edited the same way as the Instrument.

9. Trs. – Glb.

Value are edited the same way as the Instrument.

Trs. is for Transpose

Glb. is for Global Transpose (transpose all channels)

Transpose values: Default: 00. 01 to 7F is higher. FF to 80 is lower.

10. Con.

First, this command is one that toggles. When the song plays, every time the music engine will see this column set (TOG is then written for this column), it will toggle the value. It is first off.

By Toggling (TOG) function in the Con. column you can activate the automatic slide generator for the channel.

It creates a subtle slide effect for all the notes that are toggled on.

The Con. toggle can be used in combination with the Sld. column by entering values for the slide speed.

This can make your slide notes sound a lot smoother.

Note:

- It is recommended to add the Toggles as the final step, this will preserve the layout/structure of your track.

- When you will read a song you created, some TOG may appear. This is because the music engine only has simple commands for note that last either 1 line, 2 lines, 4 lines, 8 lines, 16 lines, 32 lines or 64 lines. Every note that is not using this length is build by “Connecting” those lengths together or using a command that multiplies one of those lengths by 1.5 (so we can have 3 lines, 6 lines, 12 lines, 24 lines, 48 lines, 96 lines). If a sheet has a Note that last 7 lines like this:

	Note	Vol.	Ins.	Oct.	Len	Ptc.	Sld.	Dty Cyc	Spd		Trs.	Glb.	Flq	Trip.	Con.	Oct.+2
0	C-0	0F	00	00	--	--	--	-----	05	00	--	--	--	---	---	---
1	---	--	--	--	--	--	--	-----	--	--	--	--	--	---	---	---
2	---	--	--	--	--	--	--	-----	--	--	--	--	--	---	---	---
3	---	--	--	--	--	--	--	-----	--	--	--	--	--	---	---	---
4	---	--	--	--	--	--	--	-----	--	--	--	--	--	---	---	---
5	---	--	--	--	--	--	--	-----	--	--	--	--	--	---	---	---
6	---	--	--	--	--	--	--	-----	--	--	--	--	--	---	---	---

When this is inserted in the ROM/NSF, the program has to make this note play for 7 lines, so what it do is it will connect a C-0 that lasts 6 lines, then one that lasts 1 line. You will then see this when reading the song again:

	Note	Vol.	Ins.	Oct.	Len	Ptc.	Sld.	Dty Cyc	Spd		Trs.	Glb.	Flq	Trip.	Con.	Oct.+2
0	C-0	0F	00	00	--	--	--	-----	05	00	--	--	--	---	TOG	---
1	---	--	--	--	--	--	--	-----	--	--	--	--	--	---	---	---
2	---	--	--	--	--	--	--	-----	--	--	--	--	--	---	---	---
3	---	--	--	--	--	--	--	-----	--	--	--	--	--	---	---	---
4	---	--	--	--	--	--	--	-----	--	--	--	--	--	---	---	---
5	---	--	--	--	--	--	--	-----	--	--	--	--	--	---	---	---
6	C-0	--	--	--	--	--	--	-----	--	--	--	--	--	---	TOG	---
7	///	--	--	--	--	--	--	-----	--	--	--	--	--	---	---	---

Note: Connect is always toggled on the same line as a note.

11. Flg – Trip. – Oct.+2

Values are to be used only by user who knows what they are doing. Everything those command does can be done another way.