ENECHNAGE Go-Challenge Interface Specification Document

Glossary

| Term | Description | | | |
|----------|---|--|--|--|
| СРО | charging Point Operator | | | |
| EV | Electric Vehicle. | | | |
| EVSE | Electric Vehicle Supply Equipment. Is considered as an independently operated and managed part of a Charge Point that can deliver energy to one EV at a time. | | | |
| Location | The Location objects live in the CPO back-end system. They describe the charging locations of an operator. | | | |

Cardinality

| Symbol | Description | Туре |
|--------|--|----------|
| ? | An optional object. If not set, the field should be omitted. | Object |
| 1 | Required object | Object |
| * | A list of zero or more objects. If empty, the field should be omitted. | [Object] |
| + | A list of at least one object. | [Object] |

Endpoint

Locations Endpoint

We offer the Locations endpoint, which allows you to fetch a list of locations within a circular area defined by a specified {latitude}, {longitude}, and {radius}.

URI

api/locations?[latitude={latitude}]&[longitude={longitude}]&[radius=
{radius}]&[date_from={date_from}]&[date_to={date_to}]

Request Method

GET

Request Parameters


| Parameter | Datatype | Requ ired | Description in OCPI |
|-----------|------------|--------------|--|
| latitude | string(11) | yes | Latitude of the point in decimal degree. Example: 50.770774. Decimal separator: "." Regex: -?[0-9]{1,2}\.[0-9]{5,7} |
| longitude | string(12) | yes | Longitude of the point in decimal degree. Example: -126.104965. Decimal separator: "." Regex: -?[0-9]{1,3}\.[0-9]{5,7} |
| radius | int | no | Search radius from latitude and longitude. Unit: km. If not specified, the default will be set to 100 km. |

Response Data

| Туре | Card. | Description |
|----------|-------|---|
| Location | * | List of all Locations with valid EVSEs. |

Object description

Location and EVSE have the following relation.



Location object

| Property | Data Type | Card. | Description |
|-----------------|-------------|-------|--|
| id | string(36) | 1 | Unique ID of the Location |
| name | string(255) | ? | Name of the Location |
| address | string(45) | 1 | Address of the Location |
| coordinat es | GeoLocation | 1 | Coordinates object containing latitude and longitude |
| evses | <u>EVSE</u> | * | Array of EVSE objects. An EVSE represents a charger connected to a charging station. |

EVSE object

| Property | Data Type | Card. | Description |
|----------|------------|-------|--|
| | | | |
| uid | string(36) | 1 | Unique identifier of the EVSE within the CPO's platform. |
| status | Status | 1 | Current status of the EVSE, such as "AVAILABLE", "BLOCKED", "CHARGING", etc. |

Data types

GeoLocation class

| Property | Data Type | Card. | Description |
|-----------|------------|-------|--|
| latitude | string(11) | 1 | Latitude of the point in decimal degree. Example: 50.770774. Decimal separator: "." Regex: -?[0-9]{1,2}\.[0-9]{5,7} |
| longitude | string(12) | 1 | Longitude of the point in decimal degree. Example: -126.104965. Decimal separator: "." Regex: -?[0-9]{1,3}\.[0-9]{5,7} |

Status enum

| Value | Value on DataBase | Description |
|-------------|----------------------|---|
| AVAILABLE | 1 | AVAILABLE The EVSE/Connector is able to start a new charging session. |
| BLOCKED | 2 | The EVSE/Connector is not accessible because of a physical barrier, i.e. a car. |
| CHARGING | 3 | The EVSE/Connector is in use. |
| INOPERATIVE | 4 | The EVSE/Connector is not yet active, or temporarily not |

| | | available for use, but not broken or defect. |
|------------|---|---|
| OUTOFORDER | 5 | The EVSE/Connector is currently out of order, some part/components may be broken/defect. |
| PLANNED | 6 | The EVSE/Connector is planned, will be operating soon. |
| REMOVED | 7 | The EVSE/Connector was discontinued/removed. |
| RESERVED | 8 | The EVSE/Connector is reserved for a particular EV driver and is unavailable for other drivers. |
| UNKNOWN | 9 | No status information available (also used when offline). |