
Operating
Systems:
Internals
and Design
Principles

### Chapter 8 Virtual Memory

Seventh Edition William Stallings

#### Operating Systems: Internals and Design Principles

You're gonna need a bigger boat.



— Steven Spielberg, JAWS, 1975

#### Hardware and Control Structures

- Two characteristics fundamental to memory management:
  - 1) all memory references are logical addresses that are dynamically translated into physical addresses at run time
  - 2) a process may be broken up into a number of pieces that don't need to be contiguously located in main memory during execution
- If these two characteristics are present, it is not necessary that all of the pages or segments of a process be in main memory during execution

# **Terminology**

Virtual memory	A storage allocation scheme in which secondary memory can be addressed as though it were part of main memory. The addresses a program may use to reference memory are distinguished from the addresses the memory system uses to identify physical storage sites, and program-generated addresses are translated automatically to the corresponding machine addresses. The size of virtual storage is limited by the addressing scheme of the computer system, and by the amount of secondary memory available and not by the actual number of main storage locations.	
Virtual address	al address  The address assigned to a location in virtual memory to allow that location to be accessed as though it were part of main memory.	
Virtual address space	l address space The virtual storage assigned to a process.	
Address space	ace The range of memory addresses available to a process.	
Real address	The address of a storage location in main memory.	

#### Execution of a Process

- Operating system brings into main memory a few pieces of the program
- Resident set portion of process that is in main memory
- An interrupt is generated when an address is needed that is not in main memory
- Operating system places the process in a blocking state

Continued . .

#### Execution of a Process

- Piece of process that contains the logical address is brought into main memory
  - operating system issues a disk I/O Read request
  - another process is dispatched to run while the disk I/O takes place
  - an interrupt is issued when disk I/O is complete, which causes the operating system to place the affected process in the Ready state

### **Implications**

- More processes may be maintained in main memory
  - only load in some of the pieces of each process
  - with so many processes in main memory, it is very likely a process will be in the Ready state at any particular time
- A process may be larger than all of main memory



# Real and Virtual Memory

#### Real memory

main memory, the actual RAM



#### Virtual memory

- memory on disk
- allows for effective multiprogramming and relieves the user of tight constraints of main memory

#### Characteristics of Paging and Segmentation

AND PROPERTY.	Simple Paging	Virtual Memory Paging	Simple Segmentation	Virtual Memory Segmentation			
	Main memory partitioned chunks called frames.	into small fixed-size	Main memory not partitioned.				
TELEGROPHICS IN	Program broken into pages memory management syste	*	Program segments specified by the programmer to the compiler (i.e., the decision is made by the programmer).				
	Internal fragmentation wit	Internal fragmentation within frames.		No internal fragmentation.			
Š	No external fragmentation		External fragmentation.				
	Operating system must maintain a page table for each process showing which frame each page occupies.		Operating system must maintain a segment table for each process showing the load address and length of each segment.				
TREASON.	Operating system must maintain a free-frame list.  Processor uses page number, offset to calculate absolute address.		Operating system must maintain a list of free holes in main memory.				
			Processor uses segment number, offset to calculate absolute address.				
STATE OF THE PARTY	All the pages of a process must be in main memory for process to run, unless overlays are used.	Not all pages of a process need be in main memory frames for the process to run. Pages may be read in as needed.	All the segments of a process must be in main memory for process to run, unless overlays are used.	Not all segments of a process need be in main memory for the process to run. Segments may be read in as needed.			
		Reading a page into main memory may require writing a page out to disk.		Reading a segment into main memory may require writing one or more segments out to disk.			

#### **Thrashing**


A state in which the system spends most of its time swapping process pieces rather than executing instructions To avoid this, the operating system tries to guess, based on recent history, which pieces are least likely to be used in the near future

#### Principle of Locality

- Program and data references within a process tend to cluster
- Only a few pieces of a process will be needed over a short period of time
- Therefore it is possible to make intelligent guesses about which pieces will be needed in the future
- Avoids thrashing



### Paging Behavior



 During the lifetime of the process, references are confined to a subset of pages

# Support Needed for Virtual Memory

#### For virtual memory to be practical and effective:

- hardware must support paging and segmentation
- operating system must include software for managing the movement of pages and/or segments between secondary memory and main memory

#### **Paging**

- The term *virtual memory* is usually associated with systems that employ paging
- Use of paging to achieve virtual memory was first reported for the Atlas computer
- Each process has its own page table
  - each page table entry contains the frame number of the corresponding page in main memory



# Virtual Address Page Number Offset Page Table Entry PMOther Control Bits Frame Number

(a) Paging only

# Memory Management Formats

P= present bit

M = Modified bit


STATE OF THE PARTY OF	SECULIO NE								
Virtual Address									
Segment Number	amber Offset				1				
Segment Table Entry									
PMOther Control Bits									
(b) Segmentation only									
	Virtual Address								
Se		nent Number	Page	Number	Offset				
Segment Table Entry									
	Con	trol Bits	Length	Segm	ent Base				
	Page T	Page Table Entry							

Frame Number

(c) Combined segmentation and paging

PMOther Control Bits

#### **Address Translation**



# Two-Level Hierarchical Page Table





Figure 8.4 A Two-Level Hierarchical Page Table

#### **Address Translation**




#### Inverted Page Table

- Page number portion of a virtual address is mapped into a hash value
  - hash value points to inverted page table
- Fixed proportion of real memory is required for the tables regardless of the number of processes or virtual pages supported
- Structure is called *inverted* because it indexes page table entries by frame number rather than by virtual page number



### Inverted Page Table



#### Inverted Page Table

Each entry in the page table includes:

Page number

Process identifier

 the process that owns this page

#### Control bits

includes
 flags and
 protection
 and locking
 information

#### Chain pointer


 the index value of the next entry in the chain


# Translation Lookaside Buffer (TLB)

- Each virtual memory reference can cause two physical memory accesses:
  - one to fetch the page table entry
  - one to fetch the data

To overcome the effect of doubling the memory access time, most virtual memory schemes make use of a special high-speed cache called a *translation lookaside buffer* 

#### Use of a TLB






# TLB Operation


Figure 8.8 Operation of Paging and Translation Lookaside Buffer (TLB) [FURH87]

## Associative Mapping


- The TLB only contains some of the page table entries so we cannot simply index into the TLB based on page number
  - each TLB entry must include the page number as well as the complete page table entry
- The processor is equipped with hardware that allows it to interrogate simultaneously a number of TLB entries to determine if there is a match on page number




# Direct Versus Associative Lookup



#### TLB and Cache Operation




# TLB and Cache Operation



### Page Size

- The smaller the page size, the lesser the amount of internal fragmentation
  - however, more pages are required per process
  - more pages per process means larger page tables
  - for large programs in a heavily multiprogrammed environment some portion of the page tables of active processes must be in virtual memory instead of main memory
  - the physical characteristics of most secondary-memory devices favor a larger page size for more efficient block transfer of data

### Paging Behavior of a Program



P = size of entire process

W = working set size

N =total number of pages in process

Figure 8.11 Typical Paging Behavior of a Program

N

# Example: Page Sizes

Computer	Page Size
Atlas	512 48-bit words
Honeywell-Multics	1,024 36-bit words
IBM 370/XA and 370/ESA	4 kB
VAX family	512 bytes
IBM AS/400	512 bytes
DEC Alpha	8 kB
MIPS	4 kB to 16 MB
UltraSPARC	8 kB to 4 MB
Pentium	4 kB or 4 MB
Intel Itanium	4 kB to 256 MB
Intel core i7	4 kB to 1 GB

# Page Size

The design issue of page size is related to the size of physical main memory and program size



main memory is getting larger and address space used by applications is also growing

 Contemporary programming techniques used in large programs tend to decrease the locality of references within a process



most obvious on personal computers where applications are becoming increasingly complex

#### Segmentation


 Segmentation allows the programmer to view memory as consisting of multiple address spaces or segments

#### Advantages:


- simplifies handling of growing data structures
- allows programs to be altered and recompiled independently
- lends itself to sharing data among processes
- lends itself to protection

# Segment Organization

- Each segment table entry contains the starting address of the corresponding segment in main memory and the length of the segment
- A bit is needed to determine if the segment is already in main memory
- Another bit is needed to determine if the segment has been modified since it was loaded in main memory



#### **Address Translation**




# Combined Paging and Segmentation

In a combined paging/segmentation system a user's address space is broken up into a number of segments. Each segment is broken up into a number of fixed-sized pages which are equal in length to a main memory frame

Segmentation is visible to the programmer

Paging is transparent to the programmer

#### **Address Translation**



# Combined Segmentation and Paging

Virtual Address

Segment Number Page Number Offset

Segment Table Entry

Control Bits Length Segment Base

Page Table Entry

PMOther Control Bits Frame Number

P= present bit
M = Modified bit

(c) Combined segmentation and paging

## Protection and Sharing

- Segmentation lends itself to the implementation of protection and sharing policies
- Each entry has a base address and length so inadvertent memory access can be controlled
- Sharing can be achieved by segments referencing multiple processes

#### Protection Relationships






Figure 8.14 Protection Relationships Between Segments

## Operating System Software

The design of the memory management portion of an operating system depends on three fundamental areas of choice:

- whether or not to use virtual memory techniques
- the use of paging or segmentation or both
- the algorithms employed for various aspects of memory management

#### Policies for Virtual Memory

- Key issue: Performance
  - minimize page faults

#### **Fetch Policy**

Demand paging Prepaging

#### **Placement Policy**

#### **Replacement Policy**

Basic Algorithms

Optimal

Least recently used (LRU)

First-in-first-out (FIFO)

Clock

Page Buffering

#### **Resident Set Management**

Resident set size

Fixed

Variable

Replacement Scope

Global

Local

#### **Cleaning Policy**

Demand

Precleaning

#### **Load Control**

Degree of multiprogramming

### **Fetch Policy**

Determines when a page should be brought into memory

Two main types:



Demand Paging

Prepaging

# Demand Paging

#### Demand Paging

- only brings pages into main memory when a reference is made to a location on the page
- many page faults when process is first started
- principle of locality suggests that as more and more pages are brought in, most future references will be to pages that have recently been brought in, and page faults should drop to a very low level



#### Prepaging

#### Prepaging

- pages other than the one demanded by a page fault are brought in
- exploits the characteristics of most secondary memory devices
- if pages of a process are stored contiguously in secondary memory it is more efficient to bring in a number of pages at one time
- ineffective if extra pages are not referenced
- should not be confused with "swapping"

### **Placement Policy**

- Determines where in real memory a process piece is to reside
- Important design issue in a segmentation system
- Paging or combined paging with segmentation placing is irrelevant because hardware performs functions with equal efficiency
- For NUMA systems an automatic placement strategy is desirable

# Replacement Policy

- Deals with the selection of a page in main memory to be replaced when a new page must be brought in
  - objective is that the page that is removed be the page least likely to be referenced in the near future
- The more elaborate the replacement policy the greater the hardware and software overhead to implement it

### Frame Locking

- When a frame is locked the page currently stored in that frame may not be replaced
  - kernel of the OS as well as key control structures are held in locked frames
  - I/O buffers and time-critical areas may be locked into main memory frames
  - locking is achieved by associating a lock bit with each frame



#### **Basic Algorithms**




Algorithms used for the selection of a page to replace:

- Optimal
- Least recently used (LRU)
- First-in-first-out (FIFO)
- Clock

## **Optimal Policy**

- Selects the page for which the time to the next reference is the longest
- Produces three page faults after the frame allocation has been filled




F= page fault occurring after the frame allocation is initially filled

Figure 8.15 Behavior of Four Page Replacement Algorithms

# Least Recently Used (LRU)

- Replaces the page that has not been referenced for the longest time
- By the principle of locality, this should be the page least likely to be referenced in the near future
- Difficult to implement
  - one approach is to tag each page with the time of last reference
    - this requires a great deal of overhead

### LRU Example



F= page fault occurring after the frame allocation is initially filled


Figure 8.15 Behavior of Four Page Replacement Algorithms

## First-in-First-out (FIFO)

- Treats page frames allocated to a process as a circular buffer
- Pages are removed in round-robin style
  - simple replacement policy to implement
- Page that has been in memory the longest is replaced



### FIFO Example




F= page fault occurring after the frame allocation is initially filled


Figure 8.15 Behavior of Four Page Replacement Algorithms

## Clock Policy

- Requires the association of an additional bit with each frame
  - referred to as the use bit
- When a page is first loaded in memory or referenced, the use bit is set to 1
- The set of frames is considered to be a circular buffer
- Any frame with a use bit of 1 is passed over by the algorithm
- Page frames visualized as laid out in a circle




# Clock Policy Example




F= page fault occurring after the frame allocation is initially filled

Figure 8.15 Behavior of Four Page Replacement Algorithms



#### (a) State of buffer just prior to a page replacement

# Clock Policy



(b) State of buffer just after the next page replacement

Figure 8.16 Example of Clock Policy Operation

### Comparison of Algorithms






Figure 8.17 Comparison of Fixed-Allocation, Local Page Replacement Algorithms



# Clock Policy

Figure 8.18 The Clock Page-Replacement Algorithm [GOLD89]

### Combined Examples




F= page fault occurring after the frame allocation is initially filled

Figure 8.15 Behavior of Four Page Replacement Algorithms

### Page Buffering

Improves paging performance and allows the use of a simpler page replacement policy



#### Replacement Policy and Cache Size

- With large caches, replacement of pages can have a performance impact
  - if the page frame selected for replacement is in the cache, that cache block is lost as well as the page that it holds
  - in systems using page buffering, cache performance can be improved with a policy for page placement in the page buffer
  - most operating systems place pages by selecting an arbitrary page frame from the page buffer

### Resident Set Management

- The OS must decide how many pages to bring into main memory
  - the smaller the amount of memory allocated to each process, the more processes can reside in memory
  - small number of pages loaded increases page faults
  - beyond a certain size, further allocations of pages will not effect the page fault rate



#### Resident Set Size

#### Fixed-allocation

- gives a process a fixed number of frames in main memory within which to execute
  - when a page fault occurs, one of the pages of that process must be replaced

#### Variable-allocation

 allows the number of page frames allocated to a process to be varied over the lifetime of the process

#### Replacement Scope

- The scope of a replacement strategy can be categorized as *global* or *local* 
  - both types are activated by a page fault when there are no free page frames

#### Local

• chooses only among the resident pages of the process that generated the page fault

#### Global

• considers all unlocked pages in main memory

### Resident Set Management Summary

#### **Fixed Allocation**

#### **Variable Allocation**

Local Replacement	Global Replacement
<ul> <li>Number of frames allocated to a process is fixed.</li> <li>Page to be replaced is chosen from among the frames allocated to that process.</li> </ul>	Not possible.
<ul> <li>The number of frames allocated to a process may be changed from time to time to maintain the working set of the process.</li> <li>Page to be replaced is chosen from among the frames allocated to that process.</li> </ul>	<ul> <li>Page to be replaced is chosen from all available frames in main memory; this causes the size of the resident set of processes to vary.</li> </ul>

#### Fixed Allocation, Local Scope

- Necessary to decide ahead of time the amount of allocation to give a process
- If allocation is too small, there will be a high page fault rate

If allocation is too large, there will be too few programs in main memory

- increased processor idle time
- increased time spent in swapping

# Variable Allocation Global Scope

- Easiest to implement
  - adopted in a number of operating systems
- OS maintains a list of free frames
- Free frame is added to resident set of process when a page fault occurs
- If no frames are available the OS must choose a page currently in memory
- One way to counter potential problems is to use page buffering

# Variable Allocation Local Scope

- When a new process is loaded into main memory, allocate to it a certain number of page frames as its resident set
- When a page fault occurs, select the page to replace from among the resident set of the process that suffers the fault
- Reevaluate the allocation provided to the process and increase or decrease it to improve overall performance

# Variable Allocation Local Scope

 Decision to increase or decrease a resident set size is based on the assessment of the likely future demands of active processes

#### Key elements:

- criteria used to determine resident set size
- the timing of changes

# Page Fault Frequency (PFF)

- Requires a use bit to be associated with each page in memory
- Bit is set to 1 when that page is accessed
- When a page fault occurs, the OS notes the virtual time since the last page fault for that process
- Does not perform well during the transient periods when there is a shift to a new locality

# Variable-interval Sampled Working Set (VSWS)

- Evaluates the working set of a process at sampling instances based on elapsed virtual time
- Driven by three parameters:

the minimum duration of the sampling interval

the maximum duration of the sampling interval

the number of page faults that are allowed to occur between sampling instances

## Cleaning Policy

 Concerned with determining when a modified page should be written out to secondary memory

#### Demand Cleaning

a page is written out to secondary memory only when it has been selected for replacement




#### Precleaning

allows the writing of pages in batches

#### Load Control

- Determines the number of processes that will be resident in main memory
  - multiprogramming level
- Critical in effective memory management
- Too few processes, many occasions when all processes will be blocked and much time will be spent in swapping
- Too many processes will lead to thrashing



# Multiprogramming




Figure 8.21 Multiprogramming Effects

## Process Suspension

■ If the degree of multiprogramming is to be reduced, one or more of the currently resident processes must be swapped out

#### Six possibilities exist:

- Lowest-priority process
- Faulting process
- Last process activated
- Process with the smallest resident set
- Largest process
- Process with the largest remaining execution window

### Summary

- Desirable to:
  - maintain as many processes in main memory as possible
  - free programmers from size restrictions in program development
- With virtual memory:
  - all address references are logical references that are translated at run time to real addresses
  - a process can be broken up into pieces
  - two approaches are paging and segmentation
  - management scheme requires both hardware and software support