

Enterprise Network: DHCP, DNS e Web Server

Switch Multilayer 0-3:

```
vlan 100
name SERVERS
interface range fastEthernet 0/1-3, gigaBitEthernet 0/2
switchport mode trunk
switchport trunk allowed vlan add 100
```

Multilayer 0:

```
inter vlan 100
ip address 192.168.100.2 255.255.255.0
standby 100 ip 192.168.100.1
standby 100 priority 210
standby 100 preempt
no shutdown
```

```
interface fastEthernet 0/24
switchport mode access
switchport access vlan 100
```

```
router ospf 1
network 192.168.100.0 0.0.0.255 area 0
passive-interface vlan 100
```

```
inter vlan 10
ip helper-address 192.168.100.10
```

```
inter vlan 20
ip helper-address 192.168.100.10
```

```
inter vlan 30
ip helper-address 192.168.100.10
```

Multilayer 1:

```
inter vlan 100
ip address 192.168.100.3 255.255.255.0
standby 100 ip 192.168.100.1
standby 100 priority 200
standby 100 preempt
no shutdown
```

```
router ospf 1
network 192.168.100.0 0.0.0.255 area 0
```

passive-interface vlan 100

inter vlan 10

ip helper-address 192.168.100.10

inter vlan 20

ip helper-address 192.168.100.10

inter vlan 30

ip helper-address 192.168.100.10

Multilayer 2:

inter vlan 100

ip address 192.168.110.2 255.255.255.0

standby 100 ip 192.168.110.1

standby 100 priority 210

standby 100 preempt

no shutdown

router ospf 1

network 192.168.110.0 0.0.0.255 area 0

passive-interface vlan 100

Multilayer 3:

inter vlan 100

ip address 192.168.110.3 255.255.255.0

standby 100 ip 192.168.110.1

standby 100 priority 200

standby 100 preempt

no shutdown

router ospf 1

network 192.168.110.0 0.0.0.255 area 0

passive-interface vlan 100

switch 0-5:

interface range fastEthernet 0/1-2

switchport mode trunk

switchport trunk allowed vlan add 100

Server:

IP Configuration Static: 192.168.100.10 255.255.255.0

Settings:

Default Gateway: 192.168.100.1

DNS Server: 192.168.100.10

DHCP:

Pool Name: P1-HR

Default Gateway: 192.168.10.1

DNS Server: 192.168.100.10

Start IP Address: 192.168.10.100

Subnet Mask: 255.255.255.0

Maximum Number of Users: 100

Pool Name: P1-Sales

Default Gateway: 192.168.20.1

DNS Server: 192.168.100.10

Start IP Address: 192.168.20.100

Subnet Mask: 255.255.255.0

Maximum Number of Users: 100

Pool Name: P1-FINANCE

Default Gateway: 192.168.30.1

DNS Server: 192.168.100.10

Start IP Address: 192.168.30.100

Subnet Mask: 255.255.255.0

Maximum Number of Users: 100

Pool Name: P2-HR

Default Gateway: 192.168.40.1

DNS Server: 192.168.100.10

Start IP Address: 192.168.40.100

Subnet Mask: 255.255.255.0

Maximum Number of Users: 100

Pool Name: P2-SALES

Default Gateway: 192.168.50.1

DNS Server: 192.168.100.10

Start IP Address: 192.168.50.100

Subnet Mask: 255.255.255.0

Maximum Number of Users: 100

Pool Name: P2-FINANCE

Default Gateway: 192.168.60.1

DNS Server: 192.168.100.10
Start IP Address: 192.168.60.100
Subnet Mask: 255.255.255.0
Maximum Number of Users: 100

DNS:

Name: compania.local
Address: 192.168.100.10

HTTP:

Edit index

```
<html>

<head>
<title>Enterprise Headquarters</title>
</head>

<body bgcolor="white">

<center>
<h1>Enterprise Headquarters</h1>
<h3>Network Services Portal</h3>
</center>

<hr>

<p><b>Server Status:</b> Online</p>

<p>Services Available:</p>

<ul>
  <li>DHCP Server</li>
  <li>DNS Server</li>
  <li>Web Server</li>
</ul>

<p>Network: 192.168.100.0/24</p>

<p>Welcome to the Enterprise Network Lab built in Cisco Packet Tracer.</p>

</body>

</html>
```