T **TechPlug POS**

TechPlug (Pvt) Ltd
techplug.co.zw

RESTAURANT GUIDE

How your restaurant system works

Every screen and menu, step by step — from the first sale of the day to reports, online orders and your plan.

Works offline · USD · ZiG · ZAR · Kitchen screen · QR menu & online orders · Branches

FOR
Restaurant owners, managers, cashiers and kitchen staff

VERSION
1.0 · November 2026

OPEN THE SYSTEM
pos.techplug.co.zw

HELP
TechPlug on WhatsApp (number in Settings → Plan & payments)

CONTENTS

What is in this guide

1	Summary	What the system does and what you need
2	Getting started	Set-up, connecting tills, PINs and staff roles
3	Selling	Taking an order, payment, change, numbers, cancelling
4	Kitchen, orders and tables	The kitchen screen, open orders, table service
5	Every screen	What each menu item on the left is for
6	Stock, reports and books	Knowing what you sold, what you used and what you made
7	Your web page, QR menu and online orders	Pick-up and delivery from customers' phones
8	Settings	Every settings tab explained
9	Account, plan and safety	My account, paying TechPlug, backups, branches
10	Daily checklist and problems	Opening, closing and quick fixes

HOW TO READ THIS GUIDE

Screens are shown as they look on a till. Words in **bold** are buttons or menu names exactly as you will see them. Yellow boxes are things to remember, green boxes are tips, red boxes are warnings.

SUMMARY

1 What TechPlug POS does

TechPlug POS runs the front of your restaurant: the till, the kitchen screen, tables, change in several currencies, stock, your books, staff with their own PINs, and a free web page with a QR menu where customers can order from their phones.

It keeps working when the internet goes down. Every sale is saved on the till first and copied to your online account as soon as there is a connection, so the owner can see the day's sales from home and a broken till never loses the restaurant's records.




Figure 1. *How the parts connect. The till works on its own; the online account keeps every device and the owner's phone up to date.*

Counter

Sell, take payment in USD, ZiG or Rand, give change in any of them, and hand over an order number.

Kitchen

Orders appear on the kitchen screen with a timer. The cook taps **Done** and the counter knows it is ready.

Owner

Reports, books, stock and staff from any phone or computer — and branches if you have more than one shop.

What you need

Item	Details
A till	Any Windows computer (install the TechPlug POS app) or a tablet/phone with Chrome. Open **pos.techplug.co.zw**.
A receipt printer (optional)	Any printer the computer can print to. 80 mm thermal printers work best for slips and kitchen tickets.
Internet (most of the time)	Needed to sync, for the QR menu and for online orders. Selling carries on without it.
An email address	For the restaurant's online account. Use one the owner checks — it receives password reset links.
Extra screens (optional)	A tablet in the kitchen, a phone for the waiter, a screen facing customers.

GETTING STARTED

2 Setting up your restaurant

Setting up takes about ten minutes. The owner does it once on the first till; every other till, tablet and phone then simply **connects** to the same restaurant.




Figure 2. *The set-up path, left to right and top to bottom.*




Figure 3. *Set-up, step 1: your restaurant and its web address.*

Connecting another till, tablet or phone

1. On the new device open **pos.techplug.co.zw** (or install the Windows app).
2. Tap **Connect to my restaurant** and sign in with the restaurant's email and password.
3. The device downloads the menu, staff and the last six months of sales. It is ready when the PIN screen shows your restaurant's name.

> **TIP**
> Each till gets its own range of slip numbers (till 1 starts at 1, till 2 at 501, and so on) so two tills never print the same number. You can see or change a till's number in **Settings → Numbering & printing**.

Staff and what they can do

Everyone logs in with their own 4-digit PIN — never share the owner PIN. After 5 wrong tries the screen locks for 30 seconds, then longer each time. What each person sees depends on their role:

Role	Can use
Owner	Everything, including Settings, Branches, the plan and changing managers.
Manager	Till, kitchen, orders, change, stock, reports, books, menu and staff (but not owners).
Cashier	Sell, Tables, Orders and customer Change.
Kitchen	Kitchen screen, Sold out switches, Stock and Orders.
Attendant	Takes orders at tables (waiter). Payment is taken at the counter.

SELLING

3 Taking an order

The **Sell** screen is where cashiers spend the day. Meals are grouped by category along the top; tap a meal to add it to the order on the right.




Figure 4. *The life of a counter order.*




Figure 5. *The Sell screen with an order. The total and* **Pay** *button are bottom right.*

Taking payment

1. Tap **Pay**. Choose how the customer pays: **Cash**, **EcoCash**, **InnBucks**, **Swipe** and any others you set up.
2. For cash, choose the currency and tap the notes the customer gave (or type the amount). The change appears in green.
3. If you do not have small change, use **Not enough change?**: give part in another currency, or type the customer's name and the rest is kept for them.
4. Tap **Confirm**. The order number appears and the slip and kitchen ticket print (if printing is on).




Figure 6. *Payment: $20 received, $7 change.*




Figure 7. *Order sent — the number to hand over and the printed ticket.*

Order numbers

Choose in **Settings → Numbering & printing** whether customers get a plastic **number card**, a **printed slip** or both. With cards, the cashier types the card number; the number is free again once the order is collected.

Adding to an order, cancelling and change

You want to…	Do this
Add to an order already paid	**Orders** → the order → **Drink** (adds drinks or anything else). Only the new items are paid and sent to the kitchen.
Cancel an order	**Orders** → the order's ··· menu → **Cancel sale**, choose a reason. A manager's PIN is needed. Cancelled sales stay in the records, marked cancelled.
Keep change for a customer	In payment, hand over what you can; type the customer's name (and phone) for the rest. It shows in **Change** until it is collected.
Give kept change back	**Change** → find the customer → **Collect change**, or use it towards their next order.
Mark a meal sold out	**Sold out** → switch the meal off. It greys out on every till and on the QR menu.

Meal photos on the Sell screen

Add a photo to a meal in **Menu** and its button on the Sell screen shows the picture. Meals without photos show their initials in a coloured tile, so a mixed menu still looks tidy.




Figure 8. *Customer change: money the restaurant is holding for customers.*




Figure 9. *Sell screen with meal photos.*

4 Kitchen, orders and tables

The kitchen screen

Put a tablet or a second screen in the kitchen, log in with a Kitchen PIN and open **Kitchen**. Each order shows its number, items, extras, notes and how long it has been waiting. The timer turns orange and then red when an order takes longer than your serving times. Tap **Done** when the food is ready.




Figure 10. *Kitchen screen: order 1 waiting 3 seconds.*




Figure 11. *Orders: in the kitchen, ready to serve, served today.*

Orders

Orders lists everything not yet collected. Tap **Served** when the customer has their food. Use **Drink** to add to an order, and the ··· menu to **Reprint ticket**, **Mark ready** or **Cancel sale**.

Tables

If you serve at tables (turn it on in **Settings → How you serve**), **Tables** shows every table and whether it is free, ordering, waiting for food or ready to pay. A waiter opens a table, adds rounds through the evening, and the cashier prints the bill and takes payment once.




Figure 12. *Tables: free, busy and waiting tables at a glance.*

REFERENCE

5 Every screen

The menu on the left changes with the person logged in — a cashier sees only what a cashier needs. Here is every item in order.

Screen	Who	What it is for
Tables	Cashier, attendant, manager	Table service: open tables, add rounds, print the bill. Shown when table service is on.
Sell	Cashier, manager, owner	Take counter orders and payments.
Orders	Everyone	Orders in the kitchen, ready to serve and served today.
Online orders	Cashier, manager, owner	Orders from your QR menu and web page. Shown when online orders are on.
Kitchen	Kitchen, manager	What to cook, with timers. Tap Done when ready.
Change	Cashier, manager	Change kept for customers, and paying it back.
Sold out	Kitchen, manager	Switch meals and ingredients off for today.
Stock	Kitchen, manager	What is left, what was used, stock counts and purchases.
Reports	Manager, owner	Sales, customers, busy times, best sellers, staff, serving speed.
Books	Manager, owner	Profit and loss, purchases, expenses, the cash drawer.
Branches	Owner	All your branches' sales together; add a branch. Shown with an online account.
Staff	Manager, owner	Add people, set roles and PINs, suspend someone, the staff log.
Menu	Manager, owner	Categories, meals, prices, photos, extras (add-ons).
Settings	Owner (some parts managers)	Everything about how the restaurant works — see section 8.

YOUR NAME, TOP RIGHT

Tap your name to open **My account** (change your PIN, see the account email), switch to another person, lock the till, or **Switch restaurant** on a shared device.




Figure 13. *Menu: categories and extras.*




Figure 14. *Staff: roles, PINs and the staff log.*

6 Stock, reports and books

Stock

Link each meal to the ingredients it uses (for example sadza and beef use mealie-meal and beef). Every sale then takes the stock down by itself. Record what you buy in **Books → Purchases**, note spoilt food with **Record waste**, and count what is really there with **Stock take** — the difference shows what went missing.




Figure 15. *Stock: what is left, what was used today and items running low.*

Reports

Pick **Today**, **7 days**, **30 days** or **90 days**. Tabs show the overview (sales, customers, average order), busy times and staff, what sells when, serving speed and money by payment method and currency.




Figure 16. *Reports: customers per day compared with the week before.*

Books

Books is the restaurant's money in one place: **Profit** (sales minus food cost and expenses), **Purchases**, **Expenses** (rent, wages, electricity), the **Sales journal** and **Cancellations**. The cash drawer box tells you how much cash should be in the drawer.




Figure 17. *Books: profit and loss and the cash drawer for the last 30 days.*

> **TIP**
>
> A new device keeps the last six months of sales. To see older history on it, open **Settings → Online account → Load older sales**.

CUSTOMERS' PHONES

7 Your web page, QR menu and online orders

Every restaurant with an online account gets a free web page at **pos.techplug.co.zw/*your-name***. It shows your menu, prices, opening hours, phone and location, and marks meals that are sold out. Turn on online orders and customers can order for pick-up — or delivery — from their phone.



Figure 18. *An online order from the customer's phone to collection.*




Figure 19. *What the customer sees on their phone.*

Turning it on

1. **Settings → Website & QR menu**: switch on **Restaurant web page**, **QR menu** and, if you want them, **Online orders**.
2. Fill in your phone, WhatsApp number, address and opening hours, then **Save details**.
3. Tap **Print QR posters** and put one on each table and at the counter. Table posters tell the till which table ordered.




Figure 20. *Settings → Website & QR menu.*




Figure 21. *A QR poster ready to print.*

Handling online orders at the till

A new order rings on every connected till and shows a red badge on **Online orders**. Tap the time it will take (**10 min**, **15 min**…) to accept it, or **Decline**. It then goes to the kitchen like any other order, as a tab named **WEB 1**, **WEB 2**…




Figure 22. *A new online order waiting to be accepted.*

The customer's phone follows the order:

New → Accepted → Ready → On the way (delivery) → Collected / delivered

Delivery

In **Settings → Website & QR menu → Delivery** switch on delivery, set the fee and the area you deliver to. Customers then choose pick-up or delivery and type their address; the fee is added to their total. When the food leaves, tap **Send out**; when the rider returns with the money, tap **Rider paid in**.

When a customer asks on WhatsApp "what do you have?"

> **REPLY YOU CAN COPY**
>
> Hi! Here is today's menu with prices — you can order straight from it and we'll tell you when it's ready: **pos.techplug.co.zw/*your-name***

SETTINGS

8 Every settings tab




Figure 23. *Settings, with its tabs along the top.*

Tab	What you set there
Restaurant & branding	Name, tagline, logo, colour, phone, address and the line printed at the bottom of slips.
Online account	Connect this till, the account email, sync state, change password or email, load older sales, disconnect.
Website & QR menu	Your web page, QR menu, online orders, delivery, details shown to customers, QR posters.
How you serve	Counter only, tables only, or both; table names and areas.
Numbering & printing	Number cards or slips, this till's number, when tickets print, what prints.
Payment methods	Cash, EcoCash, InnBucks, swipe, bank — switch on the ones you take.
Currencies	USD, ZiG, ZAR and today's exchange rates; which notes appear as quick buttons.
Menu & categories	Order of categories and what shows on the first screen.
Delivery	Your own delivery orders (riders, fees) for phone orders.
Serving times	How many minutes is normal for the kitchen; the kitchen timer colours.
Plan & payments	Your plan, until when it is paid, how to pay TechPlug and every payment recorded.
Backup	Download a backup file of the restaurant, or restore one.
Start fresh	Clear practice sales before you open (menu and staff stay).

9 Your account and your plan

My account

Tap your name (top right) → **My account**. Everyone can change their own PIN. The owner also sees the restaurant's account email and can change the password or email used to connect tills.




Figure 24. *My account.*




Figure 25. *Settings → Online account.*

Plans and prices

Plan	Price	What you get
Free trial	Free, 30 days	Everything, so you can run the restaurant on it before paying.
Restaurant	$15 a month	One restaurant, as many tills, phones and staff as you need.
Group	$35 a month	Up to 5 branches, each with its own tills, plus a combined view in **Branches**.

> **REMEMBER**
> When a trial or a paid month ends you still have **3 days** to pay while the till keeps selling. After that new sales pause until TechPlug records your payment — your records and reports stay open the whole time.

Paying TechPlug

Open **Settings → Plan & payments** for your plan, the end date and how to pay (cash, EcoCash or bank). Use your web address as the reference. As soon as TechPlug receives the money it is recorded and your tills carry on by themselves — nothing to install or restart.




Figure 26. *What happens as a trial or paid month runs out, and how a payment brings the till back.*




Figure 27. *Settings → Plan & payments.*

Branches

On the Group plan, open **Branches → Add a branch**. The new branch gets a copy of your menu and its own tills, staff and web address. **Branches** shows today's and the week's sales for every branch side by side. On a shared device use **Switch restaurant** (owner PIN or account password) to move between branches.




Figure 28. *Branches: every shop's sales in one place.*

Keeping the restaurant safe

- Every person has their own PIN; suspend people who leave instead of sharing PINs.
- Only the owner knows the account password. Change it if a till is stolen or a manager leaves.
- Download a backup now and then (**Settings → Backup**) and keep it off the till.
- Records are never deleted: a cancelled sale stays in the books, marked with who cancelled it and why.

EVERY DAY

10 Daily checklist and quick fixes

Opening

- Switch on the till and printer; check the top bar says **Online**.
- Update today's exchange rates if they changed.
- Switch off anything sold out.
- Open the kitchen screen.

Closing

- Make sure every order is served or cancelled.
- Count the cash and compare with **Books → Cash drawer**.
- Record today's purchases and expenses.
- Leave the till connected for a minute so everything syncs.

Problems and what to do

Problem	What to do
Top bar says "No internet"	Keep selling — everything is saved on the till and syncs when the internet is back.
A till shows different sales	Wait a few seconds; tills sync every 8 seconds when online. Check both are online.
Nothing prints	Check the printer is on and set as the computer's default printer, then use **Reprint ticket** on the order in **Orders**.
Wrong PIN, screen locked	Wait for the countdown. A manager or owner can set a new PIN in **Staff**.
"Sales are paused"	The plan has ended. Pay TechPlug; the till unlocks by itself once the payment is recorded.
Online orders not arriving	Check **Online orders** is switched on, at least one till is online, and the menu shows "Open now".
A "new version" bar appears	Tap it when the counter is quiet; the till reloads in a few seconds.
Forgot the account password	Message TechPlug on WhatsApp; we will reset it. Tills stay connected.

GETTING HELP

TechPlug: **techplug.co.zw** · WhatsApp button in **Settings → Plan & payments** and on **pos.techplug.co.zw/site**. Tell us your restaurant's web address and a photo of the screen.