

Fair Day Playbook

Everything left to do, in order, with every step spelled out. Then the tent, the walls, the signs, the cables, and the day itself, top to bottom, with pictures.

The whole booth in one line: the TV outside plays the loop for the line → Dakota hands you a lanyard at the rope → inside, four games on iPads, ninety seconds each → the results screen offers **Sign up** or **Play another game** → on the way out, the exit table: give your name, the worker checks the live sign-up sheet and hands you a gift box. Top Camera score each hour wins a \$25 gift card.

What is in here

1. **Part 1. The week before**, ten jobs, each as taps and clicks.
2. **Part 2. The shopping list**, with counts.
3. **Part 3. Setup day**, in the order that does not make you redo anything.
4. **Part 4. The tent and the walls**, with diagrams.
5. **Part 5. Where every sign goes**.
6. **Part 6. The day: roles, scripts, the hourly prize, fixes**.
7. **Part 7. Teardown**.

Confirmed 13 Sept: two 10x10 tents as one 20 by 10 room in the gym corner, outlet behind the back wall, TV on a table outside next to Dakota, entrance front-left, exit on the right side 3 to 4 ft from the locked ball-room door. The layout page shows it.

Companion notes on the project drive: STATE-2026-09-12.md (what is live and how to roll things back), IPAD-SETUP-2026-09-12.md (every iPad tap). Team page with the loop, the music vote and the sign drafts: tinyurl.com/ncc-preview . Games: tinyurl.com/ncc-booth . Sign-up: tinyurl.com/ncc-booth-signup

Part 1. The week before

Ten jobs. Do them in this order. Each one says who, how long, and every step.

1. Get the TV loop onto the booth laptop (Matt, 20 min, the one that bites if skipped)

The TV plays from the laptop, not from the website. The video and the music only exist in the project folder on your PC.

- 1 Plug a USB stick into your PC. Open **File Explorer** and go to **C:\Users\mstat\projects\X32-Haley-tool**.
- 2 Select **START-TV.bat** and the **docs** folder (click one, hold Ctrl, click the other). Right-click, **Copy**.
- 3 Open the USB stick in File Explorer, right-click an empty spot, **Paste**. About 60 MB. Wait for it to finish.
- 4 On the booth laptop, make a folder on the Desktop called **Booth** and paste both items into it. They must sit side by side: **Booth\START-TV.bat** and **Booth\docs**.
- 5 Plug the TV into the laptop with the HDMI cable. Turn the TV on and pick the HDMI input with the TV remote.
- 6 On the laptop, right-click the **speaker icon** at the bottom right of the screen, choose the sound output, and pick the **TV** (it is named after the TV brand). If you skip this, the music plays out of the laptop.
- 7 Double-click **START-TV.bat**. A black window opens, then Chrome fills the screen with the loop. You should hear the riser, three pops, then music under the slides. Let it run two full cycles.
- 8 To stop it: press **Alt+F4**, then close the small black window.

If the laptop has no HDMI port: buy a USB-C to HDMI adapter (Part 2). **If Chrome is not installed**, the bat falls back to Edge, which also works.

If it is this same PC going to the fair: skip the USB. Double-click START-TV.bat where it already lives and do steps 5 to 8 only.

2. Ask about the gym PA (Matt, one text)

- 1 Ask Shaina or Pastor: "Will music play over the gym speakers during the fair?"
- 2 If **yes**: on the laptop, right-click **START-TV.bat**, choose **Edit** (opens Notepad), find the line **set "SOUND=1"** near the middle, change the 1 to **0**, save. The loop runs silent. Or just mute the TV with the remote on the day.
- 3 If **no**: leave it. On the day, set the TV volume so you can hear it at the rope and not at the next booth.

3. Print the signs (whoever is near a Staples, by Thursday)

- 1 Wait for the team to pick page numbers on the team page. The QR sign and the High Score sign are already in.
- 2 Open **matt5306.github.io/ncc-media-booth/preview/booth-signs.pdf** on your phone and save it, or email it to yourself.
- 3 At Staples, Print & Marketing counter: "Poster prints, **18 by 24**, these pages only, matte." Foam-board mounting is optional and makes them hang flat. Budget roughly \$15 to \$25 a sign, half that unmounted.
- 4 Cheaper option for the QR sign and How It Works: print them on the church printer at letter size, four copies each, and tape those inside the tent at eye level.

4. iPads (one person, 15 min per iPad, the day before)

The full tap-by-tap version is IPAD-SETUP-2026-09-12.md. This is the short list.

- 1 **Settings > Wi-Fi**, join the gym network. Do this in the gym.
- 2 Safari, go to **tinyurl.com/ncc-booth**, Share button, **Add to Home Screen**, Add. All three iPads are game stations. The **exit-table laptop** keeps the sign-up sheet open, with **tinyurl.com/ncc-booth-signup** in a second tab for anyone without a phone.
- 3 **Settings > Display & Brightness > Auto-Lock > Never**. Brightness most of the way up.
- 4 Open the booth icon, tap **Camera**, tap Play, tap **Allow** when it asks for the camera.
- 5 **Settings > General > Date & Time > Set Automatically** on. Every iPad must agree on the time or the prize rounds drift.

- 6 Open the booth icon, tap the small **Host** button. Round length **60**. "After a game" **Auto-return ON**. Then **Clear all scores on this device**.
- 7 Play one full round of **every** game, including Sound. At the end you should see two buttons at the bottom, **Sign up** and **Play another game**, and a countdown. If you do not, tell Matt.
- 8 **Settings > Accessibility > Guided Access** on, set a passcode, write it on tape on the back. On the day: open the booth icon, triple-click the top button, **Start**.

5. The Google Form (Matt, 5 min)

- 1 Open **forms.google.com**, open the sign-up form, click **Responses**, then the green **Sheets** icon.
- 2 Find the row that says **Test Entry (delete me)**. Right-click its row number on the left, **Delete row**.
- 3 Back in the form, click the **three dots** at the top right, **Add collaborators**, type **media@newcreationchog.org**, Editor, Send.

6. Gift cards (Matt or Olivia, one store trip)

- 1 Buy **three \$25 cards** (Visa or Amazon), one per hour of the fair plus a spare. Keep the receipts for the media budget.
- 2 Put them in one envelope marked **PRIZE, exit table**. Whoever runs the exit hands them out (Part 6).

7. Gift boxes (Elsie, Haley, Dakota, build Sunday the 13th after service)

- 1 Per box: **one candy** (this pays off the "secret candy drawer" joke in the video; label it "from the secret candy drawer"), **one salty** (pretzels or popcorn), **one sweet** (fruit snack or Rice Krispies treat), **one drink** (juice pouch or a drink-mix stick, lighter than a bottle), the **kaleidoscope**, and a **card** with the sign-up link.
- 2 Nothing that melts. Nothing with nuts. Everything individually wrapped.
- 3 24 boxes. If the line looks longer than that on the day, the box goes to people who sign up first.

8. Interns under 18 (Matt, one text each)

- 1 For any intern under 18, text a parent: "Autumn is on our team slide at the fair and on our team's private preview page. OK with you?" Keep the reply.
-

9. Lanyards and the rope (Pastor Byers, Dakota)

- 1 About 80 lanyards from the youth ministry, in a box at the rope.
 - 2 A rope with two posts (a real stanchion, or two heavy plant stands and a rope). It only has to look like a rope.
-

10. Team feedback deadline (everyone, Wednesday)

- 1 Music vote (a number), sign pages to print, and how the results screen feels. Wording changes are minutes. New photos or video take longer, so those first.
-

Part 2. The shopping list

One trip. Tick as you go. Most of it is Walmart or Dollar Tree; the cables are anywhere.

ITEM	HOW MANY	WHY
☐ Large binder clips (2 inch)	20	The main way signs hang: clip foam board to the top hem of a sidewall or to the roof frame.
☐ Magnetic hooks (the strong kind)	8	Stick to the steel tent legs; hang light signs or the rope ends. Test one on the frame first.
☐ Safety pins , big	1 pack	Paper signs straight through the fabric.
☐ Zip ties , 8 inch	1 bag	Lights and cords to the frame; sidewall grommets to the legs.
☐ Canopy weight bags or 4 one-gallon water jugs	4	Gym floor, no stakes. The walls catch every draft from the doors; weights stop the tent walking.
☐ Gaffer tape (or duct tape)	1 roll	Cords to the floor along the wall. Gaffer leaves no goo on the gym floor. Ask the church first.
☐ Extension cords , 25 ft, an 8-outlet power strip and one small power strip	2 cords, 1 + 1 strips	Corner strip: TV, laptop, the lane lights, USB block, clip light. The second cord runs along the back wall to the small strip under the exit table, for the name-check laptop and floor strip 3.
☐ HDMI cable , 6 ft (+ USB-C to HDMI adapter if the laptop has no HDMI)	1	Laptop to TV. Carries the sound too.
☐ Clip-on LED light or a small ring light	1	The Camera game needs light on the visitor's face. Sidewalls make the tent dim.
☐ Tablet floor tripods (you have these)	3	Three stations at standing height. The exit table uses a laptop, not an iPad.
☐ Black tablecloths	2	TV table and the round exit table. Hides the cables and the small power strip under the exit table.

☐	Rope + 2 posts (stanchion set or improvise)	1	The bouncer needs something to lift.
☐	iPad chargers + 6 ft cables	3	Auto-Lock Never drains them. Charge at the stations.
☐	Sharpie, a clipboard, one sheet	1	The exit host writes each hour's winner so nobody gets two cards.
☐	\$25 gift cards	3	One per hour plus a spare.

Do not buy: painter's tape or Command hooks for the walls. Neither holds on tent fabric. Tape only goes on the floor.

Part 3. Setup day, in order

Arrive **two hours** before the doors. Four people. This order means nothing gets moved twice.

WHEN	WHAT	WHO
-2:00	Unload by the spot. Tent bag, tables, TV, laptop bag, cables, the sign folder, the box of boxes, lanyards, rope, weights.	All four
-1:50	Both tent frames up , side by side, backs to the gym wall (Part 4). Weights on all six legs. Middle wall stays off.	All four
-1:35	Sidewalls on : back, left, right, then the two front panels. Tie back the entrance (front-left) and the exit (right-front) with the gold sashes.	Two people
-1:35	Power run at the same time: extension cord from the outlet along the wall to the tent, power strip inside the back corner, tape the cord flat.	Other two
-1:20	TV table outside the front wall, right of the entrance, next to Dakota. TV facing the line, laptop behind it, HDMI in, sound output set to the TV, START-TV.bat. Let it run. Curtain lights clipped to the roof edge, power banks on the legs.	Matt
-1:10	Tripod stands inside : iPads 1 and 3 by the back wall, iPad 2 between them pulled 3 ft forward, the host spot behind it. Charger cables down the legs, taped. Clip light on the Camera stand, aimed at where the visitor stands. Floor lights: two rolls as a lane from the back wall to the flap, the third from the exit table across the front of the stands.	Two people
-1:00	Signs (Part 5). Outside walls first, then the station posters inside above each table.	Two people
-0:45	Exit table across the back-right corner: boxes and both coolers in the corner behind it, the worker between. QR sign facing the visitor, laptop facing the worker with the sign-up sheet open, prize envelope and clipboard. The exit itself stays wide open.	Exit host
-0:40	Rope and lanyards at the entrance side of the flap. Dakota's spot.	Dakota
-0:30	Walk it as a visitor . Watch the TV for one cycle, take a lanyard, play a round, watch for the two buttons, sign up (one real test entry is fine), take a box. Fix what felt wrong.	Everyone, once

-0:15	On every iPad: Host > Clear all scores , then Guided Access > Start . TV volume set. Phones on silent.	Matt
-------	--	------

0:00	Doors. Dakota puts on the sunglasses.
------	---------------------------------------

Two rules for the gym floor: tape only on the floor, never on the walls or the floor markings, and ask the church which tape they allow. Weights on the tent legs, never stakes.

Part 4. The tent and the walls


Putting up a 10x10 pop-up, four people

- 1 Stand the folded frame upright on its feet, roughly on the spot. Each person takes a leg.
- 2 Everyone walks **backward at the same time**, pulling the frame open until it is about three-quarters spread. Do not force the last bit yet.
- 3 Throw the canopy fabric over the top while it is still low. Line the corners up with the four corner brackets; velcro or clip the corners on.
- 4 Now finish spreading the frame all the way. The roof goes taut. Push the center roof peak up until it clicks.
- 5 Raise the legs **one at a time**, one click each, going around; then a second click each. Never one leg all the way up first, that twists the frame. Stop at the height where the roof edge clears the tallest teammate's head by a hand.
- 6 Set a weight bag or jug on each leg's foot and strap it to the leg.

Sidewalls

- 1 Each wall has velcro along its top edge that wraps the roof edge, and velcro or zippers down the sides that join it to the next wall or to the leg.
- 2 Do the **back wall** first, then the **two side walls**, then the **front**. Pull each wall snug before joining the next; wrinkles later mean sagging signs.
- 3 The front wall is the one with the **door flap** (a zipper up the middle, or a whole panel you roll up). Roll the flap up and tie it for the whole fair: that is the entrance and the exit, and it lets light and air in. If the front wall has no flap, leave that wall off entirely.
- 4 If a wall has grommets at the bottom, zip-tie them to the leg feet so the wall does not lift when someone brushes it.


Why not blackout? The old plan was a blacked-out tent. The Camera game uses the iPad camera on the visitor's face, and a dark tent makes a murky picture. Walls on three sides plus the open flap plus the clip light at the Camera station is the right amount of dark: it feels backstage, and the camera still works.



Side view. Weights on the feet, walls snug under the roof hem, signs on binder clips, one clip light inside at the Camera station.

The layout, from above

Confirmed 13 Sept: two 10x10 tents as one 20 ft by 10 ft room in the gym corner. Entrance at the left of the front, exit on the right side, TV outside next to Dakota, three iPads on tripods along the back wall with the host spot behind the middle one, a lane of floor light from the flap to the stands, and the round exit table across the back-right corner guarding the boxes and water. The exit itself stays clear. Updated 16 Sept.



The full three-page build plan (front wall, lights and power, what to bring, build order) is BOOTH-BUILD-PLAN-2026-09-13.pdf on the team page.

Signs decided: Backstage / Media Team large beside Dakota; Wanted on the bare 2 ft of the left wall in front of the curtain lights. The rest are placed on the plan as suggestions, marked with a star.

Part 5. Where every sign goes

SIGN (PAGE)	WHERE	HOW IT HANGS
1 Backstage / Media Team	Outside, large, on the front wall next to Dakota, between the entrance and the TV. Decided.	On an easel, or two binder clips on the roof hem.
2 Sign-up QR	Inside, on the right wall beside the exit table, eye level. A small copy stands on the exit table facing the visitor.	Binder clips on the roof hem; a photo frame or a folded card on the table.
3 High Score Board	Inside, next to the QR sign by the exit table, so people waiting for a box read the prize rule.	Binder clips.
4 Crew Only	Outside, beside the entrance flap.	Binder clips on the roof hem.
5 All Access	Outside, on the front wall above the TV.	Binder clips.
6 Wanted	Outside the left wall, on the bare 2 ft in front of the curtain lights. Decided.	Binder clips.
7 How It Works	Two copies. Outside where the rope starts, so the line reads it before reaching Dakota. Inside on the back wall, right of the stands.	Binder clips.

Keep the TV wall calm. The TV is the sign. Only All Access goes above it; nothing beside it. The four station posters were dropped from the Canva design, so they are not placed.

Hanging tips that save an hour

- 1** Hang from the **top hem** of the wall, never the middle. The hem is doubled fabric with the velcro inside; the middle stretches and sags.
- 2** Two clips per sign, one at each top corner. One clip and the sign swings.
- 3** Foam board hangs straight. Paper posters curl; tape a strip of cardboard across the back top edge before clipping.
- 4** Magnet hooks only hold on **steel** legs. Aluminum frames, which most cheap tents are, do not take magnets. Test one before you count on it.

5

Eye level for a standing adult is about **5 feet** to the center of the sign. Lower is better than higher; nobody looks up.

Part 6. The day

Roles, four people

WHO	WHERE	WHAT THEY SAY
Dakota , the bouncer	At the rope, sunglasses on	"Lanyard? You are on the list. Go on in. Four games, any order, ninety seconds each. Top Camera score this hour wins a gift card."
Matt , station host	The host spot, behind iPad 2	"Tap the game you want. Read the card, tap to start. Want a tip? Hold still once the box turns green."
Floating host	Between the stands and the exit table	Same. Points finished players along the floor light to the exit table. Resets a station if a visitor wandered off: tap Play another game, or just wait 40 seconds.
Exit host	Behind the exit table	"Did you sign up? Scan this, thirty seconds. What name did you put?" Sees the name on the live sheet, hands over a box and a water. Nobody helps themselves. Also runs the hourly prize.

The hourly prize, step by step

- 1 At the top of each hour the boards flip to a new round on their own. On **each** iPad, open the Camera game (or tap Play another game and then Camera) and read the **LAST ROUND** line at the bottom of the high-score board.
- 2 Highest score across the iPads wins. Write the initials and score on the clipboard so nobody gets two cards.
- 3 Say it out loud at the exit: "Last hour's top Camera score, J.M.R. with 840. Come get your card." If they are gone, the card goes to the next round's winner, not to second place.
- 4 The gift box is **not** the prize. Everyone who signs up gets a box. Keep those two sentences separate when you talk to people.

When something goes wrong

WHAT YOU SEE	DO THIS
TV shows a black screen or the laptop desktop	Alt+F4 the browser, double-click START-TV.bat again. If the TV says "no signal", reseal the HDMI at both ends.

TV has picture, no sound	Right-click the speaker icon on the laptop, pick the TV as output. TV remote: volume up, not muted.
An iPad shows a blank page	Wi-Fi. Settings > Wi-Fi, rejoin, then open the booth icon again.
Camera game shows a drawn room, not the camera	Camera permission. Settings > Safari > Camera > Allow. Or open the booth in Safari instead of the icon.
A visitor got out of the booth app	Guided Access was not started. Triple-click the top button, Start.
The results screen does not show the two buttons	Host > After a game > ON. If it still does not, the iPad cached an old version: Safari, reload the page once.
Two iPads show different round end times	Date & Time not automatic on one of them, or a different round length under Host.
The sign-up page froze on a half-finished form	Tap Start over at the bottom.
Wi-Fi drops for good	Pages already open keep working. Do not close them. The sign-up page holds entries and sends them when Wi-Fi returns.

Part 7. Teardown, 30 minutes

- 1 On each iPad: triple-click, passcode, **End** Guided Access. Open the sign-up page on each iPad once more on Wi-Fi so any held entries send. Then power everything down.
 - 2 Laptop: Alt+F4, close the black window, unplug HDMI, pack.
 - 3 Signs: unclip into the folder. Clips into the bag. Count the clips; they are next year's clips.
 - 4 Tables out of the tent, tablecloths folded.
 - 5 Pull the tape up slowly. Coil the cord. Power strip in the bag.
 - 6 Weights off the legs.
 - 7 Sidewalls off **before** touching the frame: front, sides, back. Fold each in half, then roll.
 - 8 Lower the legs one click at a time, round and round, same as going up. Pull the roof peak down, take the canopy off, then collapse the frame with one person on each leg walking in.
 - 9 Leftover boxes, lanyards, the clipboard and the prize envelope go to Matt. The clipboard sheet is the prize record.
-

Afterwards. The sign-up sheet is in the Google Form. Someone from the team reaches out within a week, which is what the thank-you screen promised. The games stay live at tinyurl.com/ncc-booth for training the people who said yes.

Built 12 September 2026 from the booth plan, the team chat, and the state of the software that night. Source: FAIR-DAY-PLAYBOOK-2026-09-12.html in the project folder.