Kubernetes and Istio

03 - Pod

Generated: June 2026
Version 1.0

3 - Pod

Pod overview

A **pod** is a group of one or more containers (such as Docker containers), with shared storage/network, and a specification for how to run the containers. Pods are the smallest deployable artifacts in a Kubernetes cluster. This is the Kubernetes equivalent of a "machine" in whatever cloud you're using.

Pods are usually not created directly. Instead, they're created using workload resources like Deployment or Job. Workload resources will create and manage pods for you. When a pod is created directly, it is called a **naked pod**. If a naked pod is deleted, it will not be recreated. Kubernetes will restart and replace containers within pods as needed, but not pods themselves.

Workload resources are Kubernetes resources that manage pods. A controller is a control loop that watches the state of your cluster, then makes or requests changes where needed. Each controller tries to move the current cluster state closer to the desired state. Controllers check the state of the cluster through the Kubernetes API server. A workload resource is the configuration you use to define how your pods should be managed.

Here are some built-in workload resources:

- **Deployment** and **ReplicaSet** (replicaset): Deployment is recommended for managing stateless applications in your cluster. Deployments manage ReplicaSets and provide declarative updates to pods.
- **StatefulSet** (statefulset): Lets you run one or more related pods that do track state somehow. For example, if your workload records data persistently, you can run a StatefulSet that matches each pod with a PersistentVolume. Your code, running in the pods for that StatefulSet, can replicate data to other pods in the same StatefulSet to improve overall resilience.
- **DaemonSet** (daemonset): Defines pods that provide facilities that are local to a specific node in your cluster, such as a driver for a storage system or hardware device.
- **Job** (job): Defines pods that run to completion, then stop. Jobs are appropriate for data processing that will take a finite time.

Here's a Deployment that runs a single Pod running the `nginx` container:

```yaml
apiVersion: apps/v1
kind: Deployment
metadata:
  name: nginx-deployment
  labels:
    app: nginx
spec:
  replicas: 1
  selector:
    matchLabels:
      app: nginx
  template:
    metadata:
      labels:
        app: nginx
    spec:
      containers:
      - name: nginx
        image: nginx:1.14.2
        ports:
        - containerPort: 80
```

Save this as `nginx-deployment.yaml` and run `kubectl apply -f nginx-deployment.yaml`.

Pod lifecycle

Pods follow a defined lifecycle, starting in the `Pending` phase, moving through `Running` if at least one of its primary containers starts OK, and then through either the `Succeeded` or `Failed` phases depending on whether any container in the pod terminated in failure.

Whilst a pod is running, the kubelet is able to restart containers to handle some kind of fault. Within a pod, Kubernetes tracks different container states and determines what action to take to make the pod healthy again.

In the Kubernetes API, pods have both a specification and an actual status. The status for a pod object consists of a set of pod conditions. You can also check whether or not pod readiness gates are met.

Kubernetes will check certain assumptions about pods before it schedules them onto nodes. For example, it verifies that the sum of the CPU requests for containers defined on a node is no greater than the CPU capacity of the node. If you don't want some checks to be performed, you may be able to disable them with pod scheduling readiness.

You can configure containers that run when Kubernetes starts up a pod. Your cluster may also run long-running sidecar containers to provide supporting services for the main application pod (such as service meshes).

Init containers

Init containers are specialized containers that run before app containers in a Pod. Init containers can contain utilities or setup scripts not present in an app image.

You can specify init containers in the Pod specification alongside the `containers` array (which describes app containers).

Init containers run and complete their tasks before the main application container starts. If an init container fails, the kubelet repeatedly restarts it until it succeeds. However, if the Pod has a `restartPolicy` of `Never`, Kubernetes does not restart the Pod.

To specify an init container for a Pod, add the `initContainers` field into the Pod specification, as an array of `container` items (similar to the app `containers` field and its contents). See API for Container for more info.

Init containers support all the fields and features of app containers, including resource limits, volumes, and security settings. However, the resource requests and limits for an init container are handled differently. Also, init containers do not support `lifecycle`, `livenessProbe`, `readinessProbe`, or `startupProbe` because they must run to completion before the Pod can be ready.

If you specify multiple init containers for a Pod, kubelet runs each init container sequentially. Each init container must succeed before the next can run. When all of the init containers have run, kubelet initializes the app containers for the Pod and runs them as usual.

Here's a manifest for a Pod with two init containers, which counts to 60:

```yaml
apiVersion: v1
kind: Pod
metadata:
  name: init-demo
spec:
  containers:
  - name: nginx
    image: nginx
    ports:
    - containerPort: 80
    volumeMounts:
    - name: workdir
      mountPath: /usr/share/nginx/html
  initContainers:
  - name: install
    image: busybox:1.28
    command:
    - wget
    - "-O"
    - "/work-dir/index.html"
    - http://kubernetes.io
    volumeMounts:
    - name: workdir
      mountPath: "/work-dir"
  dnsPolicy: Default
  volumes:
  - name: workdir
    emptyDir: {}
```

Pod phases

A Pod's `status` field is a PodStatus object, which has a `phase` field.

The phase of a Pod is a simple, high-level summary of where the Pod is in its lifecycle. The phase is not intended to be a comprehensive rollup of observations of container or Pod state, nor is it intended to be a comprehensive state machine.

The number and meanings of Pod phase values are tightly guarded. Other than what is documented here, nothing should be assumed about Pods that have a given `phase` value.

Here are the possible values for `phase`:

- `Pending`: The Pod has been accepted by the Kubernetes cluster, but one or more of the containers has not been set up and made ready to run. This includes time a Pod spends waiting to be scheduled as well as time spent downloading container images over the network.
- `Running`: The Pod has been bound to a node, and all of the containers have been created. At least one container is still running, or is in the process of starting or restarting.
- `Succeeded`: All containers in the Pod have terminated in success, and will not be restarted.
- `Failed`: All containers in the Pod have terminated, and at least one container has terminated in failure. That is, the container either exited with non-zero status or was terminated by the system, and is not set for automatic restarting.
- `Unknown`: For some reason the state of the Pod could not be obtained, typically due to an error in communicating with the host of the Pod.

Pod conditions

A Pod has a PodStatus, which has an array of PodConditions through which the Pod has or has not passed:

- `PodScheduled`: the Pod has been scheduled to a node.
- `PodReadyToStartContainers`: the Pod sandbox has been successfully created and networking configured.
- `ContainersReady`: all containers in the Pod are ready.
- `Initialized`: all init containers have started successfully.
- `Ready`: the Pod is able to serve requests and should be added to the load balancing pools of all matching Services.

Container States

As well as the phase of the Pod overall, Kubernetes tracks the state of each container inside a Pod. You can use container lifecycle hooks to trigger events to run at certain points in a container's lifecycle.

Once the scheduler assigns a Pod to a Node, the kubelet starts creating containers for that Pod using a container runtime. There are three possible container states: `Waiting`, `Running`, and `Terminated`.

To check the state of a Pod's containers, you can use `kubectl describe pod <name-of-pod>`. The output shows the state for each container within that Pod.

Each state has a specific meaning:

- `Waiting`: This is the default state of a container. If a container is not in either the `Running` or `Terminated` state, it is `Waiting`. A container in the `Waiting` state is still running the operations it requires in order to complete start up: for example, pulling the container image from a container image registry, or applying Secret data. When you use `kubectl` to query a Pod with a container that is `Waiting`, you also see a Reason field to summarize why the container is in that state.
- `Running`: The `Running` status indicates that a container is executing without issues. If there was a `postStart` hook configured, it has already executed and finished. When you use `kubectl` to query a Pod with a container that is `Running`, you also see information about when the container entered the `Running` state.
- `Terminated`: A container in the `Terminated` state began execution and then either ran to completion or failed for some reason. When you use `kubectl` to query a Pod with a container that is `Terminated`, you see a reason, an exit code, and the start and finish time for that container's period of execution. If a container has a `preStop` hook configured, this hook runs before the container enters the `Terminated` state.

Container Probes

A probe is a diagnostic performed periodically by the kubelet on a container. To perform a probe, the kubelet can invoke different actions:

- `ExecAction` (performed with the help of the container runtime)
- `TCPSocketAction` (checked directly by the kubelet)
- `HTTPGetAction` (checked directly by the kubelet)

You can extend the probe with configuration fields:

```yaml
apiVersion: v1
kind: Pod
metadata:
  name: liveness-demo
spec:
  containers:
  - name: liveness
    image: registry.k8s.io/busybox
    args:
    - /bin/sh
    - -c
    - touch /tmp/healthy; sleep 30; rm -rf /tmp/healthy; sleep 600
    livenessProbe:
      exec:
        command:
        - cat
        - /tmp/healthy
      initialDelaySeconds: 5
      periodSeconds: 5
```

The kubelet can optionally perform and react to three kinds of probes on running containers:

- `livenessProbe`: Indicates whether the container is running. If the liveness probe fails, the kubelet kills the container, and the container is subjected to its restart policy. If a container does not provide a liveness probe, the default state is `Success`.
- `readinessProbe`: Indicates whether the container is ready to respond to requests. If the readiness probe fails, the endpoints controller removes the Pod's IP address from the endpoints of all Services that match the Pod. The default state of readiness before the initial delay is `Failure`. If a container does not provide a readiness probe, the default state is `Success`.
- `startupProbe`: Indicates whether the application within the container is started. All other probes are disabled if a startup probe is provided, until it succeeds. If the startup probe fails, the kubelet kills the container, and the container is subjected to its restart policy. If a container does not provide a startup probe, the default state is `Success`.

Init containers: An application container is created in a pod and has a fixed set of tasks and then terminates. Init containers are created before application containers and are used to start application dependencies.

Container Runtime Pod (PID=0): Pod

pause container

Network Namespace

Cgroups

Volumes

Shared Memory Segment

Container Runtime Pod (PID=0): Pod

Init Container

Application Container

Network Namespace

Cgroups

Volumes

Shared Memory Segment

5. Debugging shell

You can debug a shell running in a container. For example, if you have a container based on `gcr.io/distroless/base` which does not include any debugging utilities, you can debug it using `busybox`. First run the container:

```
kubectl run ephemeral-demo --image=gcr.io/distroless/base --restart=Never -- sleep 1d
```

Then run `busybox` and add a debugging container to it. If you specify the `-i` flag to `kubectl debug`, you automatically attach to the new debugging container.

```
kubectl debug -it ephemeral-demo --image=busybox:1.28 --target=ephemeral-demo
```

This command adds a new busybox container and attaches to it. The `--target` parameter targets the process namespace of another container. It's necessary here because `kubectl run` does not enable [process namespace sharing](https://kubernetes.io/docs/tasks/configure-pod-container/share-process-namespace/) in the pod it creates.

You can view the process list of the `ephemeral-demo` container. To see the output of the `ps` command, run `kubectl logs ephemeral-demo -c ephemeral-demo`.

```
Process ID   USER     TIME   COMMAND
    1 root      0:00 sleep 1d
    7 root      0:00 /bin/busybox-extras telnetd -F
    8 root      0:00 sh
   13 root      0:00 ps
```

You can interact with this container, for example to see files in its filesystem namespace:

```
kubectl exec -it ephemeral-demo -c ephemeral-demo -- sh
```

6. Pod conditions

A Pod has a PodStatus, which has an array of PodConditions through which the Pod has or has not passed:

- `PodScheduled`: the Pod has been scheduled to a node.
- `PodReadyToStartContainers`: the Pod sandbox has been successfully created and networking configured.
- `ContainersReady`: all containers in the Pod are ready.
- `Initialized`: all init containers have started successfully.
- `Ready`: the Pod is able to serve requests and should be added to the load balancing pools of all matching Services.

7. Container States

As well as the phase of the Pod overall, Kubernetes tracks the state of each container inside a Pod. You can use container lifecycle hooks to trigger events to run at certain points in a container's lifecycle.

Once the scheduler assigns a Pod to a Node, the kubelet starts creating containers for that Pod using a container runtime. There are three possible container states: `Waiting`, `Running`, and `Terminated`.

To check the state of a Pod's containers, you can use `kubectl describe pod <name-of-pod>`. The output shows the state for each container within that Pod.

Each state has a specific meaning:

- `Waiting`: This is the default state of a container. If a container is not in either the `Running` or `Terminated` state, it is `Waiting`. A container in the `Waiting` state is still running the operations it requires in order to complete start up: for example, pulling the container image from a container image registry, or applying Secret data. When you use `kubectl` to query a Pod with a container that is `Waiting`, you also see a Reason field to summarize why the container is in that state.
- `Running`: The `Running` status indicates that a container is executing without issues. If there was a `postStart` hook configured, it has already executed and finished. When you use `kubectl` to query a Pod with a container that is `Running`, you also see information about when the container entered the `Running` state.
- `Terminated`: A container in the `Terminated` state began execution and then either ran to completion or failed for some reason. When you use `kubectl` to query a Pod with a container that is `Terminated`, you see a reason, an exit code, and the start and finish time for that container's period of execution. If a container has a `preStop` hook configured, this hook runs before the container enters the `Terminated` state.

Container Runtime Pod (PID=0)
Container (main app)
1. Pod initialization
Init Container
Application Starting Point
Exit
Status: Initializing (Succeeded)
2. Healthy Phase
HTTP GET / (Port=80)
Status: pod.containers[].ready: true
HTTP GET / (Port=80)
Status: pod.containers[].ready: false
3. Unhealthy Phase (App Deadlocks or Crashes)
HTTP GET / (Port=80)
Status: pod.containers[].ready: false
TCP Socket Server Error
Failure
Status: pod.containers[].ready: false
4. Terminal (Failed) Exit
Status: pod.containers[].ready: false
Status: pod.containers[].ready: false
Status: pod.containers[].ready: false