Dependency Injection (DI)

Dependency Injection (DI) is a design pattern in which a class receives its **dependencies** (services or objects) from an external source rather than creating them itself. It is a form of **Inversion of Control** (IoC), where the framework controls when and how to inject the dependencies.

Without Dependency Injection (tight coupling):

```
public class Car {
    private Engine engine = new Engine();

    public void start() {
        engine.ignite(); // Car is tightly coupled to Engine
    }
}
```

Problems:

- Car is tightly coupled to Engine.
- If you want to change Engine (e.g., to ElectricEngine), you must **modify the Car** class.
- Testing Car is difficult because you can't easily mock Engine.

With Dependency Injection, the class doesn't create the dependency — **someone else does**:

```
public class Car {
    private Engine engine;

    public Car(Engine engine) { // Dependency is injected
        this.engine = engine;
    }

    public void start() {
        engine.ignite();
    }
}
```

Benefits of DI:

- Loose coupling between classes and their dependencies.
- Easier to test (you can inject mock objects).
- Promotes cleaner, more maintainable code.

The Spring IoC Container

The **Spring IoC (Inversion of Control) container** is the core of the Spring Framework. It creates the objects, configures and assembles their dependencies, and manages their entire lifecycle. The container uses DI to manage the components that make up a application.

Core Spring Classes (Packages)

Dependency Injection Types

Constructor Injection

Dependencies are provided as a **constructor parameter**.

```
public class Car {
    private Engine engine;

    @Autowired
    public Car(Engine engine) {
        this.engine = engine;
    }
}
```

Setter Injection

Dependencies are provided through a **setter method**.

```
public class Car {
    private Engine engine;

    @Autowired
    public void setEngine(Engine engine) {
        this.engine = engine;
    }
}
```

Field Injection

Dependencies are injected **directly into fields** using reflection.

```
public class Car {
    @Autowired
    private Engine engine;
}
```

Interface

Dependencies are injected **via an interface** method.

```
public interface EngineAware {
    void setEngine(Engine engine);
}

public class Car implements EngineAware {
    private Engine engine;

    @Override
    public void setEngine(Engine engine) {
        this.engine = engine;
    }
}
```

Lookup

Dependencies are looked up **dynamically** from the container.

```
public class Car {
    public void start() {
        Engine engine = context.getBean(Engine.class);
        engine.ignite();
    }
}
```

The @Autowired and @Inject Annotations

The `@Autowired` and `@Inject` annotations are used for **automatic dependency injection** in Spring. They tell the framework to automatically find and inject the required beans.

@Autowired

```
@Component
public class Car {
    @Autowired
    private Engine engine;

    public void start() {
        engine.ignite();
    }
}
```

@Inject

```
@Component
public class Car {
    @Inject
    private Engine engine;

    public void start() {
        engine.ignite();
    }
}
```

@Autowired works in Spring and **@Inject** is a standard.

@Qualifier

```
@Component
public class Car {
    @Autowired
    @Qualifier("electricEngine")
    private Engine engine;

    public void start() {
        engine.ignite();
    }
}
```

@Primary

```
@Component
@Primary
public class ElectricEngine implements Engine {
    @Override
    public void ignite() {
        System.out.println("Electric engine ignited");
    }
}
```

Circular Dependencies in Spring

A **circular dependency** occurs when two or more beans depend on each other, directly or indirectly.

Example:

```
@Component
public class A {
    @Autowired
    private B b;
}

@Component
public class B {
    @Autowired
    private A a;
}
```

Spring handles circular dependencies **if at least one dependency** (but **not** all) is **not** set by the constructor.

Example:

```
@Component
public class A {
    private B b;

    @Autowired
    public void setB(B b) {
        this.b = b;
    }
}

@Component
public class B {
    @Autowired
    private A a;
}
```

Resources

- [Spring Framework Documentation](https://docs.spring.io/spring-framework/docs/current/reference/html/)
- [Spring Dependency Injection Guide - Baeldung](https://www.baeldung.com/spring-dependency-injection)