VARIATIONAL MONTE CARLO METHODS FOR QUANTUM DOTS

Matteo Seclì

July 2015

UNIVERSITY OF TRENTO - DEPARTMENT OF PHYSICS

CONTENTS

What are quantum dots?

The algorithm

The 2-electrons system

The 6-electrons system

Conclusion

WHAT ARE QUANTUM DOTS?

Quantum dots can be thought as artificial atoms.

The term "quantum dots" refers to finite fermion systems consisting of an artificial 3D confinement of a few electrons, that have a size of only a few hundred angstroms.

Although this definition is quite precise, I prefer a more immediate one: "quantum dots are *artificial atoms*". Despite its simplicity, this definition contains a good amount of relevant information. Like natural atoms, in fact, quantum dots are made up of electrons confined in an attractive potential; and as one may guess, they show a similar shell-like structure with its relative *magic numbers*.

Such confinement is usually achieved by restricting the two-dimensional electron gas that forms at the interface between two different semiconductor materials (or heterostructure), either laterally or vertically.

However, there are some obvious differences READ DIFFERENCES.

While in natural atoms the attractive potential is generated by a charged nucleus, in quantum dots there is no such a thing.

Quantum dots can be thought as artificial atoms.

Similarities with natural atoms:

The term "quantum dots" refers to finite fermion systems consisting of an artificial 3D confinement of a few electrons, that have a size of only a few hundred angstroms.

Although this definition is quite precise, I prefer a more immediate one: "quantum dots are *artificial atoms*". Despite its simplicity, this definition contains a good amount of relevant information. Like natural atoms, in fact, quantum dots are made up of electrons confined in an attractive potential; and as one may guess, they show a similar shell-like structure with its relative *magic numbers*.

Such confinement is usually achieved by restricting the two-dimensional electron gas that forms at the interface between two different semiconductor materials (or heterostructure), either laterally or vertically.

However, there are some obvious differences READ DIFFERENCES.

While in natural atoms the attractive potential is generated by a charged nucleus, in quantum dots there is no such a thing.

Quantum dots can be thought as artificial atoms.

Similarities with natural atoms:

· They are made up of electrons confined in an attractive potential

The term "quantum dots" refers to finite fermion systems consisting of an artificial 3D confinement of a few electrons, that have a size of only a few hundred angstroms.

Although this definition is quite precise, I prefer a more immediate one: "quantum dots are *artificial atoms*". Despite its simplicity, this definition contains a good amount of relevant information. Like natural atoms, in fact, quantum dots are made up of electrons confined in an attractive potential; and as one may guess, they show a similar shell-like structure with its relative *magic numbers*.

Such confinement is usually achieved by restricting the two-dimensional electron gas that forms at the interface between two different semiconductor materials (or heterostructure), either laterally or vertically.

However, there are some obvious differences READ DIFFERENCES.

While in natural atoms the attractive potential is generated by a charged nucleus, in quantum dots there is no such a thing.

Quantum dots can be thought as artificial atoms.

Similarities with natural atoms:

- · They are made up of electrons confined in an attractive potential
- They have a shell-structure with its relative magic numbers

The term "quantum dots" refers to finite fermion systems consisting of an artificial 3D confinement of a few electrons, that have a size of only a few hundred angstroms.

Although this definition is quite precise, I prefer a more immediate one: "quantum dots are *artificial atoms*". Despite its simplicity, this definition contains a good amount of relevant information. Like natural atoms, in fact, quantum dots are made up of electrons confined in an attractive potential; and as one may guess, they show a similar shell-like structure with its relative *magic numbers*.

Such confinement is usually achieved by restricting the two-dimensional electron gas that forms at the interface between two different semiconductor materials (or heterostructure), either laterally or vertically.

However, there are some obvious differences READ DIFFERENCES.

While in natural atoms the attractive potential is generated by a charged nucleus, in quantum dots there is no such a thing.

Quantum dots can be thought as artificial atoms.

Similarities with natural atoms:

- · They are made up of electrons confined in an attractive potential
- They have a shell-structure with its relative magic numbers

Differences:

The term "quantum dots" refers to finite fermion systems consisting of an artificial 3D confinement of a few electrons, that have a size of only a few hundred angstroms.

Although this definition is quite precise, I prefer a more immediate one: "quantum dots are *artificial atoms*". Despite its simplicity, this definition contains a good amount of relevant information. Like natural atoms, in fact, quantum dots are made up of electrons confined in an attractive potential; and as one may guess, they show a similar shell-like structure with its relative *magic numbers*.

Such confinement is usually achieved by restricting the two-dimensional electron gas that forms at the interface between two different semiconductor materials (or heterostructure), either laterally or vertically.

However, there are some obvious differences READ DIFFERENCES.

While in natural atoms the attractive potential is generated by a charged nucleus, in quantum dots there is no such a thing.

Quantum dots can be thought as artificial atoms.

Similarities with natural atoms:

- · They are made up of electrons confined in an attractive potential
- They have a shell-structure with its relative magic numbers

Differences:

· Shape of the potential (2D isotropic harmonic potential)

The term "quantum dots" refers to finite fermion systems consisting of an artificial 3D confinement of a few electrons, that have a size of only a few hundred angstroms.

Although this definition is quite precise, I prefer a more immediate one: "quantum dots are *artificial atoms*". Despite its simplicity, this definition contains a good amount of relevant information. Like natural atoms, in fact, quantum dots are made up of electrons confined in an attractive potential; and as one may guess, they show a similar shell-like structure with its relative *magic numbers*.

Such confinement is usually achieved by restricting the two-dimensional electron gas that forms at the interface between two different semiconductor materials (or heterostructure), either laterally or vertically.

However, there are some obvious differences READ DIFFERENCES.

While in natural atoms the attractive potential is generated by a charged nucleus, in quantum dots there is no such a thing.

Quantum dots can be thought as artificial atoms.

Similarities with natural atoms:

- · They are made up of electrons confined in an attractive potential
- They have a shell-structure with its relative magic numbers

Differences:

- · Shape of the potential (2D isotropic harmonic potential)
- · Dimensions (quantum dots are a few hundred angstroms big)

The term "quantum dots" refers to finite fermion systems consisting of an artificial 3D confinement of a few electrons, that have a size of only a few hundred angstroms.

Although this definition is quite precise, I prefer a more immediate one: "quantum dots are *artificial atoms*". Despite its simplicity, this definition contains a good amount of relevant information. Like natural atoms, in fact, quantum dots are made up of electrons confined in an attractive potential; and as one may guess, they show a similar shell-like structure with its relative *magic numbers*.

Such confinement is usually achieved by restricting the two-dimensional electron gas that forms at the interface between two different semiconductor materials (or heterostructure), either laterally or vertically.

However, there are some obvious differences READ DIFFERENCES.

While in natural atoms the attractive potential is generated by a charged nucleus, in quantum dots there is no such a thing.

Quantum dots can be thought as artificial atoms.

Similarities with natural atoms:

- · They are made up of electrons confined in an attractive potential
- They have a shell-structure with its relative magic numbers

Differences:

- · Shape of the potential (2D isotropic harmonic potential)
- · Dimensions (quantum dots are a few hundred angstroms big)
- · Structure and source of the potential

The term "quantum dots" refers to finite fermion systems consisting of an artificial 3D confinement of a few electrons, that have a size of only a few hundred angstroms.

Although this definition is quite precise, I prefer a more immediate one: "quantum dots are *artificial atoms*". Despite its simplicity, this definition contains a good amount of relevant information. Like natural atoms, in fact, quantum dots are made up of electrons confined in an attractive potential; and as one may guess, they show a similar shell-like structure with its relative *magic numbers*.

Such confinement is usually achieved by restricting the two-dimensional electron gas that forms at the interface between two different semiconductor materials (or heterostructure), either laterally or vertically.

However, there are some obvious differences READ DIFFERENCES.

While in natural atoms the attractive potential is generated by a charged nucleus, in quantum dots there is no such a thing.

Building technique: stack up different layers of semiconductor materials.

Quantum dots are built by stacking up different layers of semiconductors. The electron gas forms at the interface of different layers, and the confinement is obtained by applying a voltage to the top metal electrodes – called *gates*. In the Figure, the white bars have a length of 0.5 µm; so, the gates are created by lithographic patterning.

Another common method to fabricate quantum dots is to build heterostructure pillars by etching techniques. Here, the electrodes are at the top and at the bottom of the pillars.

 $Other fabricating \ processes \ include \ self-growth \ mechanisms, in \ which \ the \ growth \ conditions \ determine \ the \ form \ of \ the \ structure \ (that \ the \ t$

can be pyramidal, disk shaped or lens shaped), and cleaved-edge overgrowth, that consists in two separate Molecular Beam Epitaxy

growths on a specific substrate.

4

Building technique: stack up different layers of semiconductor materials.

Then, an electron gas forms at the interface between two layers.

Quantum dots are built by stacking up different layers of semiconductors. The electron gas forms at the interface of different layers, and the confinement is obtained by applying a voltage to the top metal electrodes – called *gates*. In the Figure, the white bars have a length of 0.5 µm; so, the gates are created by lithographic patterning.

Another common method to fabricate quantum dots is to build heterostructure pillars by etching techniques. Here, the electrodes are at the top and at the bottom of the pillars.

Other fabricating processes include self-growth mechanisms, in which the growth conditions determine the form of the structure (that

can be pyramidal, disk shaped or lens shaped), and cleaved-edge overgrowth, that consists in two separate Molecular Beam Epitaxy

growths on a specific substrate.

4

Building technique: stack up different layers of semiconductor materials.

Then, an electron gas forms at the interface between two layers.

The electron gas is confined by applying an electric voltage to the whole structure, either laterally of vertically.

Quantum dots are built by stacking up different layers of semiconductors. The electron gas forms at the interface of different layers, and the confinement is obtained by applying a voltage to the top metal electrodes – called *gates*. In the Figure, the white bars have a length of 0.5 µm; so, the gates are created by lithographic patterning.


Another common method to fabricate quantum dots is to build heterostructure pillars by etching techniques. Here, the electrodes are at the top and at the bottom of the pillars.

Other fabricating processes include self-growth mechanisms, in which the growth conditions determine the form of the structure (that can be pyramidal, disk shaped or lens shaped), and cleaved-edge overgrowth, that consists in two separate Molecular Beam Epitaxy growths on a specific substrate.

Building technique: stack up different layers of semiconductor materials.

Then, an electron gas forms at the interface between two layers.

The electron gas is confined by applying an electric voltage to the whole structure, either laterally of vertically.



(a) Lateral quantum dot.


(b) Etched quantum dots.

Quantum dots are built by stacking up different layers of semiconductors. The electron gas forms at the interface of different layers, and the confinement is obtained by applying a voltage to the top metal electrodes – called *gates*. In the Figure, the white bars have a length of 0.5 µm; so, the gates are created by lithographic patterning.

Another common method to fabricate quantum dots is to build heterostructure pillars by etching techniques. Here, the electrodes are at the top and at the bottom of the pillars.

Other fabricating processes include self-growth mechanisms, in which the growth conditions determine the form of the structure (that can be pyramidal, disk shaped or lens shaped), and cleaved-edge overgrowth, that consists in two separate Molecular Beam Epitaxy growths on a specific substrate.

4



The variational principle is a powerful tool that allows, for *any* system, to calculate an *upper bound* estimate for the *ground state* energy.

The Variational Principle is a method of general validity that can be used to gather information about a system with a Hamiltonian that we are unable to diagonalize. Specifically, this principle gives us an *upper bound* for the energy of the ground state. The formulation is really simple: if you pick *any state* $|\psi\rangle$ whatsoever, then SHOW FORMULA ON SLIDE.

In practice, one chooses a class of states for $|\psi\rangle$ parametrized by one or more parameters – the so-called *variational parameters*, and then calculates the quantity E_T for multiple sets of values of the variational parameters $\alpha_1 \ldots, \alpha_n$. The lower value of E_T obtained in this way is the required upper bound. If one manages to find an even lower value for E_T with a more clever wave-function, then he has found a better upper bound for the ground state energy.

The variational principle is a powerful tool that allows, for *any* system, to calculate an *upper bound* estimate for the *ground state* energy.

Being $E_{\rm gs}$ the ground-state energy, $|\psi\rangle$ a state whatsoever and \hat{H} the Hamiltonian of the system, the principle states that

The Variational Principle is a method of general validity that can be used to gather information about a system with a Hamiltonian that we are unable to diagonalize. Specifically, this principle gives us an *upper bound* for the energy of the ground state. The formulation is really simple: if you pick *any state* $|\psi\rangle$ whatsoever, then SHOW FORMULA ON SLIDE.

In practice, one chooses a class of states for $|\psi\rangle$ parametrized by one or more parameters – the so-called *variational parameters*, and then calculates the quantity E_T for multiple sets of values of the variational parameters $\alpha_1 \ldots, \alpha_n$. The lower value of E_T obtained in this way is the required upper bound. If one manages to find an even lower value for E_T with a more clever wave-function, then he has found a better upper bound for the ground state energy.

The variational principle is a powerful tool that allows, for *any* system, to calculate an *upper bound* estimate for the *ground state* energy.

Being $E_{\rm gs}$ the ground-state energy, $|\psi\rangle$ a state whatsoever and \hat{H} the Hamiltonian of the system, the principle states that

$$E_{\rm gs} \le \frac{\left\langle \psi \middle| \hat{H} \middle| \psi \right\rangle}{\left\langle \psi \middle| \psi \right\rangle}.\tag{1}$$

The Variational Principle is a method of general validity that can be used to gather information about a system with a Hamiltonian that we are unable to diagonalize. Specifically, this principle gives us an *upper bound* for the energy of the ground state. The formulation is really simple: if you pick *any state* $|\psi\rangle$ whatsoever, then SHOW FORMULA ON SLIDE.

In practice, one chooses a class of states for $|\psi\rangle$ parametrized by one or more parameters – the so-called *variational parameters*, and then calculates the quantity E_T for multiple sets of values of the variational parameters $\alpha_1 \ldots, \alpha_n$. The lower value of E_T obtained in this way is the required upper bound. If one manages to find an even lower value for E_T with a more clever wave-function, then he has found a better upper bound for the ground state energy.

The variational principle is a powerful tool that allows, for *any* system, to calculate an *upper bound* estimate for the *ground state* energy.

Being $E_{\rm gs}$ the ground-state energy, $|\psi\rangle$ a state whatsoever and \hat{H} the Hamiltonian of the system, the principle states that

$$E_{\rm gs} \le \frac{\left\langle \psi \mid \hat{H} \mid \psi \right\rangle}{\left\langle \psi \mid \psi \right\rangle}.\tag{1}$$

We are going to use this principle by calculating the quantity on the right hand side, for a chosen *trial wave-function* ψ_T . We will come back later on how to guess a realistic ψ_T .

The Variational Principle is a method of general validity that can be used to gather information about a system with a Hamiltonian that we are unable to diagonalize. Specifically, this principle gives us an *upper bound* for the energy of the ground state. The formulation is really simple: if you pick *any* state $|\psi\rangle$ whatsoever, then SHOW FORMULA ON SLIDE.

In practice, one chooses a class of states for $|\psi\rangle$ parametrized by one or more parameters – the so-called *variational parameters*, and then calculates the quantity E_T for multiple sets of values of the variational parameters $\alpha_1 \ldots, \alpha_n$. The lower value of E_T obtained in this way is the required upper bound. If one manages to find an even lower value for E_T with a more clever wave-function, then he has found a better upper bound for the ground state energy.

In the function-representation of the states, we can recast the above relation as

In the function-representation of the states, we can recast the above relation as

$$E_{\rm gs} \le \int d\vec{\tau} \, \mathcal{P}(\vec{\tau}) E_L(\vec{\tau}) \simeq \frac{1}{n} \sum_{i=1}^n E_L(\vec{\tau}), \tag{2}$$

In the function-representation of the states, we can recast the above relation as

$$E_{\rm gs} \le \int d\vec{\tau} \, \mathcal{P}(\vec{\tau}) E_L(\vec{\tau}) \simeq \frac{1}{n} \sum_{i=1}^n E_L(\vec{\tau}), \tag{2}$$

where

In the function-representation of the states, we can recast the above relation as

$$E_{\rm gs} \le \int d\vec{\tau} \, \mathcal{P}(\vec{\tau}) E_L(\vec{\tau}) \simeq \frac{1}{n} \sum_{i=1}^n E_L(\vec{\tau}),$$
 (2)

where

$$\mathcal{P}(\vec{\tau}) = \frac{|\psi_T|^2}{\int d\vec{\tau} |\psi_T|^2} \quad \text{and} \quad E_L(\vec{\tau}) = \frac{1}{\psi_T} \hat{H} \psi_T. \tag{3}$$

In the function-representation of the states, we can recast the above relation as

$$E_{\rm gs} \le \int d\vec{\tau} \, \mathcal{P}(\vec{\tau}) E_L(\vec{\tau}) \simeq \frac{1}{n} \sum_{i=1}^n E_L(\vec{\tau}),$$
 (2)

where

$$\mathcal{P}(\vec{\tau}) = \frac{|\psi_T|^2}{\int d\vec{\tau} |\psi_T|^2} \quad \text{and} \quad E_L(\vec{\tau}) = \frac{1}{\psi_T} \hat{H} \psi_T. \tag{3}$$

The quantity E_L is called the local energy.

Let's do a brief recap.

· Our upper bound is given by $\int d\vec{\tau} \, \mathcal{P}(\vec{\tau}) E_L(\vec{\tau})$

- · Our upper bound is given by $\int d\vec{\tau} \, \mathcal{P}(\vec{\tau}) E_L(\vec{\tau})$
- · We can calculate it as $\frac{1}{n} \sum_{i=1}^{n} E_L(\vec{\tau})$ for a big enough n

- · Our upper bound is given by $\int d\vec{\tau} \, \mathcal{P}(\vec{\tau}) E_L(\vec{\tau})$
- · We can calculate it as $\frac{1}{n} \sum_{i=1}^{n} E_L(\vec{\tau})$ for a big enough n
- \cdot In other words, the idea is to sample tons of E_L values at different positions in space and then take the mean

- · Our upper bound is given by $\int d\vec{\tau} \, \mathcal{P}(\vec{\tau}) E_L(\vec{\tau})$
- · We can calculate it as $\frac{1}{n} \sum_{i=1}^{n} E_L(\vec{\tau})$ for a big enough n
- \cdot In other words, the idea is to sample tons of E_L values at different positions in space and then take the mean
- · Since the E_L 's have a certain distribution, we should sample more points where the probability is higher and less points where the probability is lower, in order to be sure to have a consistent set of samples.

- · Our upper bound is given by $\int d\vec{\tau} \, \mathcal{P}(\vec{\tau}) E_L(\vec{\tau})$
- · We can calculate it as $\frac{1}{n} \sum_{i=1}^{n} E_L(\vec{\tau})$ for a big enough n
- · In other words, the idea is to sample tons of E_L values at different positions in space and then take the mean
- \cdot Since the E_L 's have a certain distribution, we should sample more points where the probability is higher and less points where the probability is lower, in order to be sure to have a consistent set of samples.
- But how can we achieve such a distribution of samples?

The solution is to use the Metropolis algorithm.

The solution is to use the Metropolis algorithm.

Let's suppose that we have just sampled E_L at a certain point in space, let's call it $\vec{r}^{\rm old}$.

The solution is to use the Metropolis algorithm.

Let's suppose that we have just sampled E_L at a certain point in space, let's call it $\vec{r}^{\rm old}$. Then, we make a random move to another point in space, $\vec{r}^{\rm new}$.

The solution is to use the Metropolis algorithm.

Let's suppose that we have just sampled E_L at a certain point in space, let's call it \vec{r}^{old} . Then, we make a random move to another point in space, \vec{r}^{new} .

To check whether we moved to a higher probability region, we calculate the ratio of the respective probabilities, that is

The solution is to use the Metropolis algorithm.

Let's suppose that we have just sampled E_L at a certain point in space, let's call it $\vec{r}^{\rm old}$. Then, we make a random move to another point in space, $\vec{r}^{\rm new}$.

To check whether we moved to a higher probability region, we calculate the ratio of the respective probabilities, that is

$$R \doteq \frac{\mathcal{P}(\vec{r}^{\text{new}})}{\mathcal{P}(\vec{r}^{\text{old}})} = \frac{|\psi(\vec{r}^{\text{new}})|^2}{|\psi(\vec{r}^{\text{old}})|^2}.$$
 (4)

Then

Then

· If $R \ge 1$, we accept this move because we are moving to a higher probability region and we sample E_L in the new position.

Then

- · If $R \ge 1$, we accept this move because we are moving to a higher probability region and we sample E_L in the new position.
- · If R<1, we can't blindly reject this move just because we are moving to a lower probability region; after all, we also have to populate the tails of the distribution! However, we can't accept all of this kind of moves.

Then

- · If $R \ge 1$, we accept this move because we are moving to a higher probability region and we sample E_L in the new position.
- · If R < 1, we can't blindly reject this move just because we are moving to a lower probability region; after all, we also have to populate the tails of the distribution! However, we can't accept all of this kind of moves.

Solution: generate a random number $r \in (0,1)$, and accept the move (i.e., sample E_L) if $r \leq R$. Otherwise, the sample is rejected.

Then

- · If $R \ge 1$, we accept this move because we are moving to a higher probability region and we sample E_L in the new position.
- · If R < 1, we can't blindly reject this move just because we are moving to a lower probability region; after all, we also have to populate the tails of the distribution! However, we can't accept all of this kind of moves.

Solution: generate a random number $r \in (0,1)$, and accept the move (i.e., sample E_L) if $r \leq R$. Otherwise, the sample is rejected.

This procedure is known as the brute force Metropolis algorithm.

Let's recap it:

· Choose a starting position $ar{r}^{\mathrm{old}}$ and a step-length l.

- · Choose a starting position $\vec{r}^{\rm old}$ and a step-length l.
- · Generate a random number ε in the interval (0,1) and compute a new position $\vec{r}^{\text{new}} = \vec{r}^{\text{old}} + l \varepsilon$.

- · Choose a starting position \vec{r}^{old} and a step-length l.
- · Generate a random number ε in the interval (0,1) and compute a new position $\bar{r}^{\text{new}} = \bar{r}^{\text{old}} + l \varepsilon$.
- · Compute the acceptance ratio $R = \frac{|\psi_T(\vec{r}^{\text{new}})|^2}{|\psi_T(\vec{r}^{\text{bld}})|^2}$.

- · Choose a starting position \vec{r}^{old} and a step-length l.
- · Generate a random number ε in the interval (0,1) and compute a new position $\bar{r}^{\text{new}} = \bar{r}^{\text{old}} + l\varepsilon$.
- · Compute the acceptance ratio $R = \frac{|\psi_T(\vec{r}^{\text{new}})|^2}{|\psi_T(\vec{r}^{\text{old}})|^2}$.
- · Generate a new random number r in the interval (0,1).

- · Choose a starting position \vec{r}^{old} and a step-length l.
- · Generate a random number ε in the interval (0,1) and compute a new position $\vec{r}^{\text{new}} = \vec{r}^{\text{old}} + l\varepsilon$.
- · Compute the acceptance ratio $R = \frac{|\psi_T(\vec{r}^{\text{new}})|^2}{|\psi_T(\vec{r}^{\text{told}})|^2}$.
- · Generate a new random number r in the interval (0,1).
- · If $R \geq r$, accept the step and store the position by letting $\vec{r}^{\rm old} = \vec{r}^{\rm new}.$

- · Choose a starting position \vec{r}^{old} and a step-length l.
- · Generate a random number ε in the interval (0,1) and compute a new position $\vec{r}^{\text{new}} = \vec{r}^{\text{old}} + l\varepsilon$.
- · Compute the acceptance ratio $R = \frac{|\psi_T(\vec{r}^{\text{new}})|^2}{|\psi_T(\vec{r}^{\text{told}})|^2}$.
- · Generate a new random number r in the interval (0,1).
- · If $R \geq r$, accept the step and store the position by letting $\vec{r}^{\rm old} = \vec{r}^{\rm new}$.
- If R < r, reject the step and discard the position by letting $\vec{r}^{\text{new}} = \vec{r}^{\text{old}}$.

A clever approach is to implement the importance sampling.

An improved acceptance ratio wastes less points. A better approach is to implement the *Importance sampling*, that consists in doing more clever assumptions on the shape of the transition probability.

Since we know the system we are working on, we know that if we recast the Schrödinger equation as a diffusion problem, the transition probability is going to be a Gaussian distribution (or a modified Gaussian).

A clever approach is to implement the importance sampling. *Idea*: use the knowledge about the system to improve the acceptance ratio R.

An improved acceptance ratio wastes less points. A better approach is to implement the *Importance sampling*, that consists in doing more clever assumptions on the shape of the transition probability.

Since we know the system we are working on, we know that if we recast the Schrödinger equation as a diffusion problem, the transition probability is going to be a Gaussian distribution (or a modified Gaussian).

A clever approach is to implement the importance sampling.

Idea: use the knowledge about the system to improve the acceptance ratio $\it R$.

Procedure:

An improved acceptance ratio wastes less points. A better approach is to implement the *Importance sampling*, that consists in doing more clever assumptions on the shape of the transition probability.

Since we know the system we are working on, we know that if we recast the Schrödinger equation as a diffusion problem, the transition probability is going to be a Gaussian distribution (or a modified Gaussian).

A clever approach is to implement the importance sampling.

Idea: use the knowledge about the system to improve the acceptance ratio R.

Procedure:

· Recast the Schrödinger equation a *diffusion problem*, in which the walker is pushed in those regions where the trial wave-function is larger.

An improved acceptance ratio wastes less points. A better approach is to implement the *Importance sampling*, that consists in doing more clever assumptions on the shape of the transition probability.

Since we know the system we are working on, we know that if we recast the Schrödinger equation as a diffusion problem, the transition probability is going to be a Gaussian distribution (or a modified Gaussian).

A clever approach is to implement the importance sampling.

Idea: use the knowledge about the system to improve the acceptance ratio R.

Procedure:

- · Recast the Schrödinger equation a *diffusion problem*, in which the walker is pushed in those regions where the trial wave-function is larger.
- · The force \vec{F} responsible for pushing the walker is called the quantum force, and can be expressed as

An improved acceptance ratio wastes less points. A better approach is to implement the *Importance sampling*, that consists in doing more clever assumptions on the shape of the transition probability.

Since we know the system we are working on, we know that if we recast the Schrödinger equation as a diffusion problem, the transition probability is going to be a Gaussian distribution (or a modified Gaussian).

A clever approach is to implement the importance sampling.

Idea: use the knowledge about the system to improve the acceptance ratio R.

Procedure:

- · Recast the Schrödinger equation a *diffusion problem*, in which the walker is pushed in those regions where the trial wave-function is larger.
- · The force \vec{F} responsible for pushing the walker is called the quantum force, and can be expressed as

$$\vec{F} = 2\frac{1}{\psi_T} \nabla \psi_T \tag{5}$$

An improved acceptance ratio wastes less points. A better approach is to implement the *Importance sampling*, that consists in doing more clever assumptions on the shape of the transition probability.

Since we know the system we are working on, we know that if we recast the Schrödinger equation as a diffusion problem, the transition probability is going to be a Gaussian distribution (or a modified Gaussian).

· The new position is calculated as

READ THE NEW POSITION.

Here, the random variable ε is no more uniform! For importance sampling, it's a *Gaussian* random variable.

· The new position is calculated as

$$r^{\text{new}} = r^{\text{old}} + D\vec{F}(r^{\text{old}})\Delta t + \varepsilon,$$
 (6)

READ THE NEW POSITION.

Here, the random variable ε is no more uniform! For importance sampling, it's a *Gaussian* random variable.

· The new position is calculated as

$$r^{\text{new}} = r^{\text{old}} + D\vec{F}(r^{\text{old}})\Delta t + \varepsilon,$$
 (6)

where Δt is a chosen time-step and D=0.5 is the diffusion constant.

READ THE NEW POSITION.

Here, the random variable ε is no more uniform! For importance sampling, it's a *Gaussian* random variable.

· The new position is calculated as

$$r^{\text{new}} = r^{\text{old}} + D\vec{F}(r^{\text{old}})\Delta t + \varepsilon,$$
 (6)

where Δt is a chosen time-step and D=0.5 is the diffusion constant.

· The improved acceptance ratio can be expressed as

READ THE NEW POSITION.

Here, the random variable ε is no more uniform! For importance sampling, it's a *Gaussian* random variable.

· The new position is calculated as

$$r^{\text{new}} = r^{\text{old}} + D\vec{F}(r^{\text{old}})\Delta t + \varepsilon,$$
 (6)

where Δt is a chosen time-step and D=0.5 is the diffusion constant.

· The improved acceptance ratio can be expressed as

$$R = \frac{|\psi_T(r^{\text{new}})|^2 G(r^{\text{old}}, r^{\text{new}}, \Delta t)}{|\psi_T(r^{\text{old}})|^2 G(r^{\text{new}}, r^{\text{old}}, \Delta t)}.$$
 (7)

READ THE NEW POSITION.

Here, the random variable ε is no more uniform! For importance sampling, it's a *Gaussian* random variable.

· The new position is calculated as

$$r^{\text{new}} = r^{\text{old}} + D\vec{F}(r^{\text{old}})\Delta t + \varepsilon,$$
 (6)

where Δt is a chosen time-step and D=0.5 is the diffusion constant.

· The improved acceptance ratio can be expressed as

$$R = \frac{|\psi_T(r^{\text{new}})|^2 G(r^{\text{old}}, r^{\text{new}}, \Delta t)}{|\psi_T(r^{\text{old}})|^2 G(r^{\text{new}}, r^{\text{old}}, \Delta t)}.$$
 (7)

where $G(x, y, \Delta t)$ is the Green's function

READ THE NEW POSITION.

Here, the random variable ε is no more uniform! For importance sampling, it's a *Gaussian* random variable.

· The new position is calculated as

$$r^{\text{new}} = r^{\text{old}} + D\vec{F}(r^{\text{old}})\Delta t + \varepsilon,$$
 (6)

where Δt is a chosen time-step and D=0.5 is the diffusion constant.

· The improved acceptance ratio can be expressed as


$$R = \frac{|\psi_T(r^{\text{new}})|^2 G(r^{\text{old}}, r^{\text{new}}, \Delta t)}{|\psi_T(r^{\text{old}})|^2 G(r^{\text{new}}, r^{\text{old}}, \Delta t)}.$$
 (7)

where $G(x, y, \Delta t)$ is the Green's function

$$G(y, x, \Delta t) = \frac{1}{(4\pi D\Delta t)^{3N/2}} \exp(-(y - x - D\Delta t F(x))^2 / 4D\Delta t).$$
 (8)

READ THE NEW POSITION.

Here, the random variable ε is no more uniform! For importance sampling, it's a *Gaussian* random variable.



Hamiltonian of the system:

Let's apply this algorithm to two electrons in an harmonic oscillator, without the electron-electron repulsion.

The unperturbed Hamiltonian is SHOW THE HAMILTONIAN.

Unlike the one-dimensional case, for two dimensions we need two quantum numbers: n_x and n_y for the x and y directions, respectively, and this causes a degeneracy in the energy levels. The principal quantum number is $n = n_x + n_y$.

Hamiltonian of the system:

$$\hat{H}_0 = \sum_{i=1}^2 \left(-\frac{1}{2} \nabla_i^2 + \frac{1}{2} \omega^2 r_i^2 \right),\tag{9}$$

Let's apply this algorithm to two electrons in an harmonic oscillator, without the electron-electron repulsion.

The unperturbed Hamiltonian is SHOW THE HAMILTONIAN.

Unlike the one-dimensional case, for two dimensions we need two quantum numbers: n_x and n_y for the x and y directions, respectively, and this causes a degeneracy in the energy levels. The principal quantum number is $n = n_x + n_y$.

Hamiltonian of the system:

$$\hat{H}_0 = \sum_{i=1}^2 \left(-\frac{1}{2} \nabla_i^2 + \frac{1}{2} \omega^2 r_i^2 \right),\tag{9}$$

Energy of a single electron in a 2D harmonic potential:

Let's apply this algorithm to two electrons in an harmonic oscillator, without the electron-electron repulsion.

The unperturbed Hamiltonian is SHOW THE HAMILTONIAN.

Unlike the one-dimensional case, for two dimensions we need two quantum numbers: n_x and n_y for the x and y directions, respectively, and this causes a degeneracy in the energy levels. The principal quantum number is $n = n_x + n_y$.

Hamiltonian of the system:

$$\hat{H}_0 = \sum_{i=1}^2 \left(-\frac{1}{2} \nabla_i^2 + \frac{1}{2} \omega^2 r_i^2 \right),\tag{9}$$

Energy of a single electron in a 2D harmonic potential:

$$E_s = \hbar\omega(n_x + n_y + 1). \tag{10}$$

Let's apply this algorithm to two electrons in an harmonic oscillator, without the electron-electron repulsion.

The unperturbed Hamiltonian is SHOW THE HAMILTONIAN.

Unlike the one-dimensional case, for two dimensions we need two quantum numbers: n_x and n_y for the x and y directions, respectively, and this causes a degeneracy in the energy levels. The principal quantum number is $n = n_x + n_y$.

Configuration:

This is the configuration of the system.

You see that the spatial parts of the wave-functions are equal because of the spin degeneracy, so the ground state energy of the complete system has a factor of 2 to take this thing into account.

For the same reason, the exact wave-function (or at least, its spatial part) can be expressed as the product of the single-particle wave-functions.

C is a normalization constant.

Configuration:



This is the configuration of the system.

You see that the spatial parts of the wave-functions are equal because of the spin degeneracy, so the ground state energy of the complete system has a factor of 2 to take this thing into account.

For the same reason, the exact wave-function (or at least, its spatial part) can be expressed as the product of the single-particle wave-functions.

 ${\it C}$ is a normalization constant.

Configuration:



Ground-state energy of the system, in natural units:

This is the configuration of the system.

You see that the spatial parts of the wave-functions are equal because of the spin degeneracy, so the ground state energy of the complete system has a factor of 2 to take this thing into account.

For the same reason, the exact wave-function (or at least, its spatial part) can be expressed as the product of the single-particle wave-functions.

 ${\it C}$ is a normalization constant.

Configuration:



Ground-state energy of the system, in natural units:

$$E_{\rm gs} = 2\omega. \tag{11}$$

This is the configuration of the system.

You see that the spatial parts of the wave-functions are equal because of the spin degeneracy, so the ground state energy of the complete system has a factor of 2 to take this thing into account.

For the same reason, the exact wave-function (or at least, its spatial part) can be expressed as the product of the single-particle wave-functions.

 ${\it C}$ is a normalization constant.

Configuration:



Ground-state energy of the system, in natural units:

$$E_{\rm gS} = 2\omega. \tag{11}$$

Exact wave-function:

This is the configuration of the system.

You see that the spatial parts of the wave-functions are equal because of the spin degeneracy, so the ground state energy of the complete system has a factor of 2 to take this thing into account.

For the same reason, the exact wave-function (or at least, its spatial part) can be expressed as the product of the single-particle wave-functions.

C is a normalization constant.

Configuration:



Ground-state energy of the system, in natural units:

$$E_{\rm gs} = 2\omega. \tag{11}$$

Exact wave-function:

$$\phi(\vec{r_1}, \vec{r_2}) = C \exp\left(-\omega \left(r_1^2 + r_2^2\right)/2\right). \tag{12}$$

This is the configuration of the system.

You see that the spatial parts of the wave-functions are equal because of the spin degeneracy, so the ground state energy of the complete system has a factor of 2 to take this thing into account.

For the same reason, the exact wave-function (or at least, its spatial part) can be expressed as the product of the single-particle wave-functions.

C is a normalization constant.

Since we know the exact wave-function, the problem is trivial. We choose our trial wave-function as

Since we know the exact wave-function, the problem is trivial.

We model our trial wave-function by adding a variational parameter α .

For $\alpha=1$ we expect to obtain a variational energy exactly equal to the ground state energy $E_{\rm gs}=2\omega$.

Since we know the exact wave-function, the problem is trivial. We choose our trial wave-function as

$$\psi_T(\vec{r}_1, \vec{r}_2) = \exp\left(-\alpha\omega\left(r_1^2 + r_2^2\right)/2\right). \tag{13}$$

Since we know the exact wave-function, the problem is trivial.

We model our trial wave-function by adding a variational parameter α .

For $\alpha=1$ we expect to obtain a variational energy exactly equal to the ground state energy $E_{\rm gs}=2\omega$.

Since we know the exact wave-function, the problem is trivial. We choose our trial wave-function as

$$\psi_T(\vec{r}_1, \vec{r}_2) = \exp(-\alpha\omega(r_1^2 + r_2^2)/2).$$
 (13)

where α is a variational parameter.

Since we know the exact wave-function, the problem is trivial.

We model our trial wave-function by adding a variational parameter α .

For $\alpha=1$ we expect to obtain a variational energy exactly equal to the ground state energy $E_{\rm gs}=2\omega$.

Since we know the exact wave-function, the problem is trivial. We choose our trial wave-function as

$$\psi_T(\vec{r}_1, \vec{r}_2) = \exp(-\alpha\omega(r_1^2 + r_2^2)/2).$$
 (13)

where α is a variational parameter.


For $\alpha=1$ we expect to obtain a variational energy exactly equal to the ground state energy $E_{\rm gs}=2\omega$.

Since we know the exact wave-function, the problem is trivial.

We model our trial wave-function by adding a variational parameter α .

For $\alpha=1$ we expect to obtain a variational energy exactly equal to the ground state energy $E_{\rm gs}=2\omega$.





The variational energy versus the variational parameter α . The settings used are: brute force sampling with step length 2, no Jastrow factor, no parallelization, 1000 variations of α around 1 with step 0.001, 1×10^7 Monte Carlo steps. Acceptance ratio varies from 40 to 60 %.

The full Hamiltonian is

The Hamiltonian of the full system, that includes the electron-electron repulsion, has an extra term that diverges when the two particles are near to each other.

The full Hamiltonian is

$$\hat{H} = -\frac{1}{2}\nabla_1^2 - \frac{1}{2}\nabla_2^2 + \frac{1}{2}\omega r_1^2 + \frac{1}{2}\omega r_2^2 + \frac{1}{|\vec{r_1} - \vec{r_2}|}.$$
 (14)

The Hamiltonian of the full system, that includes the electron-electron repulsion, has an extra term that diverges when the two particles are near to each other.

The full Hamiltonian is

$$\hat{H} = -\frac{1}{2}\nabla_1^2 - \frac{1}{2}\nabla_2^2 + \frac{1}{2}\omega r_1^2 + \frac{1}{2}\omega r_2^2 + \frac{1}{|\vec{r_1} - \vec{r_2}|}.$$
 (14)

Problem:

The Hamiltonian of the full system, that includes the electron-electron repulsion, has an extra term that diverges when the two particles are near to each other.

The full Hamiltonian is

$$\hat{H} = -\frac{1}{2}\nabla_1^2 - \frac{1}{2}\nabla_2^2 + \frac{1}{2}\omega r_1^2 + \frac{1}{2}\omega r_2^2 + \frac{1}{|\vec{r_1} - \vec{r_2}|}.$$
 (14)

Problem: the term

$$\frac{1}{|\vec{r_1} - \vec{r_2}|} \tag{15}$$

could be a division by zero.

The Hamiltonian of the full system, that includes the electron-electron repulsion, has an extra term that diverges when the two particles are near to each other.

The full Hamiltonian is

$$\hat{H} = -\frac{1}{2}\nabla_1^2 - \frac{1}{2}\nabla_2^2 + \frac{1}{2}\omega r_1^2 + \frac{1}{2}\omega r_2^2 + \frac{1}{|\vec{r_1} - \vec{r_2}|}.$$
 (14)

Problem: the term

$$\frac{1}{|\vec{r_1} - \vec{r_2}|} \tag{15}$$

could be a division by zero.

Solution:

The Hamiltonian of the full system, that includes the electron-electron repulsion, has an extra term that diverges when the two particles are near to each other.

The full Hamiltonian is

$$\hat{H} = -\frac{1}{2}\nabla_1^2 - \frac{1}{2}\nabla_2^2 + \frac{1}{2}\omega r_1^2 + \frac{1}{2}\omega r_2^2 + \frac{1}{|\vec{r_1} - \vec{r_2}|}.$$
 (14)

Problem: the term

$$\frac{1}{|\vec{r_1} - \vec{r_2}|} \tag{15}$$

could be a division by zero.

Solution: add, in the wave-function, a factor that cancels the divergence in the Hamiltonian.

The Hamiltonian of the full system, that includes the electron-electron repulsion, has an extra term that diverges when the two particles are near to each other.

The extra factor is usually modeled as

An extra factor to the non-interacting wave-function is added, that has the form READ THE SLIDE.

In two dimensions

$$a = \begin{cases} 1 & \text{anti-parallel spin} \\ 1/3 & \text{parallel spin} \end{cases}$$
 (16)

The extra factor is usually modeled as

$$\exp\left(\frac{ar}{1+\beta r}\right) \tag{17}$$

An extra factor to the non-interacting wave-function is added, that has the form READ THE SLIDE.

In two dimensions

$$a = \begin{cases} 1 & \text{anti-parallel spin} \\ 1/3 & \text{parallel spin} \end{cases}$$
 (16)

The extra factor is usually modeled as

$$\exp\left(\frac{ar}{1+\beta r}\right) \tag{17}$$

that is called the Padé-Jastrow factor.

An extra factor to the non-interacting wave-function is added, that has the form READ THE SLIDE.

In two dimensions

$$a = \begin{cases} 1 & \text{anti-parallel spin} \\ 1/3 & \text{parallel spin} \end{cases}$$
 (16)

The extra factor is usually modeled as

$$\exp\left(\frac{ar}{1+\beta r}\right) \tag{17}$$

that is called the Padé-Jastrow factor.

r is the inter-particle distance, a is a parameter that depends on the spin, while β is a *variational parameter*.

An extra factor to the non-interacting wave-function is added, that has the form READ THE SLIDE.

In two dimensions

$$a = \begin{cases} 1 & \text{anti-parallel spin} \\ 1/3 & \text{parallel spin} \end{cases}$$
 (16)

The extra factor is usually modeled as

$$\exp\left(\frac{ar}{1+\beta r}\right) \tag{17}$$

that is called the Padé-Jastrow factor.


r is the inter-particle distance, a is a parameter that depends on the spin, while β is a *variational parameter*.

For $\omega=1$ we get the upper bound E=3, that is compatible with the *actual* ground state energy.


An extra factor to the non-interacting wave-function is added, that has the form READ THE SLIDE.

In two dimensions

$$a = \begin{cases} 1 & \text{anti-parallel spin} \\ 1/3 & \text{parallel spin} \end{cases}$$
 (18)



The variational energy versus the variational parameters α and β . The settings used are: brute force sampling with step length 2, Jastrow factor, no parallelization, 200 variations of α and β with step 0.01, 1 \times 10⁵ Monte Carlo steps. Acceptance ratio varies from 45 to 55%.



The variational energy versus the variational parameters α and β . The settings used are: brute force sampling with step length 2, Jastrow factor, no parallelization, 20 variations of α and β with step 0.01, 1×10^6 Monte Carlo steps. Acceptance ratio varies from 45 to 55 %. The relative distance is about 1.64 in natural units.

Idea: take multiple measurements for each point in order to lower the error.

Despite the fact that we have very good values, you see that the error is still quite large.

Idea: take multiple measurements for each point in order to lower the error.

If we take n measurements of the same quantity, its error falls like

Despite the fact that we have very good values, you see that the error is still quite large.

Idea: take multiple measurements for each point in order to lower the error.

If we take n measurements of the same quantity, its error falls like

$$\frac{1}{\sqrt{n}}$$

Despite the fact that we have very good values, you see that the error is still quite large.


Idea: take multiple measurements for each point in order to lower the error.

If we take n measurements of the same quantity, its error falls like

$$\frac{1}{\sqrt{n}}$$

We obtain more precise energy values even with less Monte Carlo steps.

Despite the fact that we have very good values, you see that the error is still quite large.



The variational energy versus the variational parameters α and β . The settings used are: brute force sampling with step length 2, Jastrow factor, parallelization (8 threads), 20 variations of α and β with step 0.01, 2 × 10⁵ Monte Carlo steps. Acceptance ratio varies from 45 to 55 %.

Idea: implement importance sampling in order to waste less points.

A further improvement would be to implement the importance sampling, as explained in the previous section.

The only thing we have to care about is the amount of the time-step. READ THE SLIDE.

Idea: implement importance sampling in order to waste less points.

Problem:

A further improvement would be to implement the importance sampling, as explained in the previous section.

The only thing we have to care about is the amount of the time-step. READ THE SLIDE.

Idea: implement importance sampling in order to waste less points.

Problem: if the time-step is too small and we don't use enough Monte Carlo steps, we have bad data.

A further improvement would be to implement the importance sampling, as explained in the previous section.

The only thing we have to care about is the amount of the time-step. READ THE SLIDE.

Idea: implement importance sampling in order to waste less points.

Problem: if the time-step is too small and we don't use enough Monte Carlo steps, we have bad data.

Reason: the walker remains near its starting point and will not cover completely the integration space.

A further improvement would be to implement the importance sampling, as explained in the previous section.

The only thing we have to care about is the amount of the time-step. READ THE SLIDE.

Idea: implement importance sampling in order to waste less points.

Problem: if the time-step is too small and we don't use enough Monte Carlo steps, we have bad data.

Reason: the walker remains near its starting point and will not cover completely the integration space.

Solution:

A further improvement would be to implement the importance sampling, as explained in the previous section.

The only thing we have to care about is the amount of the time-step. READ THE SLIDE.

Idea: implement importance sampling in order to waste less points.

Problem: if the time-step is too small and we don't use enough Monte Carlo steps, we have bad data.

Reason: the walker remains near its starting point and will not cover completely the integration space.

Solution:

· For a given time-step, increase the number of Monte Carlo cycles until the acceptance ratio is slightly below 100%.

A further improvement would be to implement the importance sampling, as explained in the previous section.

The only thing we have to care about is the amount of the time-step. READ THE SLIDE.

Idea: implement importance sampling in order to waste less points.

Problem: if the time-step is too small and we don't use enough Monte Carlo steps, we have bad data.


Reason: the walker remains near its starting point and will not cover completely the integration space.

Solution:


- · For a given time-step, increase the number of Monte Carlo cycles until the acceptance ratio is slightly below 100%.
- For a given number of Monte Carlo cycles, increase the time-step until the acceptance ratio is slightly below 100%.

A further improvement would be to implement the importance sampling, as explained in the previous section.


The only thing we have to care about is the amount of the time-step. READ THE SLIDE.




The variational energy versus the variational parameters α and β . The settings used are: importance sampling with $\Delta t=0.001$, Jastrow factor, parallelization (8 threads), 20 variations of α and β with step 0.01, 2 × 10⁵ Monte Carlo steps. Acceptance ratio is about 99.999 %.



The variational energy versus the variational parameters α and β . The settings used are: importance sampling with $\Delta t=0.01$, Jastrow factor, parallelization (8 threads), 20 variations of α and β with step 0.01, 2 × 10⁵ Monte Carlo steps. Acceptance ratio is about 99.999%.



The variational energy versus the variational parameters α and β . The settings used are: importance sampling with $\Delta t=0.1$, Jastrow factor, parallelization (8 threads), 20 variations of α and β with step 0.01, 2 × 10⁵ Monte Carlo steps. Acceptance ratio is about 99.793 %.



THE TRIAL WAVE-FUNCTION

The trial wave-function is like the one we used for 2 electrons, but this time is more general.

.

Now, we can extend the previous reasoning to the 6-electrons case, trying to discuss it in the most possible general way.

Recall that, for 2-electrons, the wave-function had this form. That is, it was the product among the single-particle wave-functions and a repulsion factor called the Jastrow factor.

THE TRIAL WAVE-FUNCTION

The trial wave-function is like the one we used for 2 electrons, but this time is more general.

For 2 electrons, it was

.

Now, we can extend the previous reasoning to the 6-electrons case, trying to discuss it in the most possible general way.

Recall that, for 2-electrons, the wave-function had this form. That is, it was the product among the single-particle wave-functions and a repulsion factor called the Jastrow factor.

The trial wave-function is like the one we used for 2 electrons, but this time is more general.

For 2 electrons, it was

$$\psi_T(\vec{r}_1, \vec{r}_2) = \phi(\vec{r}_1)\phi(\vec{r}_2) \exp\left(\frac{ar_{12}}{1 + \beta r_{12}}\right)$$
(19)

.

Now, we can extend the previous reasoning to the 6-electrons case, trying to discuss it in the most possible general way.

Recall that, for 2-electrons, the wave-function had this form. That is, it was the product among the single-particle wave-functions and a repulsion factor called the Jastrow factor.

The trial wave-function is like the one we used for 2 electrons, but this time is more general.

For 2 electrons, it was

$$\psi_T(\vec{r}_1, \vec{r}_2) = \phi(\vec{r}_1)\phi(\vec{r}_2) \exp\left(\frac{ar_{12}}{1 + \beta r_{12}}\right)$$
 (19)

where ϕ is the single-particle spatial wave-function for $(n_x,n_y)=(0,0)$, that is equal for both electron 1 and electron 2, and r_{12} is the inter-particle distance.

Now, we can extend the previous reasoning to the 6-electrons case, trying to discuss it in the most possible general way.

Recall that, for 2-electrons, the wave-function had this form. That is, it was the product among the single-particle wave-functions and a repulsion factor called the Jastrow factor.

For N electrons, the generalization is straightforward:

For N electrons, the generalization is straightforward:

$$\psi_T(\vec{r}_1, \dots, \vec{r}_N) = |S| \prod_{i < j}^N \exp\left(\frac{ar_{ij}}{1 + \beta r_{ij}}\right) \tag{20}$$

For N electrons, the generalization is straightforward:

$$\psi_T(\vec{r}_1, \dots, \vec{r}_N) = |S| \prod_{i < j}^N \exp\left(\frac{ar_{ij}}{1 + \beta r_{ij}}\right)$$
(20)


where |S| is the Slater determinant.

For N electrons, the generalization is straightforward:

$$\psi_T(\vec{r}_1, \dots, \vec{r}_N) = |S| \prod_{i < j}^N \exp\left(\frac{ar_{ij}}{1 + \beta r_{ij}}\right)$$
 (20)

where |S| is the Slater determinant.


$$|S| = \begin{vmatrix} \phi_1(\vec{r}_1) & \phi_2(\vec{r}_1) & \dots & \phi_N(\vec{r}_1) \\ \phi_1(\vec{r}_2) & \phi_2(\vec{r}_2) & \dots & \phi_N(\vec{r}_1) \\ \vdots & & & \vdots \\ \phi_1(\vec{r}_N) & \phi_2(\vec{r}_N) & \dots & \phi_N(\vec{r}_N) \end{vmatrix}$$
(21)



Smart thing:

Now, let's take a look at the configuration of the system. You see that we are free to label the particles in whatever way we want; for example, we can say that (INDICATE ALL SPIN UP) this is particle 1, this is particle 2 and this is particle 3, and the others are numbered accordingly. If we do that, we can split the Slater determinant into two smaller determinants; one for spin-up particles, and one for spin-down particles.

SHOW NEXT SLIDE WITHOUT COMMENTS.



Smart thing: for spin-independent Hamiltonians, the Slater determinant can be split in a product of two Slater determinants, one for the single-particle orbitals with spin up and the other for single-particle orbitals with spin down.

Now, let's take a look at the configuration of the system. You see that we are free to label the particles in whatever way we want; for example, we can say that (INDICATE ALL SPIN UP) this is particle 1, this is particle 2 and this is particle 3, and the others are numbered accordingly. If we do that, we can split the Slater determinant into two smaller determinants; one for spin-up particles, and one for spin-down particles.

SHOW NEXT SLIDE WITHOUT COMMENTS.

We can arbitrarily choose that the first N/2 particles are spin-up and the other half are spin-down.

We can arbitrarily choose that the first N/2 particles are spin-up and the other half are spin-down. This way, our trial wave-function can be written as

We can arbitrarily choose that the first N/2 particles are spin-up and the other half are spin-down. This way, our trial wave-function can be written as

$$\psi_T(\vec{r}_1, \dots, \vec{r}_N) = |S^{\uparrow}||S^{\downarrow}|J, \tag{22}$$

We can arbitrarily choose that the first N/2 particles are spin-up and the other half are spin-down. This way, our trial wave-function can be written as

$$\psi_T(\vec{r}_1, \dots, \vec{r}_N) = |S^{\uparrow}||S^{\downarrow}|J, \tag{22}$$

where (and similarly for $|S^{\downarrow}|$)

We can arbitrarily choose that the first N/2 particles are spin-up and the other half are spin-down. This way, our trial wave-function can be written as

$$\psi_T(\vec{r}_1, \dots, \vec{r}_N) = |S^{\uparrow}||S^{\downarrow}|J, \tag{22}$$

where (and similarly for $|S^{\downarrow}|$)

$$S^{\uparrow} = \begin{vmatrix} \phi_1(\vec{r}_1) & \phi_2(\vec{r}_1) & \dots & \phi_{N/2}(\vec{r}_1) \\ \phi_1(\vec{r}_2) & \phi_2(\vec{r}_2) & \dots & \phi_{N/2}(\vec{r}_1) \\ \vdots & & & \vdots \\ \phi_1(\vec{r}_{N/2}) & \phi_2(\vec{r}_{N/2}) & \dots & \phi_{N/2}(\vec{r}_{N/2}) \end{vmatrix}$$
(23)

We can arbitrarily choose that the first N/2 particles are spin-up and the other half are spin-down. This way, our trial wave-function can be written as


$$\psi_T(\vec{r}_1, \dots, \vec{r}_N) = |S^{\uparrow}||S^{\downarrow}|J, \tag{22}$$

where (and similarly for $|S^{\downarrow}|$)

$$S^{\uparrow} = \begin{vmatrix} \phi_1(\vec{r}_1) & \phi_2(\vec{r}_1) & \dots & \phi_{N/2}(\vec{r}_1) \\ \phi_1(\vec{r}_2) & \phi_2(\vec{r}_2) & \dots & \phi_{N/2}(\vec{r}_1) \\ \vdots & & & \vdots \\ \phi_1(\vec{r}_{N/2}) & \phi_2(\vec{r}_{N/2}) & \dots & \phi_{N/2}(\vec{r}_{N/2}) \end{vmatrix}$$
(23)

and J is the Jastrow factor.

 $\omega = 1$



The variational energy versus the variational parameters α and β . The settings used are: importance sampling with $\Delta t=0.1$, Jastrow factor, parallelization (8 threads), 10 variations of α and β with step 0.1, 2×10^5 Monte Carlo steps. $\omega=1.00$.

Our result is in very good accordance with the one calculated by DMC, that is 20.1597(2) a.u..

CONCLUSION

· The VMC technique is an easy-to-implement tool that gives an upper bound to the ground state energy of a system.

SUMMARY

JUST READ

- The VMC technique is an easy-to-implement tool that gives an upper bound to the ground state energy of a system.
- · Although is used as a starting point for DMC calculations, if we choose our trial wave-function in a smart way this technique gives an upper bound that is surprisingly compatible with the actual ground-state energy.

SUMMARY

JUST READ

- The VMC technique is an easy-to-implement tool that gives an upper bound to the ground state energy of a system.
- · Although is used as a starting point for DMC calculations, if we choose our trial wave-function in a smart way this technique gives an upper bound that is surprisingly compatible with the actual ground-state energy.
- \cdot For N interacting electrons in an attractive potential, a good approximation of the actual wave-function is

$$\psi_T(\vec{r}_1,\ldots,\vec{r}_N) = |S^\uparrow||S^\downarrow|J$$

SUMMARY

JUST READ

- The VMC technique is an easy-to-implement tool that gives an upper bound to the ground state energy of a system.
- · Although is used as a starting point for DMC calculations, if we choose our trial wave-function in a smart way this technique gives an upper bound that is surprisingly compatible with the actual ground-state energy.
- \cdot For N interacting electrons in an attractive potential, a good approximation of the actual wave-function is

$$\psi_T(\vec{r}_1,\ldots,\vec{r}_N) = |S^{\uparrow}||S^{\downarrow}|J$$

· For a quantum dot, the calculations can be further simplified by analytical means.

- The VMC technique is an easy-to-implement tool that gives an upper bound to the ground state energy of a system.
- · Although is used as a starting point for DMC calculations, if we choose our trial wave-function in a smart way this technique gives an upper bound that is surprisingly compatible with the actual ground-state energy.
- \cdot For N interacting electrons in an attractive potential, a good approximation of the actual wave-function is

$$\psi_T(\vec{r}_1,\ldots,\vec{r}_N) = |S^\uparrow||S^\downarrow|J$$

- · For a quantum dot, the calculations can be further simplified by analytical means.
- · In general, such a simplification is not possible; what one does is to optimize the code and to parallelize it as much as possible via OpenMP/MPI and possibly GPU parallelization.

- The VMC technique is an easy-to-implement tool that gives an upper bound to the ground state energy of a system.
- · Although is used as a starting point for DMC calculations, if we choose our trial wave-function in a smart way this technique gives an upper bound that is surprisingly compatible with the actual ground-state energy.
- \cdot For N interacting electrons in an attractive potential, a good approximation of the actual wave-function is

$$\psi_T(\vec{r}_1,\ldots,\vec{r}_N) = |S^{\uparrow}||S^{\downarrow}|J$$

- · For a quantum dot, the calculations can be further simplified by analytical means.
- · In general, such a simplification is not possible; what one does is to optimize the code and to parallelize it as much as possible via OpenMP/MPI and possibly GPU parallelization.
- · Thanks for your attention!

