Malware Behavior

Malware Analysis
CSCI 4976 - Fall 2015
Branden Clark



```
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], ebx
                jnz     short loc_313066
                mov     eax, [ebp+var_70]
                cmp     eax, [ebp+var_84]
                jb      short loc_313066
                sub     eax, [ebp+var_84]
                push    esi
                push    esi
                push    eax
                push    edi
                mov     [ebp+arg_0], eax
                call    sub_31486A
                test    eax, eax
                jz      short loc_31306D
                push    esi
                lea     eax, [ebp+arg_0]
                push    eax
                mov     esi, 1D0h
                push    esi
                push    [ebp+arg_4]
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], esi
                jz      short loc_31308F

loc_313066:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+55
                push    0Dh
                call    sub_31411B

loc_31306D:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+49
                call    sub_3140F3
                test    eax, eax
                jg      short loc_31307D
                call    sub_3140F3
                jmp     short loc_31308C
; ---------------------------------------------------------------------------

loc_31307D:                             ; CODE XREF: sub_312FD8
                call    sub_3140F3
                and     eax, 0FFFFh
                or      eax, 80070000h

loc_31308C:                             ; CODE XREF: sub_312FD8
                mov     [ebp+var_4], eax
```

Overview

- Section 1 review & Project 1
- Downloaders and Launchers
- Backdoors
- Credential Stealers
- Persistence Mechanisms
- Privilege Escalation



```
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], ebx
                jnz     short loc_313066
                mov     eax, [ebp+var_70]
                cmp     eax, [ebp+var_84]
                jb      short loc_313066
                sub     eax, [ebp+var_84]
                push    esi
                push    esi
                push    eax
                push    edi
                mov     [ebp+arg_0], eax
                call    sub_31486A
                test    eax, eax
                jz      short loc_31306D
                push    esi
                lea     eax, [ebp+arg_0]
                push    eax
                mov     esi, 1D0h
                push    esi
                push    [ebp+arg_4]
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], esi
                jz      short loc_31308F

loc_313066:                                     ; CODE XREF: sub_312FD8
                                                ; sub_312FD8+55
                push    0Dh
                call    sub_31411B

loc_31306D:                                     ; CODE XREF: sub_312FD8
                                                ; sub_312FD8+49
                call    sub_3140F3
                test    eax, eax
                jg      short loc_31307D
                call    sub_3140F3
                jmp     short loc_31308C
; ---------------------------------------------------------------------------

loc_31307D:                                     ; CODE XREF: sub_312FD8
                call    sub_3140F3
                and     eax, 0FFFFh
                or      eax, 80070000h

loc_31308C:                                     ; CODE XREF: sub_312FD8
                mov     [ebp+var_4], eax
```

What we’ve learned so far…

- Basic Analysis
  - Quickly glean information from the sample(s)
  - Help guide and focus Advanced Analysis



```
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], ebx
                jz      short loc_313066
                mov     eax, [ebp+var_70]
                cmp     eax, [ebp+var_84]
                jb      short loc_313066
                sub     eax, [ebp+var_84]
                push    esi
                push    esi
                push    eax
                push    edi
                mov     [ebp+arg_0], eax
                call    sub_31486A
                test    eax, eax
                jz      short loc_31306D
                push    esi
                lea     eax, [ebp+arg_0]
                push    eax
                mov     esi, 1D0h
                push    esi
                push    [ebp+arg_4]
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], esi
                jz      short loc_31308F

loc_313066:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+55
                push    0Dh
                call    sub_31411B

loc_31306D:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+49
                call    sub_3140F3
                test    eax, eax
                jg      short loc_31307D
                call    sub_3140F3
                jmp     short loc_31308C
; ---------------------------------------------------------------

loc_31307D:                             ; CODE XREF: sub_312FD8
                call    sub_3140F3
                and     eax, 0FFFFh
                or      eax, 80070000h

loc_31308C:                             ; CODE XREF: sub_312FD8
                mov     [ebp+var_4], eax
```

What we’ve learned so far…

- Advanced Analysis - Static
  - Used to see what is going on
  - Confirm suspicions aroused during basic analysis
  - Identify functionality
- Advanced Analysis - Dynamic
  - Control the program
    - Take new code paths
    - Change data
  - See what is really going on
    - Encoded data?
    - Polymorphic code?



```
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], ebx
                [illegible] short loc_313066
                mov     eax, [ebp+var_70]
                cmp     eax, [ebp+var_84]
                jb      short loc_313066
                sub     eax, [ebp+var_84]
                push    esi
                push    esi
                push    eax
                push    edi
                mov     [ebp+arg_0], eax
                call    sub_31486A
                test    eax, eax
                jz      short loc_31306D
                push    esi
                lea     eax, [ebp+arg_0]
                push    eax
                mov     esi, 1D0h
                push    esi
                push    [ebp+arg_4]
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], esi
                jz      short loc_31308F

loc_313066:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+55
                push    0Dh
                call    sub_31411B

loc_31306D:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+49
                call    sub_3140F3
                test    eax, eax
                jg      short loc_31307D
                call    sub_3140F3
                jmp     short loc_31308C
; ---------------------------------------------------------------

loc_31307D:                             ; CODE XREF: sub_312FD8
                call    sub_3140F3
                and     eax, 0FFFFh
                or      eax, 80070000h

loc_31308C:                             ; CODE XREF: sub_312FD8
                mov     [ebp+var_4], eax
```

What we’ve learned so far…

- Windows API and systems
  - How does malware interact with Windows?
  - How does Windows make malware author’s lives easier?
  - How does it make their lives harder?



```
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], ebx
                jz      short loc_313066
                mov     eax, [ebp+var_70]
                cmp     eax, [ebp+var_84]
                jb      short loc_313066
                sub     eax, [ebp+var_84]
                push    esi
                push    esi
                push    eax
                push    edi
                mov     [ebp+arg_0], eax
                call    sub_31486A
                test    eax, eax
                jz      short loc_31306D
                push    esi
                lea     eax, [ebp+arg_0]
                push    eax
                mov     esi, 150h
                push    esi
                push    [ebp+arg_4]
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], esi
                jz      short loc_31308F

loc_313066:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+55
                push    0Dh
                call    sub_31411B

loc_31306D:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+49
                call    sub_3140F3
                test    eax, eax
                jg      short loc_31307D
                call    sub_3140F3
                jmp     short loc_31308C
; ---------------------------------------------------------------

loc_31307D:                             ; CODE XREF: sub_312FD8
                call    sub_3140F3
                and     eax, 0FFFFh
                or      eax, 80070000h

loc_31308C:                             ; CODE XREF: sub_312FD8
                mov     [ebp+var_4], eax
```

Apply that knowledge!

- Project 1
  - Due TWO weeks from today (10/13 11:59PM)
  - Like a larger lab, but without questions
  - You will write a report on the sample
    - Analysis, things found, difficulties, conclusion, etc
    - You will be given an official guide and an example report



```
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], ebx
                jnz     short loc_313066
                mov     eax, [ebp+var_70]
                cmp     eax, [ebp+var_84]
                jb      short loc_313066
                sub     eax, [ebp+var_84]
                push    esi
                push    esi
                push    eax
                push    edi
                mov     [ebp+arg_0], eax
                call    sub_31486A
                test    eax, eax
                [illegible] short loc_31306D
                push    edi
                lea     eax, [ebp+arg_0]
                push    eax
                mov     esi, 100h
                push    esi
                push    [ebp+arg_4]
                push    edi
                call    sub_314623
                test    eax, eax
                [illegible] [ebp+arg_0], esi
                jz      short loc_31308F

loc_313066:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+55
                [illegible]
                call    sub_31411B

loc_31306D:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+49
                call    sub_3140F3
                test    eax, eax
                jg      short loc_31307D
                call    sub_3140F3
                jmp     short loc_31308C
; ---------------------------------------------------------------------------

loc_31307D:                             ; CODE XREF: sub_312FD8
                call    sub_3140F3
                and     eax, 0FFFFh
                or      eax, 80070000h

loc_31308C:                             ; CODE XREF: sub_312FD8
                mov     [ebp+var_4], eax
```

Overview

- Section 1 review & Project 1
- Downloaders and Launchers
- Backdoors
- Credential Stealers
- Persistence Mechanisms
- Privilege Escalation



```
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], ebx
                jnz     short loc_313066
                mov     eax, [ebp+var_70]
                cmp     eax, [ebp+var_84]
                jb      short loc_313066
                sub     eax, [ebp+var_84]
                push    esi
                push    esi
                push    eax
                push    edi
                mov     [ebp+arg_0], eax
                call    sub_31486A
                test    eax, eax
                jz      short loc_31306D
                push    esi
                lea     eax, [ebp+arg_0]
                push    eax
                mov     esi, 1D0h
                push    esi
                push    [ebp+arg_4]
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], esi
                jz      short loc_31308F

loc_313066:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+55
                push    0Dh
                call    sub_31411B

loc_31306D:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+49
                call    sub_3140F3
                test    eax, eax
                jg      short loc_31307D
                call    sub_3140F3
                jmp     short loc_31308C
; ---------------------------------------------------------------------

loc_31307D:                             ; CODE XREF: sub_312FD8
                call    sub_3140F3
                and     eax, 0FFFFh
                or      eax, 80070000h

loc_31308C:                             ; CODE XREF: sub_312FD8
                mov     [ebp+var_4], eax
```

Downloaders and Launchers

- Names are pretty self explanatory
  - Downloaders
    - Downloads a (probably) more complex sample and installs/runs it
  - Launchers
    - Unpacks/Decrypts/Drops a (probably) more complex sample and installs/runs it

- PMA Lab11-01.exe



```
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], ebx
                jz      short loc_313066
                mov     eax, [ebp+var_70]
                cmp     eax, [ebp+var_84]
                jb      short loc_313066
                sub     eax, [ebp+var_84]
                push    esi
                push    esi
                push    eax
                push    edi
                mov     [ebp+arg_0], eax
                call    sub_31486A
                test    eax, eax
                jz      short loc_31306D
                push    esi
                lea     eax, [ebp+arg_0]
                push    eax
                [illegible]
                push    esi
                push    [ebp+arg_4]
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], esi
                jz      short loc_31308F

loc_313066:                             ; CODE XREF: sub_312FD
                                        ; sub_312FD8+55
                push    0Dh
                call    sub_31411B

loc_31306D:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+49
                call    sub_3140F3
                test    eax, eax
                jg      short loc_31307D
                call    sub_3140F3
                jmp     short loc_31308C
; ---------------------------------------------------------------

loc_31307D:                             ; CODE XREF: sub_312FD8
                call    sub_3140F3
                and     eax, 0FFFFh
                or      eax, 80070000h

loc_31308C:                             ; CODE XREF: sub_312FD8
                mov     [ebp+var_4], eax
```

Overview

- Section 1 review & Project 1
- Downloaders and Launchers
- Backdoors
- Credential Stealers
- Persistence Mechanisms
- Privilege Escalation
- User-mode rootkits

```
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], ebx
                jnz     short loc_313066
                mov     eax, [ebp+var_70]
                cmp     eax, [ebp+var_84]
                jb      short loc_313066
                sub     eax, [ebp+var_84]
                push    esi
                push    esi
                push    eax
                push    edi
                mov     [ebp+arg_0], eax
                call    sub_31486A
                test    eax, eax
                jz      short loc_31306D
                push    esi
                lea     eax, [ebp+arg_0]
                push    eax
                mov     esi, 1D0h
                push    esi
                push    [ebp+arg_4]
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], esi
                jz      short loc_31308F

loc_313066:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+55
                push    0Dh
                call    sub_31411B

loc_31306D:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+49
                call    sub_3140F3
                test    eax, eax
                jg      short loc_31307D
                call    sub_3140F3
                jmp     short loc_31308C
; ---------------------------------------------------------------------------

loc_31307D:                             ; CODE XREF: sub_312FD8
                call    sub_3140F3
                and     eax, 0FFFFh
                or      eax, 80070000h

loc_31308C:                             ; CODE XREF: sub_312FD8
                mov     [ebp+var_4], eax
```

Backdoors

- Remote access to or control of a system
  - RAT - Remote Access Trojan
- We've seen a couple of these
- Class lab lab03b.malware
  - APT1 SEASALT



```
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], ebx
                jnz     short loc_313066
                mov     eax, [ebp+var_70]
                cmp     eax, [ebp+var_84]
                jb      short loc_313066
                sub     eax, [ebp+var_84]
                push    esi
                push    esi
                push    eax
                push    edi
                mov     [ebp+arg_0], eax
                call    sub_31486A
                test    eax, eax
                jz      short loc_31306D
                push    esi
                lea     eax, [ebp+arg_0]
                push    eax
                mov     esi, 1D0h
                push    esi
                push    [ebp+arg_4]
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], esi
                jz      short loc_31308F

loc_313066:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+55
                push    0Dh
                call    sub_31411B

loc_31306D:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+49
                call    sub_3140F3
                test    eax, eax
                jg      short loc_31307D
                call    sub_3140F3
                jmp     short loc_31308C
; ---------------------------------------------------------------

loc_31307D:                             ; CODE XREF: sub_312FD8
                call    sub_3140F3
                and     eax, 0FFFFh
                or      eax, 80070000h

loc_31308C:                             ; CODE XREF: sub_312FD8
                mov     [ebp+var_4], eax
```

Overview

- Section 1 review & Project 1
- Downloaders and Launchers
- Backdoors
- Credential Stealers
- Persistence Mechanisms
- Privilege Escalation



```
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], ebx
                jnz     short loc_313066
                mov     eax, [ebp+var_70]
                cmp     eax, [ebp+var_84]
                jb      short loc_313066
                sub     eax, [ebp+var_84]
                push    esi
                push    esi
                push    eax
                push    edi
                mov     [ebp+arg_0], eax
                call    sub_31486A
                test    eax, eax
                jz      short loc_31306D
                push    esi
                lea     eax, [ebp+arg_0]
                push    eax
                mov     esi, 1D0h
                push    esi
                push    [ebp+arg_4]
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], esi
                jz      short loc_31308F

loc_313066:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+55
                push    0Dh
                call    sub_31411B

loc_31306D:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+49
                call    sub_3140F3
                test    eax, eax
                jg      short loc_31307D
                call    sub_3140F3
                jmp     short loc_31308C
; ---------------------------------------------------------------

loc_31307D:                             ; CODE XREF: sub_312FD8
                call    sub_3140F3
                and     eax, 0FFFFh
                or      eax, 80070000h

loc_31308C:                             ; CODE XREF: sub_312FD8
                mov     [ebp+var_4], eax
```

Credential Stealers



- GINA - Graphical Identification and Authentication (Win XP & earlier)
  - A framework for getting all authentication attempts
    - Similar to the networking stack, several modules get the packet and can handle accordingly
    - Microsoft - It has uses, we promise
      - side note: Lenovo rootkit
- Credential Provider (Now used)
  - Basically the same thing
  - Great write-up by Tyler Wrightson

Credential Stealers - Background

- Windows Authentication (Long ago)
  - Type your password EVERY time you access a resource
  - Quickly became annoying
  - The solution?



```
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], ebx
                jz      short loc_313066
                mov     eax, [ebp+var_70]
                cmp     eax, [ebp+var_84]
                jb      short loc_313066
                sub     eax, [ebp+var_84]
                push    esi
                push    esi
                push    eax
                push    edi
                mov     [ebp+arg_0], eax
                call    sub_31486A
                test    eax, eax
                jz      short loc_31306D
                push    esi
                lea     eax, [ebp+arg_0]
                push    eax
                mov     esi, 1D0h
                push    esi
                push    [ebp+arg_4]
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], esi
                jz      short loc_31308F

loc_313066:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+55
                push    0Dh
                call    sub_31411B

loc_31306D:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+49
                call    sub_3140F3
                test    eax, eax
                jg      short loc_31307D
                call    sub_3140F3
                jmp     short loc_31308C
; ---------------------------------------------------------------------------

loc_31307D:                             ; CODE XREF: sub_312FD8
                call    sub_3140F3
                and     eax, 0FFFFh
                or      eax, 80070000h

loc_31308C:                             ; CODE XREF: sub_312FD8
                mov     [ebp+var_4], eax
```

Credential Stealers - Background

- Windows Authentication
  - SSO - Single Sign-On
  - Type your password ONCE, Windows keeps the hash around
  - When Windows needs to access a resource it just passes the hash around

Problem? So can you!
(Pass-the-Hash Attack)



```
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], ebx
                jz      short loc_313066
                mov     eax, [ebp+var_70]
                cmp     eax, [ebp+var_84]
                jb      short loc_313066
                sub     eax, [ebp+var_84]
                push    esi
                push    esi
                push    eax
                push    edi
                mov     [ebp+arg_0], eax
                call    sub_31486A
                test    eax, eax
                jz      short loc_31306D
                push    esi
                lea     eax, [ebp+arg_0]
                push    eax
                mov     esi, 1D0h
                push    esi
                push    [ebp+arg_4]
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], esi
                jz      short loc_31308F

loc_313066:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+55
                push    0Dh
                call    sub_31411B

loc_31306D:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+49
                call    sub_3140F3
                test    eax, eax
                jg      short loc_31307D
                call    sub_3140F3
                jmp     short loc_31308C
; ---------------------------------------------------------------------------

loc_31307D:                             ; CODE XREF: sub_312FD8
                call    sub_3140F3
                and     eax, 0FFFFh
                or      eax, 80070000h

loc_31308C:                             ; CODE XREF: sub_312FD8
                mov     [ebp+var_4], eax
```

Credential Stealers - Background

- Windows Authentication
  - SSO - Single Sign-On
  - Type your password ONCE, Windows keeps the hash around
  - When Windows needs to access a resource it just passes the hash around

Problem? So can you!
(Pass-the-Hash Attack)
What do we do now?



```
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], ebx
                jz      short loc_313066
                mov     eax, [ebp+var_70]
                cmp     eax, [ebp+var_84]
                jb      short loc_313066
                sub     eax, [ebp+var_84]
                push    esi
                push    esi
                push    eax
                push    edi
                mov     [ebp+arg_0], eax
                call    sub_31486A
                test    eax, eax
                jz      short loc_31306D
                push    esi
                lea     eax, [ebp+arg_0]
                push    eax
                mov     esi, 1D0h
                push    esi
                push    [ebp+arg_4]
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], esi
                jz      short loc_31308F

loc_313066:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+55
                push    0Dh
                call    sub_31411B

loc_31306D:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+49
                call    sub_3140F3
                test    eax, eax
                jg      short loc_31307D
                call    sub_3140F3
                jmp     short loc_31308C
; ---------------------------------------------------------------------------

loc_31307D:                             ; CODE XREF: sub_312FD8
                call    sub_3140F3
                and     eax, 0FFFFh
                or      eax, 80070000h

loc_31308C:                             ; CODE XREF: sub_312FD8
                mov     [ebp+var_4], eax
```

Credential Stealers

- Windows Authentication
  - SSO - Single Sign-On
  - Type your password ONCE, Windows keeps encrypted password around
  - No more passing hashes, since we have the password now!
    - wait a minute…



```
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], ebx
                jnz     short loc_313066
                mov     eax, [ebp+var_70]
                cmp     eax, [ebp+var_84]
                jb      short loc_313066
                sub     eax, [ebp+var_84]
                push    esi
                push    esi
                push    eax
                push    edi
                mov     [ebp+arg_0], eax
                call    sub_31486A
                test    eax, eax
                jz      short loc_31306D
                push    esi
                lea     eax, [ebp+arg_0]
                push    eax
                mov     esi, 1D0h
                push    esi
                push    [ebp+arg_4]
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], esi
                jz      short loc_31308F

loc_313066:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+55
                push    0Dh
                call    sub_31411B

loc_31306D:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+49
                call    sub_3140F3
                test    eax, eax
                jg      short loc_31307D
                call    sub_3140F3
                jmp     short loc_31308C
; ---------------------------------------------------------------

loc_31307D:                             ; CODE XREF: sub_312FD8
                call    sub_3140F3
                and     eax, 0FFFFh
                or      eax, 80070000h

loc_31308C:                             ; CODE XREF: sub_312FD8
                mov     [ebp+var_4], eax
```

Credential Stealers

- Windows Authentication
  - SSO - Single Sign-On
  - Type your password ONCE, Windows keeps encrypted password around
  - No more passing hashes, since we have the password now!
    - wait a minute…

Ciphertext is in memory
Encryption keys are in memory



```
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], ebx
                jnz     short loc_313066
                mov     eax, [ebp+var_70]
                cmp     eax, [ebp+var_84]
                jb      short loc_313066
                sub     eax, [ebp+var_84]
                push    esi
                push    esi
                push    eax
                push    edi
                mov     [ebp+arg_0], eax
                call    sub_31486A
                test    eax, eax
                jz      short loc_31306D
                push    esi
                lea     eax, [ebp+arg_0]
                push    eax
                mov     esi, 1D0h
                push    esi
                push    [ebp+arg_4]
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], esi
                jz      short loc_31308F

loc_313066:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+55
                push    0Dh
                call    sub_31411B

loc_31306D:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+49
                call    sub_3140F3
                test    eax, eax
                jz      short loc_31307D
                call    sub_3140F3
                jmp     short loc_31308C
; ---------------------------------------------------------------

loc_31307D:                             ; CODE XREF: sub_312FD8
                call    sub_3140F3
                and     eax, 0FFFFh
                or      eax, 80070000h

loc_31308C:                             ; CODE XREF: sub_312FD8
                mov     [ebp+var_4], eax
```

Credential Stealers

- Windows Authentication
  - SSO - Single Sign-On
  - Type your password ONCE, Windows keeps encrypted password around
  - No more passing hashes, since we have the password now!
    - wait a minute…

Open Sesame…or something



```
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], ebx
                jnz     short loc_313066
                mov     eax, [ebp+var_70]
                cmp     eax, [ebp+var_84]
                jb      short loc_313066
                sub     eax, [ebp+var_84]
                push    esi
                push    esi
                push    eax
                push    edi
                mov     [ebp+arg_0], eax
                call    sub_31486A
                test    eax, eax
                jz      short loc_31306D
                push    esi
                [illegible] eax, [ebp+arg_0]
                mov     esi, 1D0h
                push    esi
                push    [ebp+arg_4]
                push    edi
                call    [illegible]23
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], esi
                jz      short loc_31308F

loc_313066:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+55
                push    0Dh
                call    sub_31411B

loc_31306D:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+49
                call    sub_3140F3
                test    eax, eax
                jg      short loc_31307D
                call    sub_3140F3
                jmp     short loc_31308C
; ---------------------------------------------------------------

loc_31307D:                             ; CODE XREF: sub_312FD8
                call    sub_3140F3
                and     eax, 0FFFFh
                or      eax, 80070000h

loc_31308C:                             ; CODE XREF: sub_312FD8
                mov     [ebp+var_4], eax
```

Credential Stealers

Amplia Security - Windows Credentials Editor



```
C:\Users\IEUser\Desktop>wce.exe -w
WCE v1.42beta (Windows Credentials Editor) - (c) 2010-2013 Amplia Security - by
Hernan Ochoa (hernan@ampliasecurity.com)
Use -h for help.


User\MALWARE:infected
MALWARE$\WORKGROUP:
```

Credential Stealers

mimikatz



```
mimikatz # sekurlsa::logonpasswords

Authentication Id : 0 ; 97373 (00000000:00017c5d)
Session           : Interactive from 1
User Name         : User
Domain            : MALWARE
Logon Server      : MALWARE
Logon Time        : 9/25/2015 6:59:47 PM
SID               : S-1-5-21-3463664321-2923530833-3546627382-1000
        msv :
         [00010000] CredentialKeys
         * NTLM     : 4eb0bb4f55b0b9546e70a1c51ed2d5d7
         * SHA1     : c44ee7da4bafd211025586a158d1b4f3dce851a7
         [00000003] Primary
         * Username : User
         * Domain   : MALWARE
         * NTLM     : 4eb0bb4f55b0b9546e70a1c51ed2d5d7
         * SHA1     : c44ee7da4bafd211025586a158d1b4f3dce851a7
        tspkg :
        wdigest :
         * Username : User
         * Domain   : MALWARE
         * Password : infected
        kerberos :
         * Username : User
         * Domain   : MALWARE
         * Password : (null)
        ssp :
        credman :
         [00000000]
         * Username : IE8Win7\IEUser
         * Domain   : IE8Win7\IEUser
         * Password : Passw0rd!
```

Overview

- Section 1 review & Project 1
- Downloaders and Launchers
- Backdoors
- Credential Stealers
- Persistence Mechanisms
- Privilege Escalation

```
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], ebx
                jnz     short loc_313066
                mov     eax, [ebp+var_70]
                cmp     eax, [ebp+var_84]
                jb      short loc_313066
                sub     eax, [ebp+var_84]
                push    esi
                push    esi
                push    eax
                push    edi
                mov     [ebp+arg_0], eax
                call    sub_31486A
                test    eax, eax
                jz      short loc_31306D
                push    esi
                lea     eax, [ebp+arg_0]
                push    eax
                mov     esi, 1D0h
                push    esi
                push    [ebp+arg_4]
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], esi
                jz      short loc_31308F

loc_313066:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+55
                push    0Dh
                call    sub_31411B

loc_31306D:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+49
                call    sub_3140F3
                test    eax, eax
                jg      short loc_31307D
                call    sub_3140F3
                jmp     short loc_31308C
; ---------------------------------------------------------------

loc_31307D:                             ; CODE XREF: sub_312FD8
                call    sub_3140F3
                and     eax, 0FFFFh
                or      eax, 80070000h

loc_31308C:                             ; CODE XREF: sub_312FD8
                mov     [ebp+var_4], eax
```

Persistence Mechanisms

- Things we’ve seen so far
  - A few registry keys
  - Startup folder
  - BHO - Browser Helper Objects
  - Services



```
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], ebx
                jnz     short loc_313066
                mov     eax, [ebp+var_70]
                cmp     eax, [ebp+var_84]
                jb      short loc_313066
                sub     eax, [ebp+var_84]
                push    esi
                push    esi
                push    eax
                push    edi
                mov     [ebp+arg_0], eax
                call    sub_31486A
                test    eax, eax
                jz      short loc_31306D
                push    esi
                lea     eax, [ebp+arg_0]
                push    eax
                mov     esi, 1D0h
                push    esi
                push    [ebp+arg_4]
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], esi
                jz      short loc_31308F

loc_313066:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+55
                push    0Dh
                call    sub_31411B

loc_31306D:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+49
                call    sub_3140F3
                test    eax, eax
                jg      short loc_31307D
                call    sub_3140F3
                jmp     short loc_31308C
; ---------------------------------------------------------------

loc_31307D:                             ; CODE XREF: sub_312FD8
                call    sub_3140F3
                and     eax, 0FFFFh
                or      eax, 80070000h

loc_31308C:                             ; CODE XREF: sub_312FD8
                mov     [ebp+var_4], eax
```

Persistence Mechanisms

- Things we’ve seen so far
  - A few registry keys
  - Startup folder
  - BHO - Browser Helper Objects
  - Services

Now go run SysInternalsSuite/Autoruns.exe



```
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], ebx
                jnz     short loc_313066
                mov     eax, [ebp+var_70]
                cmp     eax, [ebp+var_84]
                jb      short loc_313066
                sub     eax, [ebp+var_84]
                push    esi
                push    esi
                push    eax
                push    edi
                mov     [ebp+arg_0], eax
                call    sub_31486A
                test    eax, eax
                jz      short loc_31306D
                push    esi
                lea     eax, [ebp+arg_0]
                push    eax
                mov     esi, 1D0h
                push    esi
                push    [ebp+arg_4]
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], esi
                jz      short loc_31308F

loc_31306                                  ; CODE XREF: sub_312FD
                                           ; sub_312FD8+55
                push    0Dh
                call    sub_31411B

loc_31306D:                                ; CODE XREF: sub_312FD8
                                           ; sub_312FD8+49
                call    sub_3140F3
                test    eax, eax
                jg      short loc_31307D
                call    sub_3140F3
                jmp     short loc_31308C
; ---------------------------------------------------------------

loc_31307D:                                ; CODE XREF: sub_312FD8
                call    sub_3140F3
                and     eax, 0FFFFh
                or      eax, 80070000h

loc_31308C:                                ; CODE XREF: sub_312FD8
                mov     [ebp+var_4], eax
```

Persistence Mechanisms

- APPInit_DLLs
  - "...a mechanism that allows an arbitrary list of DLLs to be loaded into each user mode process on the system" - MSDN
- SvcHost DLLs
  - svchost.exe runs legitimate Microsoft services, and use for any other purpose is unsupported.
  - Trojan a legitimate service, now it looks legit!



```
push    edi
call    sub_314623
test    eax, eax
jz      short loc_31306D
cmp     [ebp+arg_0], ebx
jnz     short loc_313066
mov     eax, [ebp+var_70]
cmp     eax, [ebp+var_84]
jb      short loc_313066
sub     eax, [ebp+var_84]
push    esi
push    esi
push    eax
push    edi
mov     [ebp+arg_0], eax
call    sub_31486A
test    eax, eax
push    esi
mov     esi, 1D0h
push    esi
push    [ebp+arg_4]
push    edi
call    sub_314623
test    eax, eax
jz      short loc_31306D
                                ; CODE XREF: sub_312FD8
                                ; sub_312FD8+55
push    0Dh

loc_31306D:                     ; CODE XREF: sub_312FD8
                                ; sub_312FD8+49
call    sub_3140F3
test    eax, eax
jg      short loc_31307D
call    sub_3140F3
jmp     short loc_31308C
; ---------------------------------------------------------------

loc_31307D:                     ; CODE XREF: sub_312FD8
call    sub_3140F3
and     eax, 0FFFFh
or      eax, 80070000h

loc_31308C:                     ; CODE XREF: sub_312FD8
mov     [ebp+var_4], eax
```

Persistence Mechanisms

- DLL Load-Order Hijacking
  - Microsoft's loader looks for DLLs in specific places
  - So stick your own DLL higher in the load-order and give it the same name
    - Problem identified ~15 yrs ago, marked WNF



```
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], ebx
                jnz     short loc_313066
                mov     eax, [ebp+var_70]
                cmp     eax, [ebp+var_84]
                jb      short loc_313066
                sub     eax, [ebp+var_84]
                push    esi
                push    esi
                push    eax
                push    edi
                mov     [ebp+arg_0], eax
                call    sub_31486A
                test    eax, eax
                jz      short loc_31306D
                push    esi
                lea     eax, [ebp+arg_0]
                push    eax
                mov     esi, 1D0h
                push    esi
                push    [ebp+arg_4]
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], esi
                jz      short loc_31308F

loc_313066:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+55
                push    0Dh
                call    sub_31411B

loc_31306D:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+49
                call    sub_3140F3
                test    eax, eax
                jg      short loc_31307D
                call    sub_3140F3
                jmp     short loc_31308C
; ---------------------------------------------------------------------------

loc_31307D:                             ; CODE XREF: sub_312FD8
                call    sub_3140F3
                and     eax, 0FFFFh
                or      eax, 80070000h

loc_31308C:                             ; CODE XREF: sub_312FD8
                mov     [ebp+var_4], eax
```

Overview

- Section 1 review & Project 1
- Downloaders and Launchers
- Backdoors
- Credential Stealers
- Persistence Mechanisms
- Privilege Escalation

```
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], ebx
                jnz     short loc_313066
                mov     eax, [ebp+var_70]
                cmp     eax, [ebp+var_84]
                jb      short loc_313066
                sub     eax, [ebp+var_84]
                push    esi
                push    esi
                push    eax
                push    edi
                mov     [ebp+arg_0], eax
                call    sub_31486A
                test    eax, eax
                jz      short loc_31306D
                push    esi
                lea     eax, [ebp+arg_0]
                push    eax
                mov     esi, 1D0h
                push    esi
                push    [ebp+arg_4]
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], esi
                jz      short loc_31308F

loc_313066:                                     ; CODE XREF: sub_312FD8
                                                ; sub_312FD8+55
                push    0Dh
                call    sub_31411B

loc_31306D:                                     ; CODE XREF: sub_312FD8
                                                ; sub_312FD8+49
                call    sub_3140F3
                test    eax, eax
                jg      short loc_31307D
                call    sub_3140F3
                jmp     short loc_31308C
; ---------------------------------------------------------------------------

loc_31307D:                                     ; CODE XREF: sub_312FD8
                call    sub_3140F3
                and     eax, 0FFFFh
                or      eax, 80070000h

loc_31308C:                                     ; CODE XREF: sub_312FD8
                mov     [ebp+var_4], eax
```

Privilege Escalation

- Some of the previously mentioned techniques work
- So do Windows exploits
  - Why is it this easy

```
meterpreter > getsystem
...got system (via technique 1).
meterpreter > getuid
Server username: NT AUTHORITY\SYSTEM
meterpreter >
```



```
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], ebx
                jnz     short loc_313066
                mov     eax, [ebp+var_70]
                cmp     eax, [ebp+var_84]
                jb      short loc_313066
                sub     eax, [ebp+var_84]
                push    esi
                push    esi
                push    eax
                push    edi
                        [ebp+arg_0], eax
                call    sub_31486A
                test    eax, eax
                jz      short loc_31306D
                push    esi
                lea     eax, [ebp+arg_0]
                push    eax
                mov     esi, 1D0h
                push    esi
                push    [ebp+arg_4]
                push    edi
                call    sub_314623
                test    eax, eax
                        short loc_31306D
                        [ebp+arg_0], esi
                        short loc_31308F
                                        ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+55
                        0Dh
                        sub_31411B

loc_31306D:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+49
                call    sub_3140F3
                test    eax, eax
                jg      short loc_31307D
                call    sub_3140F3
                jmp     short loc_31308C
; ---------------------------------------------------------------

loc_31307D:                             ; CODE XREF: sub_312FD8
                call    sub_3140F3
                and     eax, 0FFFFh
                or      eax, 80070000h

loc_31308C:                             ; CODE XREF: sub_312FD8
                mov     [ebp+var_4], eax
```

Privilege Escalation

- There's a little more to it
  - An Administrator on Windows doesn't have ALL the permissions...



Privilege	Flags
SeBackupPrivilege	Disabled
SeChangeNotifyPrivilege	Default Enabled
SeCreateGlobalPrivilege	Default Enabled
SeCreatePagefilePrivilege	Disabled
SeCreateSymbolicLinkPrivilege	Disabled
SeDebugPrivilege	Disabled
SeImpersonatePrivilege	Default Enabled
SeIncreaseBasePriorityPrivilege	Disabled

  - right away...
    - AdjustTokenPrivileges(...)

```
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], ebx
                jnz     short loc_313066
                mov     eax, [ebp+var_70]
                cmp     eax, [ebp+var_84]
                jb      short loc_313066
                sub     eax, [ebp+var_84]
                push    esi
                push    esi
                push    eax
                push    edi
                mov     [ebp+arg_0], eax
                call    sub_31486A
                test    eax, eax
                jz      short loc_31306D
                push    esi
                lea     eax, [ebp+arg_0]
                push    eax
                mov     esi, 1D0h
                push    esi
                push    [ebp+arg_4]
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], esi
                jz      short loc_31308F

                                        ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+55
                push    0Dh
                call    sub_31411B

loc_31306D:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+49
                call    sub_3140F3
                test    eax, eax
                jg      short loc_31307D
                call    sub_3140F3
                jmp     short loc_31308C
; ---------------------------------------------------------------

loc_31307D:                             ; CODE XREF: sub_312FD8
                call    sub_3140F3
                and     eax, 0FFFFh
                or      eax, 80070000h

loc_31308C:                             ; CODE XREF: sub_312FD8
                mov     [ebp+var_4], eax
```

Review

- Section 1 review & Project 1
- Downloaders and Launchers
- Backdoors
- Credential Stealers
- Persistence Mechanisms
- Privilege Escalation

```
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], ebx
                jnz     short loc_313066
                mov     eax, [ebp+var_70]
                cmp     eax, [ebp+var_84]
                jb      short loc_313066
                sub     eax, [ebp+var_84]
                push    esi
                push    esi
                push    eax
                push    edi
                mov     [ebp+arg_0], eax
                call    sub_31486A
                test    eax, eax
                jz      short loc_31306D
                push    esi
                lea     eax, [ebp+arg_0]
                push    eax
                mov     esi, 1D0h
                push    esi
                push    [ebp+arg_4]
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], esi
                jz      short loc_31308F

loc_313066:                             ; CODE XREF: sub 312FD8
                                        ; sub_312FD8+55
                push    0Dh
                call    sub_31411B

loc_31306D:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+49
                call    sub_3140F3
                test    eax, eax
                jg      short loc_31307D
                call    sub_3140F3
                jmp     short loc_31308C
; ---------------------------------------------------------------

loc_31307D:                             ; CODE XREF: sub_312FD8
                call    sub_3140F3
                and     eax, 0FFFFh
                or      eax, 80070000h

loc_31308C:                             ; CODE XREF: sub_312FD8
                mov     [ebp+var_4], eax
```

Lab on Friday! (10/03)

- Same place
- Same time
- Same idea



```
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], ebx
                jnz     short loc_313066
                mov     eax, [ebp+var_70]
                cmp     eax, [ebp+var_84]
                jb      short loc_313066
                sub     eax, [ebp+var_84]
                push    esi
                push    esi
                push    eax
                push    edi
                mov     [ebp+arg_0], eax
                call    sub_31486A
                test    eax, eax
                jz      short loc_31306D
                push    esi
                lea     eax, [ebp+arg_0]
                push    eax
                mov     esi, 1D0h
                push    esi
                push    [ebp+arg_4]
                push    edi
                call    sub_314623
                test    eax, eax
                jz      short loc_31306D
                cmp     [ebp+arg_0], esi
                jz      short loc_31308F

loc_313066:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+55
                push    0Dh
                call    sub_31411B

loc_31306D:                             ; CODE XREF: sub_312FD8
                                        ; sub_312FD8+49
                call    sub_3140F3
                test    eax, eax
                jg      short loc_31307D
                call    sub_3140F3
                jmp     short loc_31308C
; ---------------------------------------------------------------------

loc_31307D:                             ; CODE XREF: sub_312FD8
                call    sub_3140F3
                and     eax, 0FFFFh
                or      eax, 80070000h

loc_31308C:                             ; CODE XREF: sub_312FD8
                mov     [ebp+var_4], eax
```

References

1. Sikorski, Michael, and Andrew Honig. Practical Malware Analysis the Hands-on Guide to Dissecting Malicious Software. San Francisco: No Starch, 2012. Print.



```
                 push    edi
                 call    sub_314623
                 test    eax, eax
                 jz      short loc_31306D
                 cmp     [ebp+arg_0], ebx
                 jnz     short loc_313066
                 mov     eax, [ebp+var_70]
                 cmp     eax, [ebp+var_84]
                 jb      short loc_313066
                 sub     eax, [ebp+var_84]
                 push    esi
                 push    esi
                 push    eax
                 push    edi
                 mov     [ebp+arg_0], eax
                 call    sub_314623
                 test    eax, eax
                 jz      short loc_31306D
                 push    esi
                 lea     eax, [ebp+arg_0]
                 push    eax
                 mov     esi, 1D0h
                 push    esi
                 push    [ebp+arg_4]
                 push    edi
                 call    sub_314623
                 test    eax, eax
                 jz      short loc_31306D
                 cmp     [ebp+arg_0], esi
                 jz      short loc_31308F

loc_313066:                                  ; CODE XREF: sub_312FD8
                                             ; sub_312FD8+55
                 push    0Dh
                 call    sub_31411B

loc_31306D:                                  ; CODE XREF: sub_312FD8
                                             ; sub_312FD8+49
                 call    sub_3140F3
                 test    eax, eax
                 jg      short loc_31307D
                 call    sub_3140F3
                 jmp     short loc_31308C
; ---------------------------------------------------------------------------

loc_31307D:                                  ; CODE XREF: sub_312FD8
                 call    sub_3140F3
                 and     eax, 0FFFFh
                 or      eax, 80070000h

loc_31308C:                                  ; CODE XREF: sub_312FD8
                 mov     [ebp+var_4], eax
```