Computer Systems

07 | External I/O Calls | Stack Frames

Dr Stuart Thomason

External Subroutines

- Input and output are hard to do in pure assembly coding
 - Use specific registers to point to address of source or destination in memory
 - Trigger a CPU interrupt to pass control to the operating system
 - Device drivers perform the I/O by liaising with hardware
- The previous lecture explained how to pass parameters into subroutines
 - We can call external subroutines (C library code) in the same way
 - But we need to be sure to follow the C calling convention (cdecl)
- We will use the I/O routines from the C standard library
 - printf Send formatted output to the console (DOS/CMD window)
 - scanf Wait for input from the console

Program Output

- We use the external printf subroutine from the C standard library
- In a C program the call would use high level syntax to specify its parameter printf("Hello World");
- We don't have that luxury in assembly code, so we need to set up a few things first
 - Define the string as a C variable outside the assembly code block (this is a bit of a cheat to make coding easier on this module)
 - Find the address of the string inside the assembly code block
- Following the cdecl calling convention...
 - We must push the parameter to the stack
 - We must use pass by reference (ie. memory address of string)
 - We must clean up the stack afterwards

Complete Example

• This is the full example code for Visual Studio

Corrupted Registers

Consider the assembly code to output the string 10 times

```
mov ecx, 10
floop: lea eax, msg
push eax
call printf
pop eax
loop floop
```

- We don't know exactly what happens inside any external subroutine
 - It will almost certainly make use of registers
 - Which would overwrite whatever is stored in them
 - In this case, the loop counter (ECX) would be corrupted
 - So we need to save any register values that are important to our code
- We already have a convenient place to store things we want to keep safe
 - Push them to the stack!

Using the Stack

• We need to save things on the stack and then restore after the external call returns

```
mov ecx, 10
floop: push ecx
lea eax, msg
push eax
call printf
pop eax
pop ecx
loop floop
```

- Now the code will behave as we expect
 - Loop counter is saved to the stack
 - Doesn't matter if external subroutine corrupts the register
 - We restore it from the stack before the loop instruction uses it

Outputting Values

• The external routine can take extra parameters that store values to be outputted

```
int age = 21;
char name[] = "Bob";
printf("I am %s and I am %d years old\n", name, age);
```

• In a C program this would output...

```
I am Bob and I am 21 years old
```

- The string contains format specifiers that are replaced by each extra parameter
 - %d Display as a decimal integer
 - %s Display as a string
 - %c Display as a single character
 - %f Display as a floating-point number
- The extra parameters to printf must match the specifiers used in the string (and they must be given in the correct order of insertion)

Example Snippets

- Output a numeric value as part of a string
- Declare the string and the value in the C part of the code

```
char msg[] = "The number is %d\n";
int num = 7;
```

- The string (containing the format specifiers) is always the first parameter
- Any extra parameters represent the data to be output within the string
- We must push these in reverse order, following the cdecl calling convention

```
push num
lea eax, msg
push eax
call printf
add esp, 8
```

• Adding to the stack pointer is a quicker way to clean up multiple parameters at once

Program Input

- We use the external scanf subroutine from the C standard library
- In a C program the call would use high level syntax to specify what type of input we want and where in memory to store it

```
scanf("%d", &num);
```

- The C syntax uses an ampersand (&) to represent the memory address of a variable (you don't need to remember this; it won't be on the exam)
- Following the cdecl calling convention...
 - We must push the parameters to the stack in reverse order
 - We must use pass by reference (ie. memory addresses of parameters)
 - We must clean up the stack afterwards
- We can input strings (text) from the user in a similar way
 - Use the %s format specifier
 - Declare a char array that is big enough to store what they enter (easy to overflow)

Example Snippets

- Input a numeric value (integer) and store it in the accumulator
- Declare the format string and a variable for the input in the C part of the code char fmt[] = "%d";

```
int num;
```

We must push these in reverse order, following the cdecl calling convention

```
lea eax, num
push eax
lea eax, fmt
push eax
call scanf
add esp, 8
```

- Remember to push the <u>address</u> of the variable, not its value
- The external subroutine will wait for the user to type something and press enter
- Then it will store what they entered at the address passed to the routine

Stacking Local Variables

• In high level languages, subroutines can declare their own internal (local) variables

```
int subber (int n) {
    int x;
    int y;
    int z;
    ...
}
```

- Local variables only exist while the subroutine is active, so it makes sense to store them on the stack
- When high level code is compiled, it will generate machine code instructions to reserve memory on the stack for each variable

Stack Frames

- Each time a subroutine is called, a new stack frame is created on the stack
- This holds data that is needed by the subroutine
 - Parameters
 - Return address
 - Local variables
- With nested calls, several (or many) stack frames will be present on the stack
- We have already looked at the ESP register (stack pointer)
 - Always points to the top of the stack
 - Will change as space is reserved for local variables
- The CPU has another register called EBP (stack base pointer)
 - This always points to the start of the current stack frame
 - Can be used to access parameters and local variables using an offset (eg. EBP-4 is the address of the second parameter that was pushed)

Building the Stack Frame

- ESP always points to the top of the stack
- EBP initially points to the base of the stack (remember the stack grows downwards)
- When a subroutine is called...
 - Parameters are pushed to the stack first
 - Then the return address is pushed
 - Then value of EBP is pushed
 - Local variables are reserved on the stack (causing ESP to change)
 - Current value of ESP is put into EBP (to begin a new stack frame)
- When a subroutine is ready to return...
 - Remove any local variables from the stack
 - Pop top value into EBP (to restore previous stack frame)
 - Pop top value into EIP (to move execution back to caller)
- Finally, the caller is responsible for cleaning any parameters from the stack

Nested Calls and Stack Frames

- Consider a main program that calls a subroutine
- The subroutine calls another nested subroutine
- The stack grows as a stack frame is built up
 - Parameters
 - · Return address
 - Old base pointer
 - Local variables
- The values of EBP and ESP change as the calls happen
 - ESP <u>always</u> points to the top of the stack (remember it grows downwards)
 - EBP changes with each subroutine call
- Stack is cleaned up (shrinks) as each subroutine returns

