

Gianmaria Silvello

Department of Information Engineering University of Padua

gianmaria.silvello@unipd.it http://www.dei.unipd.it/~silvello/



Running Time

- In some cases we can define the exact running time of an algorithm
 - See Insertion Sort





Running Time

- In some cases we can define the exact running time of an algorithm
 - See Insertion Sort

- Nevertheless, the extra precision is not useful
 - Constants do not have a real impact on running times





Running Time

- In some cases we can define the exact running time of an algorithm
 - See Insertion Sort

- Nevertheless, the extra precision is not useful
 - Constants do not have a real impact on running times

- For input "large enough" we can get rid of multiplicative factors and <u>lower order terms</u>
 - Remember when we discussed linear vs quadratic running time





 We are concerned about how the running time of the algorithm grows as the size of the input goes to the limit





- We are concerned about how the running time of the algorithm grows as the size of the input goes to the limit
- Say the input has size n then we care about how the algorithm performs when $n \rightarrow +\infty$





- We are concerned about how the running time of the algorithm grows as the size of the input goes to the limit
- Say the input has size n then we care about how the algorithm performs when $n \rightarrow +\infty$
- An algorithm A which is asymptotically better than an algorithm B will perform better for all, but very small inputs
 - n≥n₀ where n₀ is a small value selected ad-hoc



- Let us consider two algorithms:
 - Algorithm A with $T_A(n) \sim n^2$
 - Algorithm B with T_B(n) ~ n

Algorithm B is better than Algorithm A for all n≥n₀





Asymptotic Notation

- We use asymptotic notation to describe the running time of algorithms
 - For insertion sort we said that the running time is
 - $T(n) = an^2 + bn + c$
 - Using asymptotic notation we might say that $T(n) = \Theta(n^2)$
 - With asymptotic notation we abstract away some details of functions





Asymptotic Notation

- We use asymptotic notation to describe the running time of algorithms
 - For insertion sort we said that the running time is
 - $T(n) = an^2 + bn + c$
 - Using asymptotic notation we might say that $T(n) = \Theta(n^2)$
 - With asymptotic notation we abstract away some details of functions
- With asymptotic notation we mainly focus on time, but it can be used to characterise any other aspect of an algorithm (e.g., space)





- Insertion sort has $\Theta(n^2)$ worst-case running time
 - What does this mean?


 $\Theta(g(n)) = \{f(n) : \text{ there exists positive constants}$ $c_1, c_2, \text{ and } n_0 \text{ such that}$ $0 \le c_1 g(n) \le f(n) \le c_2 g(n) \text{ for all } n \ge n_0 \}$





 $\Theta(g(n)) = \{f(n) : \text{ there exists positive constants}$ $c_1, c_2, \text{ and } n_0 \text{ such that}$

$$0 \le c_1 g(n) \le f(n) \le c_2 g(n) \text{ for all } n \ge n_0$$



Source: https://www.programiz.com/dsa/asymptotic-notations


 $f(n) = \Theta(g(n))$





 $\Theta(g(n)) = \{f(n) : \text{ there exists positive constants}$ $c_1, c_2, \text{ and } n_0 \text{ such that}$

$$0 \le c_1 g(n) \le f(n) \le c_2 g(n) \text{ for all } n \ge n_0$$



For small values of n we do not care how the running time compares to c_1n and c_2n , but when $n \ge n_0$ then the running time f(n) must be sandwiched between $c_1g(n)$ and $c_2g(n)$

Source: https://www.programiz.com/dsa/asymptotic-notations

$$f(n) = \Theta(g(n))$$

n_o





- We write $f(n) = \Theta(g(n))$ with a little abuse of notation
 - we should write $f(n) \in \Theta(g(n))$ or f(n) is $\Theta(g(n))$

 We say that g(n) is an asymptotically TIGHT BOUND for f(n)





- Big-oh (or only oh) notation defines an upper bound
 - It says that an algorithm cannot go slower than big-oh





- Big-oh (or only oh) notation defines an upper bound
 - It says that an algorithm cannot go slower than big-oh


$$O(g(n)) = \{ f(n) : \exists c > 0, n_0 > 0 \mid 0 \le f(n) \le cg(n), \forall n \ge n_0 \}$$





- Big-oh (or only oh) notation defines an upper bound
 - It says that an algorithm cannot go <u>slower</u> than big-oh

$$O(g(n)) = \{ f(n) : \exists c > 0, n_0 > 0 \mid 0 \le f(n) \le cg(n), \forall n \ge n_0 \}$$




 $\underline{Source: https://www.programiz.com/dsa/asymptotic-notations}$



- Big-oh (or only oh) notation defines an upper bound
 - It says that an algorithm cannot go slower than big-oh

$$O(g(n)) = \{f(n) : \exists c > 0, n_0 > 0 \mid 0 \le f(n) \le cg(n), \forall n \ge n_0\}$$



Source: https://www.programiz.com/dsa/asymptotic-notations





 Big-oh is used for the worst-case analysis because it defines a bound for all input instances

- Big-Theta does not imply an upper bound for every possible input
 - Indeed, $\Theta(n^2)$ for insertion sort is not a tight upper bound for all inputs since we have $\Theta(n)$ when the input instance is already sorted






Big-Omega notation

 It is complementary to big-Oh, it provides a <u>lower</u> bound

$$\Omega(g(n)) = \{ f(n) : \exists c > 0, n_0 > 0 \mid 0 \le cg(n) \le f(n), \forall n \ge n_0 \}$$



Source: https://www.programiz.com/dsa/asymptotic-notations



