## **Retrieving The Authenticated User**

In the previous video you have seen how to retrieve the authenticated user by using auth global helper function. Beside this helper Laravel also provide some alternative ways like so:

- Using Auth Facade
- Using Request instance or request helper

## **Using Auth Facade**

You can retrieve the current user's instance using this syntax:

```
use Illuminate\Support\Facades\Auth;

$user = Auth::user(); // this equivalent with auth()->user()
```

If you want to get only the authenticated user's id you can use this syntax:

```
use Illuminate\Support\Facades\Auth;

$user = Auth::id(); // this equivalent with auth()->id()
```

You can also determine if the user already logged in by using <code>check()</code> method. This method will return <code>true</code> if the user authenticated. Otherwise it will return <code>false</code>.

```
use Illuminate\Support\Facades\Auth;

if (Auth::check()) {
    // The user is logged in.
} else {
    // The user is not logged in.
}
```

## **Using Request Instance**

You can retrieve the current user's instance via Request instance like this.

```
use Illuminate\Http\Request;

public function store(Request $request)
{
    $user = $request->user();
}
```

You can retrieve the current user's instance via request global helper function like this.

```
public function store()
{
    $user = request()->user();
}
```