



CYBER SENTINEL XDR

User Manual

How to set up and use Cyber Sentinel XDR – Server and Endpoint

For SOC operators and the people whose computers are being protected.


Extended Detection & Response Platform | Version 1.0.0

1. What is Cyber Sentinel XDR?

Cyber Sentinel XDR is a security platform that watches computers for cyber attacks, explains what it found using AI, and can automatically respond (for example, isolating an infected machine). It has two parts:

The two roles	
SERVER	The brain + dashboard. Install on ONE central computer. Runs the AI models and the SOC screen.
ENDPOINT AGENT	A small program on each computer you want to protect. Sends activity to the server.

How data flows:



The server combines four AI detectors – Network, User Behavior, System, and Malware – into a single threat score, explains it, and shows it on the dashboard.

2. Server side – setup

1

Install the server

Double-click **CyberSentinelXDR-Server-Setup-1.0.0.exe**. Accept the license and let it install (it is large – it contains the AI models). If Windows shows a blue SmartScreen warning, click **More info** → **Run anyway**.

When it finishes, the **Server Control Panel** opens automatically.

2

Configure in the Control Panel

The Control Panel is where you set up and run the server:


Server Control Panel
MongoDB URI your database – local, or paste your MongoDB Atlas link
API Key the shared key endpoints use – [Regenerate] to make a new one
JWT Secret / Port leave defaults unless you need to change the port (8000)
[Test Database] check the database connects (should say CONNECTED)
[Save Config] saves your settings
[Start Server] [Stop] [Open Dashboard] run the server and open the SOC screen

Set your **MongoDB URI**, click **Test Database** (wait for CONNECTED), click **Save Config**, then **Start Server**. Copy the API key – you'll need it for endpoints.

3

Open the dashboard and log in

Click **Open Dashboard** (or visit `http://localhost:8000`). Log in with your admin email + password, then your 2FA code.



The Cyber Sentinel XDR login screen (Security Operations Center).

If login says “database offline”

The server can't reach the database. Go back to the Control Panel, fix the MongoDB URI, click Test Database until it says CONNECTED, then Stop and Start the server.

3. Server side – using the dashboard

After login you get the SOC dashboard. Main areas:

SOC Dashboard	
Overview	live threat score, activity log, key stats
Alerts	stream of detections with AI (SHAP) explanations; “Respond” on serious ones
Endpoints	every protected computer, online/offline, CPU/RAM, isolate/block buttons
Attack Graph	visual map of an attack across machines
Reports	downloadable PDF incident reports
Settings	detection thresholds, auto-response, sound alerts (admin only)

Responding to a threat

On a HIGH or CRITICAL alert, click **Respond**. You’ll see the attack summary, the AI explanation, and a checklist of actions you can run on the affected computer:

- **Isolate Host** – cut the machine off the network to stop spread.
- **Block IP** – block the attacker’s address.
- **Kill Process** – stop a malicious program.
- **Quarantine File** – move a malicious file somewhere safe.
- After acting, you can download a **PDF incident report** for your records.

4. Endpoint side – protect a computer

Do this on every computer you want the server to watch.

1

Install the endpoint agent

On that computer, run **CyberSentinelXDR-Setup-1.0.0.exe** (only ~11 MB). Accept the license.

2

Enter the server details

When asked, type:

```
Backend URL: http://<your-server-address>:8000
API Key:      (the key from the server Control Panel)
```

Use your server's LAN address on the same network (e.g. `http://192.168.1.5:8000`), or a public address/tunnel if the endpoint is remote.

3

Verify it connected

Within about 30 seconds, open the server dashboard → **Endpoints**. The new computer should appear as **online** with its CPU/RAM. That's the full loop working.

Same network vs. across the internet

On the same Wi-Fi/LAN, use the server's local IP. Across the internet, the server must be reachable publicly (router port-forward, a tunnel like Cloudflare/Tailscale, or a cloud VM) and should use HTTPS.

5. Roles & who can do what

User roles	
Admin	everything: users, settings, responses, reports
Analyst	investigate, respond, download reports
Viewer	read-only – view alerts, plain-language explanations

6. Support

For help with Cyber Sentinel XDR, contact:

Contact	
Syed Mazhar Hussain Shah	Product owner
Email	syedmazharhussainshah@gmail.com
Phone	+92 300 958 9752

Cyber Sentinel XDR v1.0.0 — multi-domain detection & response.