Installing tomcat on ubuntu server

```
Login as root user
sudo -i
#apt-get update
# apt-get install default-jre
# apt-get install zip
# wget http://www-eu.apache.org/dist/tomcat/tomcat-8/v8.5.11/bin/apache-tomcat-8.5.11.zip
# mv apache-tomcat-8.5.11.zip /opt
# cd /opt
# unzip apache-tomcat-8.5.11.zip
# cd apache-tomcat-8.5.11
Give tomcat start & stop script executable permission
# cd /opt/apache-tomcat-8.5.11/bin
# chmod u+x startup.sh
# chmod u+x shutdown.sh
# chmod u+x catalina.sh
Open browser and verify tomcat service
http://tomcatIP:8080
Set user, password & role for tomcat server.
# cd /opt/apache-tomcat-8.5.11/
# vi conf/tomcat-users.xml
Replace below mentioned content
-->
<!--
 <role rolename="tomcat"/>
 <role rolename="role1"/>
 <user username="tomcat" password="<must-be-changed>" roles="tomcat"/>
 <user username="both" password="<must-be-changed>" roles="tomcat,role1"/>
 <user username="role1" password="<must-be-changed>" roles="role1"/>
</tomcat-users>
with
__>
 <role rolename="manager-script"/>
 <role rolename="manager-gui"/>
 <user username="tomcat" password="tomcat" roles="manager-script,manager-gui"/>
</tomcat-users>
```

Visualpath Imran Teli

Comment antiResourceLocking values.

vi webapps/manager/META-INF/context.xml

Replace

```
<Context antiResourceLocking="false" privileged="true" >
        <Valve className="org.apache.catalina.valves.RemoteAddrValve"
        allow="127\.\d+\.\d+\.\d+\::1|0:0:0:0:0:0:0:1" />
        </Context>
```

with

Stop and start tomcat.

bin/shutdown.sh
bin/startup.sh

Verify the settings

http://tomcatIP:8080/manager/

Username: tomcat password: tomcat

You should see below mentioned screen





Message: OK	OK .								
Manager									
List Applications	HTML_Ma			Manager Help			Manager Help		Server Status
Applications									
Path	Version	Display Name			Running S		ssions	Commands	
Į.	None specified	Welcome to Tomcat			true		<u>0</u>	Start Stop Reload Undeploy	
								Expire sessions with idle ≥ 30 minut	es
/docs	None specified	Tomcat Documentation			true		Q	Start Stop Reload Undeploy	
					ude			Expire sessions with idle ≥ 30 minut	es
/examples	None specified	Servlet and JSP Examples			true	17		Start Stop Reload Undeploy	
						V.	0	Expire sessions with idle ≥ 30 minut	es
/host-manager	None specified	Tomcat Host Manager Application			true	Т		Start Stop Reload Undeploy	
		Torricat Host Manager Application			rue		Q	Expire sessions with idle ≥ 30 minut	es
Imanagor	Mono enacified	Tomost Manager Application			true	,		Start Stop Reload Undeploy	

Tomcat Web Application Manager