

# **kDNA real-time PCR qPCR**

*DINA Ahmed*

*ISAAC Carilo*

# Background:

- Detection and quantification of the parasite load in samples, using primers (JW11, JW12) chosen in the conserved sequences of the minicircles of kinetoplasmic DNA (*Nicolas et al., 2000*).
- In *Leishmania* spp., minicircles are generally present at around 10,000 copies per kinetoplast (*Brewster et al., 1998*).

# When to use?

- Estimate the parasite load (number/ml) in blood samples or tissue biopsies of infected individuals.
- The assay can detect 1 parasite per ml of blood.

## Protocol

Preparation  
of standard  
curve

DNA  
extraction

Running and  
analysis

# Samples:

- 3 Blood samples.
- 2 Biopsy samples.
- 2 Sand fly females blood fed.

## A. Setting up the *Leishmania* standard curve:

- 1 - Using an inverted microscope examine the *Leishmania tarentolae* (*non-pathogenic*) culture → Count the number of promastigotes → Calculate the total number of parasites/ml .
- 2- Prepare different concentrations of promastigotes in 1ml of sterile (PBS), starting from  $10^7$  and no parasite.

# B - DNA extraction of parasites:

- Punch 2 discs from each filter paper samples to be tested as well as standards and place into separate tubes (about 0.5 mm width).
- Add 180 $\mu$ l PBS and 20 $\mu$ l proteinase K, and then proceed with the DNA extraction using the Qiagene kit protocol.

## C. Running the assay:

- **Idea:** *The detection of the PCR amplification products is based on detecting the fluorescent SYBR green dye once bound to the newly amplified double stranded DNA molecules.*

# Reaction mixture needed to prepare one “20µl” reaction:

Material	Quantity
2X Absolute blue SYBR Green	10µl
Forward primer (1µM)	1µl
Reverse primer (1µM)	1µl
Extracted DNA	2µl
DDH2O	6µl

# Procedure:

- Count the number of the samples to be analyzed including the standard curve and negative controls (*8 points of different DNA concentrations used in creating the standard curve, two negative control, plus the unknown samples to be tested*).
- Prepare M.M.
- Add M.M. to each reaction well (18 µl).
- Add DNA sample (2 µl), including samples from the standard curve DNA.
- Run the qPCR machine.

# qPCR thermal cycling program:


Step	Temp.	Time	Number of cycles
Enzyme activation	95 °C	15 min.	1 cycle
Denaturation	95 °C	10s	40 cycles
Annealing	58 °C	10s	
Extension	72 °C	20s	

# Take care:

- *The forward and reverse primers are diluted in a final concentration of 10 µM.*
- *Negative control samples receive 2 µl DDH<sub>2</sub>O.*

# Advantages:

- More sensitive (huge amount of KDNA to be amplified).
- No Gel.
- Quantification of parasite load.




# **Disadvantages:**

- No species identification.
- Primers used can also amplify Trypanosomes (never specific).


# Results

# Amplification plot curves:




# Standard curve for qPCR

Standard curve for current assay



Typical standard curve



# Different concentrations from positive control:

Edit Samples

File Edit Format Security

Standard | Rotor Style |

Settings :

Given Conc. Format: 123457 Unit: mg/ml More Options


Samples :


C	ID	Name	Type	Groups	Given Conc.	Selected
	49	Unknown	Unknown			Yes
	50	Unknown	Unknown			Yes
	51	Unknown	Unknown			Yes
	52	Unknown	Unknown			Yes
	53	Unknown	Unknown			Yes
	54	Unknown	Unknown			Yes
	55	Unknown	Unknown			Yes
	56	Unknown	Unknown			Yes
	57	Unknown	Unknown			Yes
	58	Unknown	Unknown			Yes
	59	Unknown	Unknown			Yes
	60	Unknown	Unknown			Yes
	61	Unknown	Unknown			Yes
	62	Unknown	Unknown			Yes
	63	Unknown	Unknown			Yes
	64	Unknown	Unknown			Yes
	65	Standard	Standard		1	Yes
	66	Unknown	Unknown			Yes
	67	Unknown	Unknown			Yes
	68	Unknown	Unknown			Yes
	69	Standard	Standard		1000000	Yes
	70	Standard	Standard		100000	Yes
	71	Standard	Standard		10000	Yes
	72	Standard	Standard		100	Yes

Page : Name: Page 1 < > New Delete Synchronize pages

Undo OK Cancel Help


# Calibration curve:






**Parasite load detected in different types of samples**


# Blood samples



# Biopsy samples




# Leishmania CytB-PCR



G4	4853	blood
G4	1043	blood
G4	4422	blood
G4	0	Biopsy
G4	164	Biopsy
G4	10293	SF
G4	98	SF

# Sand fly samples



# Reverse line blot



# Conclusion:

- 1- Higher parasite load in Sand fly samples, followed by blood samples with least parasite number detected in Biopsy samples.
- 2- Anthropophagic nature of tested sand fly samples (detected by RLB).

# Thank You

