Third Week

MALTHUS MODEL

$$\frac{dN}{dt} = (B - D)N = kN$$


From $\frac{dN}{dt} = kN$ we have $\int \frac{dN}{N} = \int kdt = k \int dt = kt + c$

so ln(N) = kt + c and thus $N(t) = Ae^{kt}$.

Since $\hat{N} = N(0) = A$, we get:

$$N(t) = \hat{N}e^{kt} \tag{2}$$

with graphs as shown on figure 1.



IMPROVING ON MALTHUS

(LOGISTIC) D = sN, ASSUMPTION s = constant

We have to solve

$$\frac{dN}{dt} = BN - DN = BN - sN^2$$

with the condition $N(0) = \hat{N}$

We can and will solve this, but let's try to GUESS what the solution will look like (a useful skill - in many other cases you won't be able to solve exactly!). Suppose that \hat{N} is very small. Then (by continuity) N(t) will be very small for

t near to zero.


Of course if N is small, N^2 is much smaller and can be neglected. Remember that N may be measured in millions or billions, so N can be small. So at early times, our ODE is Almost

linear and so

$$\frac{dN}{dt} \approx BN \to N(t) \approx \hat{N}e^{Bt}$$

So AT FIRST the population explodes, as Malthus predicted. On the other hand, if N continues to grow, since N^2 grows faster than N, we will reach a point where $sN^2 \approx BN$ ie $N \approx B/S$.

At that point, since $\frac{dN}{dt} = BN - SN^2$, the population will stop growing. So B/S should measure the MAXIMUM population possible. So we GUESS that the solution should look like this:



The number B/s is called the CARRYING CAPACITY or the SUSTAINABLE POPULATION

$$\frac{dN}{dt} = BN - sN^2 \to t = \int \frac{dN}{N(B - sN)} + c$$
Write $\frac{1}{N(B - sN)} = \frac{\alpha}{N} + \frac{\beta}{B - sN}$

$$1 = \alpha(B - sN) + \beta N$$

$$= \alpha B + (\beta - \alpha s)N \to 1 = \alpha B, \ \beta = \alpha s$$

$$\alpha = 1/B, \ \beta = s/B, \text{ so}$$

$$\int \frac{dN}{N(B-sN)} = \frac{1}{B} \int \frac{dN}{N} + \frac{s}{B} \int \frac{dN}{B-sN}$$
$$= \frac{1}{B} \ln N - \frac{1}{B} \ln |B-sN|$$

Now here we begin to feel uneasy - what if N = B/s at some time? (ln(0) is not defined).

In fact we should have worried about this when we first wrote $\frac{1}{B-sN}$ - how do we know that we are not dividing by zero?? Let's not worry about that just now: let's ASSUME (temporarily) that B - sN is never zero. That is, we assume either that N is always either LESS THAN B/s or MORE THAN B/s. OK, let's take LESS THAN first. So |B - sN| = B - sN,

and we get

$$t = \frac{1}{B} \ln N - \frac{1}{B} \ln(B - sN) + c$$
$$= \frac{1}{B} \ln \frac{N}{B - sN} + c$$

So

$$\frac{N}{B-sN} = Ke^{Bt}$$
. Since $\hat{N} = N(0)$, $\frac{\hat{N}}{B-s\hat{N}} = K$


SO

$$\frac{N}{B - sN} = \frac{\hat{N}}{B - s\hat{N}}e^{Bt}$$

Solve for N,

$$N(t) = \frac{B}{s + \left(\frac{B}{\hat{N}} - s\right)e^{-Bt}} \tag{4}$$

The graph of (4) is easy to sketch:



This is the famous logistic curve; N(t) given by (4) is called the logistic function; and $\frac{dN}{dt} = BN - sN^2$ is the logistic equation.

It's easy to see what is happening here. Initially the population is small, plenty of food and space, so we get a Malthusian population explosion. But eventually the death rate rises until it is almost equal to the birth rate (ie $sN \approx B$ or $N \approx B/s$) and then the population approaches a fixed limit.


What if N(t) > B/s?

Then
$$|B - sN| = -(B - sN)$$
 so:

$$t = \frac{1}{B} \ln N - \frac{1}{B} \ln(sN - B) + c$$
$$= \frac{1}{B} \ln \frac{N}{sN - B} + c \Rightarrow$$

$$N(t) = \frac{B}{s - \left(s - \frac{B}{\hat{N}}\right)e^{-Bt}} \tag{5}$$

And now the graph is



The number B/s is called the Carrying Capacity or the Sustainable population - in all cases, it is the value approached by N(t) as $t \to \infty$. If we set

$$N_{\infty} = B/s \tag{6}$$

then our solutions are:

$$N(t) = \frac{N_{\infty}}{1 + \left(\frac{N_{\infty}}{\hat{N}} - 1\right) e^{-Bt}} (\hat{N} < N_{\infty}) (7)$$

$$N(t) = \frac{N_{\infty}}{1 - \left(1 - \frac{N_{\infty}}{\hat{N}}\right) e^{-Bt}} (\hat{N} > N_{\infty}) (8)$$

Tutorial 3

Question 5

A fully loaded large oil tanker can be modelled as a solid object with perfectly vertical sides and a perfectly horizontal bottom, so all horizontal cross-sections have the same area, equal to A. Archimedes' principle [http://en.wikipedia.org/wiki/Buoyancy] states that the upward force exerted on a ship by the sea is equal to the weight of the water pushed aside by the ship. Let ρ be the mass density of seawater, and let M be the mass of the ship, so that its weight is Mg, where g is 9.8 m/sec². When the ship is at rest, find the distance d from sea level to the bottom of the ship. This is called the **draught** of the ship.

1° At rest position:

Vol of sea water displaced = Ad Weight of sea water displaced = PAdg "The ship is at rest, : Mg = pAdg ---- D $d = \frac{M}{PA}$

Suppose now that the ship is *not* at rest; instead it is moving in the vertical direction. Let d + x(t) be the distance from sea level to the bottom of the ship, where d is the draught as above. Show that, if gravity and buoyancy are the only forces acting on the ship, it will bob up and down with an angular frequency given by $\omega = \sqrt{\rho \, A \, g/M}$.

2° Small displacement x: upward force = PA (d+x) g

$$\therefore M\ddot{x} = Mg - \beta A(d+x)g$$

$$= \beta Adg - \beta A(d+x)g \quad (\theta y 0)$$

$$= -\beta Agx$$