
5.7 Modeling - Empties

Em	pties	.1
	Settings	, 1
	Usage and functions	۷,

Empties

The "Empty" is a null object. It contains no real Geometry, but can be used as a handle for many purposes.

Settings



Empty Draw Types.

Display

Plain Axes

Draws as six lines, initially with one pointing in each of the +X,-X,+Y,-Y,+Z,and -Z axis directions.

Arrows

Draws as arrows, initially pointing in the positive X,Y, and Z axis directions, each with a label.

Single Arrow

Draws as a single arrow, initially pointing in the +Z axis direction.

Circle

Draws as a circle initially in the XZ plane.

Cube

Draws as a cube, initially aligned to the XYZ axes.

Sphere

Draws as an implied sphere defined by 3 circles. Initially, the circles are aligned, one each, to the X, Y, and Z axes.

Cone

Draws as a cone, initially pointing in the +Y axis direction.

Image

Empties can display images. This can be used to create reference images, including blueprints or character sheets to model from, instead of using background images. The image is displayed regardless of the 3D display mode. The settings are the same as in *Background Image Settings*

Note

While alpha-images can be used, there is a known limitation with object draw order, where alphas won't always draw on top of other objects when unselected.

Size

Controls the local size of the empty. This does not change its scale, but simply resizes the shape.

Usage and functions

Empties can serve as transform handles which cannot be edited and do not render. Empties are important and useful objects. Some examples of ways to use them include: *Parent object for a group of objects*

• An Empty can be parented to any number of other objects - This gives the user the ability to control a group of objects easily, and without affecting a render.

Target for constraints

- An empty can also be used as a target for normal, or bone constraints.
- This gives the user far more control; for instance, a rig can easily be set up to enable a camera to point towards an empty using the **Track to** constraint


Array offset

• An empty can be used to offset an array modifier, meaning complex deformations can be achieved by only moving a single object.



An example of an empty being used to control an array

Blender 2.76 Reference Manual - $\ensuremath{\mathbb{C}}$ Copyright - This page is under OCL license



An example of an empty being used to control the track to constraint

Other common uses.

- Placeholders
- Rigging controls
- DOF distances
- Reference Images