# 10.2.3.2 Render - Blender Render Engine - Lighting - Lights

Lights	1
Introduction	2
Lights Common Options	2
Object Data	3
Preview	3
Light Attenuation	3
Description	4
Falloff types	4
Lin/Quad Weighted	4
Linear	4
Quadratic	5
Mixing "Linear" and "Quad"	6
Zeroing both "Linear" and "Quad"	6
Graphical Summary	
Custom Curve	7
Inverse Square	9
Inverse Linear	10
Constant	10
Sphere	11
Examples	12
Distance Example	12
Inverse Square Example	12
Sphere Example	13
Lamps Textures	14
Options	16
What the Light Affects	16
Lamps Related Settings	16
Lighting Groups	17
Materials	
Render Layers	18
See Also	18

# Lights

- Introduction
- Lights Common Options
  - Object Data
  - Preview
- Light Attenuation
  - Description
  - Falloff types
  - Sphere
  - Examples
- Lamps Textures
  - Options
- What the Light Affects


- Lamps Related Settings
  - Lighting Groups
  - See Also

# Introduction

As previously stated, there are multiple types of lighting in Blender, like indirect light or ambient light. However, one of the most used are "lights", or "lamps". In this section, we will discuss general info and settings for these lights (you will find more lamp-specific details in the *Lamps* section):

- *Light Properties* settings common to all lamps.
- Light Attenuation.
- *Textures* how to apply texture(s) to lamps.
- What Light Affects.
- Lights In Other Contexts lamp-related setting in other contexts.

# **Lights Common Options**



Lamp Properties panels

There are five types of lamps in Blender. They share all or some of the options listed here:

## **Object Data**

### **Browse Light Object Data**

Click to view all lights in the current scene.

#### Name

The name of the currently selected light object data. Edit to change the name.

#### **Number of Users**

The number of light objects sharing the light object data.

F

Create a fake user for this object data.

#### **Preview**

A quick preview of the light settings.

Lamp

#### Distance

The *Dist* field indicates the number of Blender Units (BU) at which the intensity of the current light source will be half of its intensity. Objects less than the number of BU away from the lamp will get more light, while objects further away will receive less light. Certain settings and lamp falloff types affect how the *Distance* field is interpreted, meaning that it will not always react the same; see the page about *light falloff*.

• The *Sun* and *Hemi* Lamps are another class of Lamps which uses a constant falloff. Those lamps don't have a *Dist* field, and are often called "Base Lighting Lamps".

#### **Energy**

The intensity of the light source's illumination (from 0.0 to 10.0).

#### Color

The color of the light source's illumination. Opens a color swatch.

#### **Negative**

Let the lamp cast negative light.

#### **This Layer Only**

The Lamp only illuminates objects on the same layer the lamp is on.

#### **Specular**


The Lamp creates specular highlights.

#### **Diffuse**

The Lamp does diffuse shading.

# **Light Attenuation**

## **Description**




Lamp panel, falloff options highlighted

There are two main controls for light falloff for *Point* and *Spot* lamps.

- The lamp *Falloff* type drop-down list, and
- The Sphere button.

## Falloff types

### Lin/Quad Weighted



Lamp panel with Lin/Quad Weighted Falloff options highlighted

When this setting is chosen, two sliders are shown, *Linear* and *Quadratic*, which control respectively the "linearness" and "quadraticness" of the falloff curve.

This lamp falloff type is in effect allowing the mixing of the two light attenuation profiles (linear and quadratic attenuation types).

#### Linear

This slider input field can have a value between 0.0 and 1.0. A value of 1.0 in the *Linear* field and 0.0 in the *Quadratic* field in effect means that the light from this source is completely linear. This means that at the

number of Blender Units distance specified in the *Distance* field, this light source's intensity will be half the value it was originally.


When the *Quadratic* slider is set to 0.0, the formula for working out the attenuation at a particular range for full linear attenuation is:

$$I = E \times (D / (D + L \times r))$$

Where

- I is the calculated Intensity of light.
- E is the current *Energy* slider setting.
- D is the current setting of the *Dist* field.
- L is the current setting of the *Linear* slider.
- r is the distance from the lamp where the light intensity gets measured.

### Quadratic



Lamp with Lin/Quad Weighted falloff default settings

This slider input field can have a value between 0.0 and 1.0. A value of 1.0 in the *Quadratic* field and 0.0 in the *Linear* field means that the light from this source is completely quadratic.

Quadratic attenuation type lighting is considered a more accurate representation of how light attenuates (in the real world). In fact, fully quadratic attenuation is selected by default for *Lin/Quad Weighted* lamp fallout (see *Lamp with Lin/Quad Weighted falloff default settings*).

Here again, the light intensity is half when it reaches the *Distance* value from the lamp. Comparing the quadratic falloff to the linear falloff, the intensity decays much slower at distances lower than the set *Distance*, but it attenuates much quicker after *Distance* is reached.

When the Linear slider is set to 0.0, the formula for working out the attenuation at a particular range for full quadratic attenuation is:

$$I = E \times (D^2 / (D^2 + Q \times r^2))$$

Where

- I is the calculated Intensity of light.
- E is the current *Energy* slider setting.
- D is the current setting of the *Dist* field.
- **Q** is the current setting of the *Quad* slider.
- r is the distance from the lamp where the light intensity gets measured.

### Mixing "Linear" and "Quad"

If both the *Linear* and *Quad* slider fields have values greater than 0.0, then the formula used to calculate the light attenuation profile changes to this:

$$I = E \times (D / (D + L \times r)) \times (D^2 / (D^2 + Q \times r^2))$$

Where

- I is the calculated Intensity of light.
- E is the current *Energy* slider setting.
- D is the current setting of the *Dist* field.
- L is the current setting of the *Linear* slider.
- **Q** is the current setting of the *Quad* slider.
- r is the distance from the lamp where the light intensity gets measured.

### Zeroing both "Linear" and "Quad"


If both the *Linear* and *Quadratic* sliders have 0.0 as their values, the light intensity will not attenuate with distance. This does not mean that the light will not get darker - it will, but only because the energy the light has is spread out over a wider and wider distance. The total amount of energy in the spread-out light will remain the same, though. The light angle also affects the amount of light you see. It is in fact the behavior of light in the deep space vacuum.

If what you want is a light source that doesn't attenuate and gives the same amount of light intensity to each area it hits, you need a light with properties like the *Constant* lamp *Falloff* type.

Also, when the *Linear* and *Quad* sliders are both 0.0 values the *Distance* field ceases to have any influence on the light attenuation, as shown by the equation above.

### **Graphical Summary**

Below is a graph summarizing the lin/quad attenuation type, showing attenuation with or without the *Sphere* option (described later).



### **Custom Curve**

The *Custom Curve* lamp *Falloff* type is very flexible.

Most other lamp falloff types work by having their light intensity start at its maximum (when nearest to the light source) and then with some predetermined pattern decrease their light intensity when the distance from the light source increases.

When using the *Custom Curve* Lamp Falloff type, a new panel is created called *Falloff Curve*. This *Falloff Curve* profile graph allows the user to alter how intense light is at a particular point along a light's attenuation profile (i.e. at a specific distance from the light source).

The Falloff Curve profile graph has two axes, the Distance axis and the Intensity axis.

#### **Distance** axis


It represents the position at a particular point along a light source's attenuation path. The far left is at the position of the light source and the far right is the place where the light source's influence would normally be completely attenuated. I say "normally would" because the *Falloff Curve* can be altered to do the exact opposite if required.

#### **Intensity axis**


It represents the intensity at a particular point along a light source's attenuation path. Higher intensity is represented by being higher up the intensity axis, while lower intensity light is represented by being lower down on the intensity axis.

Altering the *Falloff Curve* profile graph is easy. Just LMB click on a part of the graph you want to alter and drag it where you want it to be. If when you click you are over or near one of the tiny black square handles, it will turn white, indicating that this handle is now selected, and you will be able to drag it to a new position. If when you click on the graph you are not near a handle, one will be created at the point that you clicked, which you can then drag where you wish. You can also create handles at specific parts of the graph, clicking with LMB while holding Ctrl key; it will create a new handle at the point you have clicked.

In the example below (the default for the *Falloff Curve* Profile Graph), the graph shows that the intensity of the light starts off at its maximum (when near the light), and linearly attenuates as it moves to the right (further away from the light source).




If you want to have a light attenuation profile that gets more intense as it moves away from the light source, you could alter the graph as below:




You are obviously not just limited to simple changes such as reversing the attenuation profile, you can have almost any profile you desire.

Here is another example of a different *Falloff Curve* profile graph, along with its resultant render output:

Blender 2.76 Reference Manual - © Copyright - This page is under OCL license




### **Inverse Square**



Render showing the Inverse Square lamp falloff type effect with default settings.

This lamp falloff type attenuates its intensity according to inverse square law, scaled by the *Distance* value. Inverse square is a sharper, realistic decay, useful for lighting such as desk lamps and street lights. This is similar to the old *Quad* option (and consequently, to the new *Lin/Quad Weighted* option with *Linear* to 0 . 0 and *Quad* to 1 . 0), with slight changes.


#### **Inverse Linear**



Render showing the Inverse Linear lamp falloff type effect with default settings.

This lamp falloff type attenuates its intensity linearly, scaled by the *Dist* value. This is the default setting, behaving the same as the default in previous Blender versions without *Quad* switched on, and consequently, like the new *Lin/Quad Weighted* option with *Linear* to 1.0 and *Quad* to 0.0. This isn't physically accurate, but can be easier to light with.


#### **Constant**



Render showing the Constant lamp falloff type effect with default settings.

This lamp falloff type does not attenuate its intensity with distance. This is useful for distant light sources like the sun or sky, which are so far away that their falloff isn't noticeable. *Sun* and *Hemi* lamps always have constant falloff.

## **Sphere**



Screenshot of the 3D view window, showing the Sphere light clipping circle.

The *Sphere* option restricts the light illumination range of a *Lamp* or *Spot* lamp, so that it will completely stop illuminating an area once it reaches the number of Blender Units away from the Lamp, as specified in the Dist field.

When the *Sphere* option is active, a dotted sphere will appear around the light source, indicating the demarcation point at which this light intensity will be null.


The *Sphere* option adds a term to the chosen attenuation law, whatever it is:

$$I' = I \times (D - r) / Difr < D; 0 otherwise$$


#### Where:

- I' is the required Intensity of light (with the *Sphere* option activated).
- I is the intensity of light calculated by the chosen attenuation law (without the *Sphere* option).
- D is the current setting of the *Dist* field.
- r is the distance from the lamp where the light intensity gets measured.

See the graphic at the end of the description of the *Lin/Quad Weighted* attenuation option.



Render showing the light attenuation of a Constant falloff light Render showing the light attenuation of a Constant falloff light type with the Sphere option active.




type with the Sphere option deactivated.

## **Examples**

### **Distance Example**

In this example, the *Lamp* has been set pretty close to the group of planes. This causes the light to affect the front, middle and rear planes more dramatically. Looking at (*Various Dist ance settings*), you can see that as the *Dist* is increased, more and more objects become progressively brighter.



The *Distance* parameter is controlling where the light is falling - at a linear rate by default - to half its original value from the light's origin. As you increase or decrease this value, you are changing where this half falloff occurs. You could think of *Distance* as the surface of a sphere and the surface is where the light's intensity has fallen to half its strength in all directions. Note that the light's intensity continues to fall even after *Distance*. *Distance* just specifies the distance where half of the light's energy has weakened.

Notice in (*Distance* : 1000) that the farthest objects are very bright. This is because the falloff has been extended far into the distance, which means the light is very strong when it hits the last few objects. It is not until 1000 units that the light's intensity has fallen to half of its original intensity.

Contrast this with (*Distance* : 10), where the falloff occurs so soon that the farther objects are barely lit. The light's intensity has fallen by a half by time it even reaches the tenth object.


You may be wondering why the first few planes appear to be dimmer? This is because the surface angle between the light and the object's surface normal is getting close to oblique. That is the nature of a *Lamp* light object. By moving the light infinitely far away you would begin to approach the characteristics of the *Sun* lamp type.

## **Inverse Square Example**

*Inverse Square* makes the light's intensity falloff with a non-linear rate, or specifically, a quadratic rate. The characteristic feature of using *Inverse Square* is that the light's intensity begins to fall off very slowly but then starts falling off very rapidly. We can see this in the (*Inverse Square selected*) images.

Inverse Square selected (with the specified distances).

Blender 2.76 Reference Manual - © Copyright - This page is under OCL license



With *Inverse Square* selected, the *Distance* field specifies where the light begins to fall off faster, roughly speaking; see the light attenuation description in Falloff types for more info.


In (*Inverse Square with* **10**), the light's intensity has fallen so quickly that the last few objects aren't even lit.

Both (*Inverse Square with* **100**) and (*Inverse Square with* **1000**) appear to be almost identical and that is because the *Distance* is set beyond the farthest object's distance which is at about **40 BU** out. Hence, all the objects get almost the full intensity of the light.

As above, the first few objects are dimmer than farther objects because they are very close to the light. Remember, the brightness of an object's surface is also based on the angle between the surface normal of an object and the ray of light coming from the lamp.

This means there are at least two things that are controlling the surface's brightness: intensity and the angle between the light source and the surface's normal.

### Sphere Example



Clipping Sphere.

*Sphere* indicates that the light's intensity is null at the *Distance* distance and beyond, regardless of the chosen light's falloff. In (*Clipping Sphere*) you can see a side view example of the setup with *Sphere* enabled and a distance of **10**.

Any objects beyond the sphere receive no light from the lamp.

The *Distance* field is now specifying both where the light's rays become null, and the intensity's ratio falloff setting. Note that there is no abrupt transition at the sphere: the light attenuation is progressive (for more details, see the descriptions of the Sphere and Falloff types above).

Sphere enabled with the specified distances, Inverse Linear light falloff.

Blender 2.76 Reference Manual - © Copyright - This page is under OCL license



In (*Sphere with* **10**), the clipping sphere's radius is **10** units, which means the light's intensity is also being controlled by **10** units of distance. With a linear attenuation, the light's intensity has fallen very low even before it gets to the first object.


In (*Sphere with* 20), the clipping sphere's radius is now 20 BU and some light is reaching the middle objects.

In (*Sphere with* 40), the clipping sphere's radius is now 40 units, which is beyond the last object. However, the light doesn't make it to the last few objects because the intensity has fallen to nearly 0.

#### Hint

If a *Lamp* light is set to not cast shadows, it illuminates through walls and the like. If you want to achieve some nice effects like a fire, or a candle-lit room interior seen from outside a window, the *Sphere* option is a must. By carefully working on the *Distance* value you can make your warm firelight shed only within the room, while illuminating outside with a cool moonlight, the latter achieved with a *Sun* or *Hemi* light or both.

## **Lamps Textures**



Lamp Texture panels

When a new lamp is added, it produces light in a uniform, flat color. While this might be sufficient in simple renderings, more sophisticated effects can be accomplished through the use of *textures*. Subtle textures can add visual nuance to a lamp, while hard textures can be used to simulate more pronounced effects, such as a disco ball, dappled sunlight breaking through treetops, or even a projector. These textures are assigned to one of ten channels, and behave exactly like material textures, except that they affect a lamp's color and intensity, rather than a material's surface characteristics.


## **Options**

The lamp textures settings are grouped into two panels. Here we will only talk about the few things that differ from object material textures; see the *Materials* and *Textures* chapters for details about the standard options.

The texture-specific and the *Mapping* panels remain the same. However, you'll note there are much fewer *Mapping* options - you can only choose between *Global*, *View* or another *Object* 's texture *coordinates* (since a lamp has no texture coordinates by itself), and you can scale or offset the texture.

The *Mapping* panel is also a subset of its regular material's counterpart. You can only map a lamp texture to its regular, basic *Color* and/or to its *Shadow* color. As you can only affect colors, and a lamp has no texture coordinates on its own, the *Diffuse*, *Specular*, *Shading*, and *Geometry* options have disappeared.

# What the Light Affects



Lamp panel with the light affecting options highlighted

Every lamp has a set of switches that control which objects receive its light, and how it interacts with materials.

#### **Negative**

The light produced by the lamp is **subtracted** from the one "available" on the surfaces it hits, which darkens these surfaces instead of brightening them.

#### This Layer Only

Causes the lamp to only light objects on the same layer.

#### **Diffuse**

Prevents the lamp from producing *diffuse light* (it doesn't really "light" things).

#### Specular


Prevents the lamp from producing *specular highlights*.

## **Lamps Related Settings**

Here are some options closely related to light sources, without being lamps settings.

## **Lighting Groups**

#### **Materials**




Light Group options for Materials

By default, materials are lit by all lamps in all visible layers, but a material (and thus all objects using that material) can be limited to a single group of lamps. This sort of control can be incredibly useful, especially in scenes with complex lighting setups. To enable this, navigate to the *Material* menu's *Options* panel and select a group of lamps in the *Light Group* field. Note that a *light group* must be created first.

If the *Exclusive* button is enabled, lights in the specified group will *only* affect objects with this material.

## **Render Layers**



Light Group options for Render Layers

There's a similar control located in the *Layer panel* of the context *Render Layers*. If a light group name is selected in this *Light* field, the scene will be lit exclusively by lamps in the specified group.

## See Also

- · Lamps Introduction
- Shadows
- Materials Introduction