

# RALLY FIELD TECHNICIAN APP – ADMIN PANEL SRS

## (Software Requirements Specification)

### 1. INTRODUCTION

The Admin Panel is a secure web-based control system used by Rally administrators to manage buildings, risers, floors, images, PDFs, and technicians.

Only authorized admins can access this module.

### 2. OBJECTIVES

- Maintain accurate building metadata for technicians.
- Upload and manage ONT configuration PDFs.
- Manage floors and risers, including single and East/West riser logic.
- Upload parking and riser images.
- Manage users and their permissions.
- Override complexity and required technicians.

### 3. USER ROLES

#### ADMIN:

- Full access to all admin modules.
- Can create/edit/delete buildings, floors, risers, images, PDFs, and users.

#### TECHNICIAN:

- No access to admin panel.
- Mobile app usage only.

### 4. ADMIN PANEL MODULES

#### 4.1 Dashboard

##### Displays:

- Total buildings
- Total risers
- Total ONT PDFs
- Total images
- Recent uploads and quick navigation shortcuts.

#### 4.2 Manage Buildings

##### Fields:

- Building Name
- Address (line1, line2, city, state, country)
- Technology Type (GPON/DSL/Ethernet)

- Infrastructure Type
- Serviced By
- Techs Per Install (raw Excel string)
- Auto Complexity Score (read-only unless override)
- Required Technicians (auto/manual)
- Admin Notes

Functions:

- Search, filter buildings
- Edit existing building
- Enable “Override Complexity”
- Import from Excel (future phase)

#### 4.3 Manage Floors

Features:

- Add floors (1, 2, 3 ... PH)
- Bulk-add floors (1–60)
- Edit floor labels
- Set sorting order

#### 4.4 Manage Risers

Supports:

- A. Single Riser Buildings
- B. Dual Riser Buildings (East + West Side)

Fields:

- Riser Name
- Riser Side (Single/East/West)
- Building Selection
- Floor Assignment
- Description

Riser Logic Saved:

- If single → technician sees only one.
- If dual → show “East Side Riser” and “West Side Riser”.
- Vertical logic:

`nearest_above = smallest riser floor > selected floor`

`nearest_below = largest riser floor < selected floor`

#### **4.5 Manage Images**

Categories:

- Parking
- Riser
- Lobby
- Other

Fields:

- Building
- Category
- Title
- Description
- File Upload

#### **4.6 Manage ONT PDFs**

Fields:

- Building
- Technology (Nokia/Huawei/SmartOLT/Positron)
- PDF Title
- File Upload

Admin can:

- Upload new PDFs
- Delete or replace PDFs

#### **4.7 Manage Users**

Fields:

- Name
- Email
- Role (Admin/Technician)
- Status (Active/Disabled)

Admin can:

- Create user
- Disable user
- Send password reset link

### **5. LOGIC REQUIREMENTS**

#### **5.1 Complexity Calculation**

Input raw formats:

- "1"
- "2"
- "60%1 and 40%2"

Weight:

- 1 tech = 30%
- 2 tech = 80%

Formula:

$$\text{complexity} = (p1 * 30 + p2 * 80) / 100$$

Required Technician Logic:

If  $p2 \geq 50\%$  → Required Techs = 2

Else → Required Techs = 1

Admin Override:

If override enabled → manual values stored and shown.

## 5.2 Riser Logic

System stores:

- Riser Side
- Riser Floor
- Building Relationship

When technician selects a floor:

1. Filter risers by building.
2. If dual risers → show East and West separately.
3. Vertical logic for nearest above/below.

## 5.3 Images & PDF Rules

- Uploaded files stored with URL.
- PDFs served through in-app viewer.
- Images accessible instantly with caching.

## 6. SECURITY REQUIREMENTS

- JWT authentication
- Strict role-based access control
- Input validation for all fields
- File size & type validation

## 7. ADMIN WORKFLOW

Login →

Dashboard →

Manage Building →

Add floors →

Add risers (Single/East/West) →

Upload images →

Upload ONT PDFs →

Save →

Technicians instantly receive updated information.

END OF DOCUMENT