#### CSCI 2270, Fall 2014

HW4, Doubly linked list polynomial (this assignment was written by Professor Michael Main, and lightly edited by me)

#### The Assignment:

Implement a polynomial class that uses a doubly-linked list of polynodes to store the polynomial's terms. Each polynode of the list holds the coefficient and exponent for one term. The terms are kept in order from smallest to largest exponent. Each polynomial also maintains a pointer called recent\_ptr to the most recently accessed polynode.

### **Purposes:**

Ensure that you can write a class that uses a linked list, with a roving cursor (recent ptr) to make the list more efficient.

#### **Due Date:**

Part 1 (steps 1-6): Sunday, April 6, 11:50pm, via Moodle.
Part 2 (step 7 and extra credit): Sunday, April 13, 11:50pm, via Moodle.

#### Files that you must use:

- 1. poly.h: The header file for the new polynomial class.
- 2. poly.cxx: The implementation file for the new polynomial class. You'll complete the code in this file.

## Other files that you may find helpful:

- 1. polytest.cxx: A simple interactive test program.
- 2. **polyexam.cxx**: A non-interactive test program that will be used to grade the correctness of your **polynomial** class.
- 3. Makefile: compile the test files with the polynomial class.

# The Polynomial Class with a Linked List Discussion of the Assignment

As indicated above, you will write the **polynomial** class, which uses a doubly-linked list to store **coefficients**.

Step 1. Polynomials keep linked lists of polynodes. Look at the polynode class in poly.h. This class defines a single term (coefficient plus exponent) in a polynomial. All of the functions for a polynode are defined for you already in this header file.

Please also look at the **private** member variables for the **polynomial** class, also in **poly.h**:

### private:

```
// Head pointer for list of nodes
polynode* head_ptr;
// Tail pointer for list of nodes
polynode* tail_ptr;
// Pointer to most recently used node
mutable polynode* recent_ptr;
// Current degree of the polynomial
unsigned int current_degree;
```

The meaning of the mutable keyword will be covered in class. But a brief explanation now: Our plan is to keep the recent\_ptr always pointing to the most recently used polynode. For example, when we call the coefficient member function, we will move the recent\_ptr to point to the polynode that contains the requested exponent. With a normal member variable, we could not do this (since the coefficient is a const member function and it is forbidden from changing normal member variables). So the meaning of the mutable keyword is to indicate that changing the member variable does not change the value of the polynomial in a meaningful way (and therefore, the compiler will let const member functions change a mutable variable).

In your poly.cxx, write a clear description of how the member variables of a polynomial are used. The head\_ptr and tail\_ptr are the head and tail pointers for a doubly-linked list of polynodes that contain the polynomial's

terms in order from smallest to largest **exponent**. To make certain operations simpler, we will always keep a **polynode** for the zero-order (x^0) term. But other **polynodes** are kept only if the **coefficient** is non-zero. We always maintain **recent\_ptr** as a pointer to some **polynode** in the list--preferably the most recently used **polynode**. The degree of the **polynomial** is stored in **current degree** (using zero for the case of all zero **coefficients**).

Step 2: The **poly.h** header file contains a prototype for a **private** member function that will make it easier to implement everything else:

// A private member function to aid the other functions:
void set recent(unsigned int exponent) const;

The set\_recent function will set the recent\_ptr to the polynode that contains the requested exponent. If no such exponent exists, then recent\_ptr should be set to the last polynode that is still less than the specified exponent. Note that set\_recent is a const member function, but that it can still change the mutable recent\_ptr member variable. My implementation of set recent used four cases:

If the requested **exponent** is zero, then set **recent\_ptr** to the head of the list.

Else if the exponent is greater than or equal to the current\_degree, then set recent ptr to the tail of the list.

Else if the exponent is smaller than the exponent in the recent polynode, then move the recent ptr backward as far as needed.

Else move the recent ptr forward as far as needed.

Step 3. Implement the constructors, destructor, and assignment operator.

For the default constructor, you could start by creating a valid empty **polynomial** (with a head **polynode** that has **exponent** and **coefficient** of zero).

Then call assign\_coef to set the one term. (Note that you need to make a 2-polynode list if the exponent here is greater than 0.)

The copy constructor should also start by creating a valid empty polynomial. Then have a loop that steps through the terms of the source (using source.next\_term). Each term of the source is placed in the polynomial (using assign coef).

The assignment operator first checks for a self-assignment, then clears out the terms (using the clear function). Finally, it has a loop (similar to the copy constructor) to copy the terms of the source.

Step 4. Implement the assign\_coef function. After calling set recent (exponent), my implementation had these cases:

If there is a zero coefficient and exponent greater than current\_degree, return with no further work.

Else if there is currently no **polynode** for the given **exponent** (so that **recent\_ptr->exponent**() is less than the new **exponent**), make a new **polynode** and connect it into the list.

Else if the **coefficient** is non-zero or the **exponent** is zero, just change the **coefficient** of an existing **polynode** in the list.

Else if the exponent equals the current\_degree, the coefficient is zero (otherwise we would have hit the previous case), so we remove the tail polynode, set the recent\_ptr to the new tail, and reduce the current\_degree.

Else, in this last case, we must have a new zero **coefficient** for a **polynode** that is neither the head nor the tail. We just remove this **polynode** and set the **recent ptr** to the *previous* **polynode** in the list.

- Step 5. Implement the add\_to\_coef function, using logic like what you used in step 4.
- Step 6. Write next\_term and previous\_term so that they each start with set recent.

Hint for next\_term: Start by calling set\_recent(exponent). Normally, the right answer is then in the polynode after recent\_ptr (but there is one exception that you should handle).

Hint for previous\_term: Start by checking the special case where exponent is zero. Then call set\_recent(exponent - 1). Normally, the right answer is then in the recent\_ptr polynode (but again, there is one special case that you need to handle--the case where the polynode has exponent and coefficient of zero).

Step 7. When these above functions are working, use them to write the operator +, operator -, and operator \* functions to compute the sum, difference, and product of two polynomials. Write the derivative() function to compute the derivative of a polynomial, using the power rule. And write eval (and its sibling function, operator()) to evaluate a polynomial at a particular value of x.

For 5% extra credit, you may write the root-finding function **find\_root**, which uses Newton's method to locate a value of x that makes the **polynomial** (evaluated at x) equal to zero.