Linux 系统下软 RAID 故障磁盘替换

一【实验目标】

● 学习并掌握 Linux 系统下软 RAID1 故障磁盘的更换方式

二【实验环境】

实验机环境: Centos 6.6目标机环境: Centos 6.6实验拓扑: 如图 1 所示。



图 1 实验拓扑

三【实验原理】

RAID 1 通过磁盘数据镜像实现数据冗余,在成对的独立磁盘上产生互 为备份的数据。当原始数据繁忙时,可直接从镜像拷贝中读取数据,因此 RAID 1 可以提高读取性能。RAID 1 是磁盘阵列中单位成本最高的,但提供了很高的数据安全性和可用性。当一个磁盘失效时,系统可以自动切换到镜像磁盘上读写,而不需要重组失效的数据。

本实验就是利用这个原理,在不破坏数据的前提下替换镜像或者原始数据的磁盘。

四【实验步骤】

1、用磁盘 sdh 和 shj 创建 raid1,过程与上次试验类似,不再赘述。

[root@localhost yangbin]# mdadm -C /dev/mdl -ayes -l1 -n2 /dev/sd[h,i]1

[root@localhost yangbin]# mkdir /raid1 [root@localhost yangbin]# mount /dev/md1/raid1 mount: can't find /dev/mdl/raidl in /etc/fstab or /etc/mtab [root@localhost yangbin]# echo DEVICE /dev/sd{h,i}1 >> /etc/mdadm.conf [root@localhost yangbin]# madam -Ds>>/etc/mdadm.conf bash: madam: command not found [root@localhost yangbin]# mdadm -Ds >> /etc/mdadm.conf [root@localhost yangbin]# vi /etc/mdadm.conf [root@localhost yangbin]# mount /dev/md1/raid0 mount: can't find /dev/mdl/raid0 in /etc/fstab or /etc/mtab [root@localhost yangbin]# mount /dev/md1 /raid1/ [root@localhost yangbin]# vi /etc/fstab [root@localhost yangbin]# mdadm --manage /dev/md1 --fail /dev/sdh1 mdadm: set /dev/sdh1 faulty in /dev/md1 [root@localhost yangbin]# cat /proc/mdstat Personalities : [raid0] [raid1] md1 : active raid1 sdi1[1] sdh1[0](F) 92032 blocks super 1.2 [2/1] [U] md0 : active raid0 sdg1[1] sdf1[0] 259072 blocks super 1.2 512k chunks

图 2

2、在系统移除/dev/sdh(假设这块磁盘坏了), 先移除 sdh 的分区(只有1块 sdh1)

(1) 标记/dev/sdh1 为 fail

命令: mdadm -manage /dev/md1 -fail /dev/sdh1

[root@localhost yangbin]# mdadm --manage /dev/md1 --fail /dev/sdh1
mdadm: set /dev/sdh1 faulty in /dev/md1

用 cat /proc/mdstat 查看,出现

unused devices: <none>

(2) 移除 sdh1

命令: mdadm -manage /dev/md1 -remove /dev/sdh1

[root@localhost yangbin]# mdadm --manage /dev/mdl --remove /dev/sdhl

mdadm: hot removed /dev/sdh1 from /dev/md1 [root@localhost yangbin]# cat /proc/mdstat

Personalities : [raid0] [raid1] md1 : active raid1 sdi1[1]

92032 blocks super 1.2 [2/1] [U]

md0 : active raid0 sdg1[1] sdf1[0]

259072 blocks super 1.2 512k chunks

unused devices: <none>

3、用新的一块硬盘 sdj 代替 sdh

- (1) 将 sdi 的分区复制到 sdj 命令: sfdisk –d /dev/sdi |sfdisk /dev/sdj
- (2) 将 sdj 的分区挂到 raid1 里

命令: mdadm -manage /dev/md1 -add /dev/sdj1

[root@localhost yangbin]# mdadm --manage /dev/md1 --add /dev/sdj1

mdadm: added /dev/sdj1

[root@localhost yangbin]# cat proc/mdstat
cat: proc/mdstat: No such file or directory
[root@localhost yangbin]# cat /proc/mdstat

Personalities : [raid0] [raid1] md1 : active raid1 sdj1[2] sdi1[1] 92032 blocks super 1.2 [2/2] [UU]

md0 : active raid0 sdg1[1] sdf1[0]

259072 blocks super 1.2 512k chunks

unused devices: <none>

大功告成