MICROOH 麦可网

Android-从程序员到架构师之路

出品人: Sundy

讲师:高焕堂(台湾)

http://www.microoh.com

D05_c

Android Service的 Proxy-Stub设计模式(c)

By 高煥堂

4、举例:以既有的 SensorService为例


它的Stub和Proxy类



 从上一节里,可以看出使用AIDL来(生成 Stub类)包装Android Service的要点:


1.地头蛇(服务开发者)定义一个ISampleService接口。


- 2.使用强龙提供的AIDL工具去读取接口定义檔,产生一个Stub类和Proxy类;这个Stub类就是:ISampleService.Stub类。
- 3. 然后,撰写一个SampleService类来继承ISampleService.Stub基类。



```
public class myActivity extends Activity {
@Override
  public void onCreate(Bundle savedInstanceState) {
      // . . . . . .
     IBinder m_ib = ServiceManager.getService("CS001");
     ISampleService m_obj =
              ISampleService.Stub.asInterface( m_ib );
      // .....
      m_obj.f1(255);
      m_obj.f2(17.35);
      // . . . . . .
```

IBinder m_ib = ServiceManager.getService("CS001");






观摩ISensorService.Stub类

于是可得知,在Android (1.x和2.x版)的框架里,其SensorService类别就继承了ISensorService.Stub类,如下述代码:

```
// framework/base/services/java/SensorService.java
class SensorService extends ISensorService.Stub {
  // (省略)
  private static native int _sensors_control_init();
  private static native ParcelFileDescriptor _sensors_control_open();
  private static native boolean _sensors_control_activate(int sensor,
                boolean activate);
  private static native int _sensors_control_set_delay(int ms);
  private static native int _sensors_control_wake();
```




JNL

```
public class myActivity extends Activity {
  private static final String TAG="myActivity";
  public void onCreate(Bundle savedInstanceState) {
     super.onCreate(savedInstanceState);
     setContentView(R.layout.main);
     IBinder m_ib = ServiceManager.getService(
                            Context.SENSOR_SERVICE));
     ISensorService m_ss =
         ISensorService.Stub.asInterface( m_ib );
    // . . . . . . .
```


IBinder m_ib

= ServiceManager.getService(Context.SENSOR_SERVICE));




ISensorService m_ss =

ISensorService.Stub.asInterface(m_ib);



```
/**
* Cast an IBinder object into an ISensorService interface,
* generating a proxy if needed.
public static
android.hardware.ISensorService asInterface(android.os.IBinder obj)
     if ((obj==null)) return null;
     android.hardware.ISensorService in =
            android.hardware.ISensorService)obj.queryLocalInterface(
                                DESCRIPTOR);
     if ((in!=null)) return in;
     return new android.hardware.ISensorService.Stub.Proxy(obj);
```





Thanks...



高煥堂