МИНОБРНАУКИ РОССИИ САНКТ-ПЕТЕРБУРГСКИЙ ГОСУДАРСТВЕННЫЙ ЭЛЕКТРОТЕХНИЧЕСКИЙ УНИВЕРСИТЕТ «ЛЭТИ» ИМ. В.И. УЛЬЯНОВА (ЛЕНИНА)

Кафедра математического обеспечения и применения ЭВМ

ОТЧЕТ

по лабораторной работе № 3 по дисциплине «Операционные системы»

Тема: «Исследование организации управления основной памятью»

Студент гр. 8304	 Сергеев А.Д.
Преподаватель	 Губкин А.Ф.

Санкт-Петербург 2019

Цель работы.

Исследование структур данных и работы функций управления памятью операционной системы.

Постановка задачи:

Шаг 1.

Необходимо написать и отладить программный модуль типа .COM, который выбирает и распечатывает следующую информацию:

- 1. Количество доступной памяти.
- 2. Размер расширенной памяти.
- 3. Выводит цепочку блоков управления памятью.

Шаг 2.

Изменить программу таким образом, чтобы она освобождала память, которую не занимает.

Шаг 3.

Изменить программу ещё раз таким образом, чтобы после освобождения памяти, программа запрашивала 64Кб памяти.

Шаг 2.

Изменить первоначальный вариант программы, запросив 64Кб памяти до освобождения памяти. Обработать завершение функций ядра, проверяя флаг CF.

Необходимые сведения для составления программы.

Учёт занятой и свободной памяти ведётся при помощи списка блоков управления памятью МСВ (Memory Control Block). МСВ занимает 16 байт (параграф) и располагается всегда с адреса кратного 16 (адреса сегмента ОП) и находится в адресном пространстве непосредственно перед тем участком памяти, которым он управляет.

МСВ имеет следующую структуру:

Смещение	Длина поля (байт)	Содержимое поля	
00h	1	тип МСВ:	
		5Аh, если последний в списке,	
		4Dh, если не последний	
01h 2	2	Сегментный адрес PSP владельца участка памяти, либо	
		0000h - свободный участок,	
		0006h - участок принадлежит драйверу OS XMS UMB	
		0007h - участок является исключенной верхней памятью драйверов	
		0008h - участок принадлежит MS DOS	
		FFFAh - участок занят управляющим блоком 386MAX UMB	
		FFFDh - участок заблокирован 386MAX	
		FFFEh - участок принадлежит 386MAX UMB	
03h	2	Размер участка в параграфах	
05h	3	Зарезервирован	
08h	8	"SC" - если участок принадлежит MS DOS, то в нем системный код	
		"SD" - если участок принадлежит MS DOS, то в нем системные данные	

По сегментному адресу и размеру участка памяти, контролируемого этим МСВ можно определить местоположение следующего МСВ в списке.

Адрес первого MCB хранится во внутренней структуре MS DOS, называемой «List of Lists» (список списков).

Размер расширенной памяти находится в ячейках 30h, 31h CMOS. CMOS это энергонезависимая память, в которой хранится информация о конфигурации ПЭВМ.

Описание программы.

В результате выполнения лабораторной работы была написана программа, описание функций которой представлено ниже.

- DEC_WORD_PRINT вывод содержимого AX в десятичной системе счисления;
- HEX_BYTE_PRINT вспомогательная для HEX_WORD_PRINT процедура;
- HEX_WORD_PRINT вывод содержимого AX в шестнадцатиричной системе счисления;
- PRINT_STRING вывод строки из DX на экран;

- PRINT_AVL_MEMORY вывод количества доступной памяти (в килобайтах);
- PRINT_EXT_MEMORY вывод количества расширенной памяти (в килобайтах).
- PRINT MCB вывод списка MCB;
- FREE MEM (для пунктов 2 4) освобождение незанятой памяти;
- ALLOC MEM (для пунктов 3 4) выделение 64Кб памяти.

Ход работы

Написание исходного кода производилось в редакторе Atom на базе операционной системы Windows 10, сборка и отладка производились в эмуляторе DOSBox.

Модуль под названием NOFREE.COM выводит на экран размер доступной и расширенной памяти, а также данные MCB блоков.

```
R:\>nofree.com
Available memory: 640 kbytes
Extended memory: 15360 kbytes
MCBs:
MCB number 1
Block is occupied by MS DOS, size = 16 bytes; occupied by: no info
MCB number 2
Block is free, size = 64 bytes; occupied by: no info
MCB number 3
Block is owned by PSP = 0040, size = 256 bytes; occupied by: no info
MCB number 4
Block is owned by PSP = 0192, size = 144 bytes; occupied by: no info
MCB number 5
Block is owned by PSP = 0192, size = 648912 bytes; occupied by: NOFREE
```

Программа занимает всю доступную память.

Модуль под названием FREE.COM освобождает память, которая не занята программой.

```
R:\>free.com
Available memory: 640 kbytes
Extended memory: 15360 kbytes
MCBs:
1CB number 1
Block is occupied by MS DOS, size = 16 bytes; occupied by: no info
MCB number 2
Block is free, size = 64 bytes; occupied by: no info
MCB number 3
Block is owned by PSP = 0040, size = 256 bytes; occupied by: no info
MCB number 4
Block is owned by PSP = 0192, size = 144 bytes; occupied by: no info
MCB number 5
Block is owned by PSP = 0192, size = 1072 bytes; occupied by: FREE
MCB number 6
Block is free, size = 647824 bytes; occupied by: δπt+♥4δτ
```

Теперь программа занимает не всю память, освобождённая память относится к новому, свободному блоку.

Модуль под названием NOFREE64.COM освобождает память, которая не занята программой, а потом запрашивает 64Кб памяти.

```
R:\>nofree64.com
Available memory: 640 kbytes
Extended memory: 15360 kbytes
MCBs:
MCB number 1
Block is occupied by MS DOS, size = 16 bytes; occupied by: no info
MCB number 2
Block is free, size = 64 bytes; occupied by: no info
MCB number 3
Block is owned by PSP = 0040, size = 256 bytes; occupied by: no info
MCB number 4
Block is owned by PSP = 0192, size = 144 bytes; occupied by: no info
MCB number 5
Block is owned by PSP = 0192, size = 1136 bytes; occupied by: NOFREE64
MCB number 6
Block is owned by PSP = 0192, size = 65536 bytes; occupied by: NOFREE64
MCB number 7
Block is free, size = 582208 bytes; occupied by: nteger d
```

Дополнительная память была выделена отдельным блоком, а блок, который появился после освобождения незанятой памяти, остался неизменным.

Модуль под названием FREE64.COM сначала запрашивает 64 Кб памяти, а потом освобождает незанятое.

```
R:\>free64.com
Some error occures during memory allocating.
Available memory: 640 kbytes
Extended memory: 15360 kbytes
1CBs:
1CB number 1
Block is occupied by MS DOS, size = 16 bytes; occupied by: no info
MCB number 2
Block is free, size = 64 bytes; occupied by: no info
MCB number 3
Block is owned by PSP = 0040, size = 256 bytes; occupied by: no info
1CB number 4
Block is owned by PSP = 0192, size = 144 bytes; occupied by: no info
MCB number 5
Block is owned by PSP = 0192, size = 1136 bytes; occupied by: FREE64
MCB number 6
Block is free, size = 647760 bytes; occupied by: ♥^δ
                                                        â·u
```

Дополнительная память не была выделена, так как на момент попытки выделения вся доступная память уже принадлежит программе, о чём свидетельствует сообщение в начале вывода. Под программу выделено меньше 64Кб.

Вывод.

В результате выполнения данной лабораторной работы был изучен список блоков управления памятью, а также методы выделения и освобождения памяти для программы.

Контрольные вопросы.

Что означает «доступный объём» памяти:

Максимальный объём памяти, доступный для запуска и выполнения программ.

Где МСВ блок Вашей программы в списке:

Принадлежность блока памяти можно определить, по адресу его владельца (расположенному со смещением в один байт в МСВ). Также название модуля-владельца может содержаться в последних восьми байтах МСВ. Как видно из вывода программы, ей обычно принадлежит два блока, первый из которых имеет фиксированный размер в 144 байта, а второй зависит от размера исходного кода. Также программе будет принадлежать запрошенная и выделенная память.

Какой размер памяти программа занимает в каждом случае:

Без освобождения памяти программа занимает 144 байта и всю свободную память. После освобождения она занимает 144 байта + около 1000 байтов (в каждом случае это зависит от исходного кода), для измерения размера вычисляется ближайший к концу модуля адрес конца параграфа и к нему добавляется ещё 16 байт. Также при запросе и успешном выделении дополнительной памяти, программа также занимает и её.

ПРИЛОЖЕНИЕ А

ИСХОДНЫЙ КОД ПРОГРАММЫ. NOFREE.ASM

LAB segment

ASSUME cs: LAB, ds: LAB, es: NOTHING, ss: NOTHING org 100h

START: jmp BEGIN

AVL_MEMORY_INFO db "Available memory: \$"

MCB INFO db "MCBs:", ODh, OAh, "\$"

MCB NUM INFO db "MCB number \$"

AREA SIZE INFO db ", size = \$"

OCCUPANT INFO db "; occupied by: \$"

END LINE db 0Dh, 0Ah, "\$"

BYTES db "bytes\$"

KBYTES db "kbytes", ODh, OAh, "\$"

OWNER_INFO db ODh, OAh, "Block is \$"

OWNER UNKNOWN db "owned by PSP = \$"

OWNER FREE db "free\$"

OWNER XMS db "occupied by OS XMS UMB\$"

```
OWNER TM db "occupied by driver's top memory$"
                    db "occupied by MS DOS$"
OWNER DOS
OWNER 386CB db "busy by 386MAX UMB$"
OWNER 386B
                    db "blocked by 386MAX$"
OWNER 386
                    db "occupied by 386MAX UMB$"
OCCUPANT_UNKNOWN db "no info$"
PRINT STRING PROC NEAR; (DX: String)
    push ax
    mov ah, 09h
    int 21h
    pop ax
    ret
PRINT STRING ENDP
DEC WORD PRINT PROC NEAR; (AX: short)
    push ax
```

push cx

```
push dx
    push bx
    mov bx, 10
    xor cx, cx
NUM:
    div bx
    push dx
    xor dx, dx
    inc cx
    cmp ax, 0h
    jnz NUM
PRINT NUM:
    pop dx
    or dl, 30h
    mov ah, 02h
    int 21h
    loop PRINT NUM
    pop bx
    pop dx
    pop cx
```

```
pop ax
```

ret

DEC_WORD_PRINT ENDP

HEX_BYTE_PRINT PROC NEAR ; (AL : byte)

push ax

push bx

push dx

mov ah, 0

mov bl, 10h

div bl

mov dx, ax

mov ah, 02h

cmp dl, OAh

jl PRINT

add dl, 07h

PRINT:

add dl, '0'

int 21h;

mov dl, dh

cmp dl, OAh

```
jl PRINT EXT
    add dl, 07h
PRINT_EXT:
    add dl, '0'
    int 21h;
    pop dx
    pop bx
    pop ax
    ret
HEX_BYTE_PRINT ENDP
HEX_WORD_PRINT PROC NEAR ; (AX : short)
    push ax
    push ax
    mov al, ah
    call HEX_BYTE_PRINT
    pop ax
    call HEX BYTE PRINT
    pop ax
    ret
HEX WORD PRINT ENDP
```

;-----

PRINT_AVL_MEMORY PROC NEAR

push ax

push bx

push dx

mov dx, offset AVL_MEMORY_INFO

call PRINT STRING

xor ax, ax

int 12h

xor dx, dx

call DEC_WORD_PRINT

mov dx, offset KBYTES

call PRINT_STRING

pop dx

pop bx

pop ax

ret

PRINT AVL MEMORY ENDP

PRINT EXT MEMORY PROC NEAR

push ax

push bx

push dx

mov dx, offset EXT MEMORY INFO

call PRINT_STRING

mov al, 30h

out 70h, al

in al, 71h

mov bl, al

mov al, 31h

out 70h, al

in al, 71h

mov ah, al

mov al, bl

xor dx, dx

call DEC WORD PRINT

mov dx, offset KBYTES

call PRINT_STRING

```
pop dx
pop bx
pop ax
ret

PRINT_EXT_MEMORY ENDP

PRINT_MCB PROC near
push ax
```

push ax

push bx

push cx

push dx

push es

push si

mov dx, offset MCB_INFO
call PRINT_STRING

mov ah, 52h
int 21h
mov ax, es:[bx-2]
mov es, ax
xor cx, cx

push cx

```
NEXT MCB:
   pop cx
   mov dx, offset MCB_NUM_INFO
   call PRINT_STRING
   inc cx
   mov ax, cx
   xor dx, dx
   call DEC_WORD_PRINT
   push cx
OWNER START:
    mov dx, offset OWNER_INFO
    call PRINT STRING
    mov ax, es:[1h]
    cmp ax, 0h
    je PRINT_FREE
    cmp ax, 6h
    je PRINT XMS
    cmp ax, 7h
    je PRINT_TM
    cmp ax, 8h
    je PRINT_DOS
```

cmp ax, OFFFAh

```
je PRINT 386CB
```

cmp ax, OFFFDh

je PRINT_386B

cmp ax, OFFFEh

je PRINT 386

mov dx, offset OWNER_UNKNOWN

call PRINT STRING

call HEX WORD PRINT

jmp AREA SIZE

PRINT_FREE:

mov dx, offset OWNER FREE

call PRINT STRING

jmp AREA SIZE

PRINT XMS:

mov dx, offset OWNER_XMS

call PRINT STRING

jmp AREA SIZE

PRINT TM:

mov dx, offset OWNER_TM

call PRINT_STRING

jmp AREA_SIZE

PRINT DOS:

```
mov dx, offset OWNER DOS
   call PRINT STRING
    jmp AREA_SIZE
PRINT 386CB:
    mov dx, offset OWNER 386CB
   call PRINT_STRING
    jmp AREA SIZE
PRINT 386B:
    mov dx, offset OWNER 386B
   call PRINT STRING
    jmp AREA SIZE
PRINT_386:
    mov dx, offset OWNER 386
    call PRINT STRING
AREA SIZE:
    mov dx, offset AREA_SIZE_INFO
    call PRINT STRING
    mov ax, es:[3h]
    mov bx, 10h
```

mul bx

call DEC_WORD_PRINT

mov dx, offset BYTES

call PRINT STRING

mov dx, offset OCCUPANT_INFO

call PRINT STRING

mov ax, es:[8h]

cmp ax, 0h

je NO_OCCUPANT

mov cx, 8

xor si, si

OCCUPANT:

mov dl, es:[si + 8h]

mov ah, 02h

int 21h

inc si

loop OCCUPANT

jmp PROCEEDING

NO_OCCUPANT:

mov dx, offset OCCUPANT_UNKNOWN

call PRINT STRING

PROCEEDING:

xor ax, ax

mov al, es:[0h]

cmp al, 5Ah

je ENDING

mov ax, es:[3h]

mov bx, es

add bx, ax

inc bx

mov es, bx

mov dx, offset END LINE

call PRINT STRING

jmp NEXT MCB

ENDING:

pop cx

pop si

pop es

pop dx

pop cx

pop bx

pop ax

PRINT MCB ENDP

BEGIN:

call PRINT_AVL_MEMORY

call PRINT_EXT_MEMORY

call PRINT MCB

xor al, al

mov ah, 4Ch

int 21h

PROGRAMM END:

LAB ends

end START

ПРИЛОЖЕНИЕ Б

ИСХОДНЫЙ КОД ПРОГРАММЫ. FREE.ASM

LAB segment

ASSUME cs: LAB, ds: LAB, es: NOTHING, ss: NOTHING

org 100h

START: jmp BEGIN

AVL MEMORY INFO db "Available memory: \$"

EXT MEMORY INFO db "Extended memory: \$"

MCB INFO db "MCBs:", ODh, OAh, "\$"

MCB NUM INFO db "MCB number \$"

AREA SIZE INFO db ", size = \$"

OCCUPANT INFO db "; occupied by: \$"

END LINE db 0Dh, 0Ah, "\$"

BYTES db "bytes\$"

KBYTES db "kbytes", ODh, OAh, "\$"

OWNER_INFO db ODh, OAh, "Block is \$"

OWNER UNKNOWN db "owned by PSP = \$"

OWNER FREE db "free\$"

OWNER XMS db "occupied by OS XMS UMB\$"

OWNER TM db "occupied by driver's top memory\$" db "occupied by MS DOS\$" OWNER DOS OWNER_386CB db "busy by 386MAX UMB\$" OWNER 386B db "blocked by 386MAX\$" OWNER 386 db "occupied by 386MAX UMB\$" OCCUPANT UNKNOWN db "no info\$" FREEING_ERROR db "Some error occures during memory freeing.", ODh, OAh, "\$" ;------PRINT STRING PROC NEAR; (DX: String) push ax mov ah, 09h int 21h pop ax ret PRINT STRING ENDP

DEC WORD PRINT PROC NEAR; (AX: short)

push ax

push cx

push dx

push bx

mov bx, 10

xor cx, cx

NUM:

div bx

push dx

xor dx, dx

inc cx

cmp ax, 0h

jnz NUM

PRINT_NUM:

pop dx

or dl, 30h

mov ah, 02h

int 21h

loop PRINT_NUM

pop bx

```
pop dx
   pop cx
    pop ax
    ret
DEC_WORD_PRINT ENDP
HEX_BYTE_PRINT PROC NEAR ; (AL : byte)
   push ax
    push bx
    push dx
    mov ah, 0
    mov bl, 10h
    div bl
    mov dx, ax
    mov ah, 02h
    cmp dl, OAh
    jl PRINT
    add dl, 07h
PRINT:
    add dl, '0'
```

int 21h;

```
cmp dl, 0Ah
    jl PRINT_EXT
    add dl, 07h
PRINT EXT:
    add dl, '0'
    int 21h;
   pop dx
    pop bx
    pop ax
    ret
HEX BYTE PRINT ENDP
HEX WORD PRINT PROC NEAR ; (AX : short)
    push ax
    push ax
    mov al, ah
    call HEX BYTE PRINT
    pop ax
    call HEX_BYTE_PRINT
    pop ax
    ret
```

mov dl, dh

```
;-----
```

FREE MEM PROC NEAR

push ax

push bx

push cx

push dx

mov bx, offset PROGRAMM END

mov cl, 4

shr bx, cl

add bx, 1

mov ah, 4Ah

int 21h

jnc FREE_SUCCESS

FREE ERROR:

mov dx, offset FREEING_ERROR

call PRINT STRING

FREE SUCCESS:

pop dx

pop cx

pop bx

pop ax

ret

FREE MEM ENDP

PRINT AVL MEMORY PROC NEAR

push ax

push bx

push dx

mov dx, offset AVL MEMORY INFO

call PRINT STRING

xor ax, ax

int 12h

xor dx, dx

call DEC_WORD_PRINT

mov dx, offset KBYTES

call PRINT_STRING

pop dx

```
pop bx
```

pop ax

ret

PRINT AVL MEMORY ENDP

PRINT EXT MEMORY PROC NEAR

push ax

push bx

push dx

mov dx, offset EXT MEMORY INFO

call PRINT_STRING

mov al, 30h

out 70h, al

in al, 71h

mov bl, al

mov al, 31h

out 70h, al

in al, 71h

mov ah, al

mov al, bl

xor dx, dx

call DEC_WORD_PRINT

mov dx, offset KBYTES

call PRINT_STRING

pop dx

pop bx

pop ax

ret

PRINT EXT MEMORY ENDP

PRINT MCB PROC near

push ax

push bx

push cx

push dx

push es

push si

mov dx, offset MCB_INFO

call PRINT_STRING

mov ah, 52h

int 21h

mov ax, es: [bx-2]

```
mov es, ax
   xor cx, cx
   push cx
NEXT_MCB:
   pop cx
   mov dx, offset MCB NUM INFO
   call PRINT_STRING
   inc cx
   mov ax, cx
   xor dx, dx
   call DEC_WORD_PRINT
   push cx
OWNER START:
    mov dx, offset OWNER INFO
    call PRINT_STRING
    mov ax, es:[1h]
    cmp ax, 0h
    je PRINT_FREE
    cmp ax, 6h
    je PRINT_XMS
```

cmp ax, 7h

```
je PRINT TM
    cmp ax, 8h
    je PRINT_DOS
    cmp ax, OFFFAh
    je PRINT_386CB
    cmp ax, OFFFDh
    je PRINT 386B
    cmp ax, OFFFEh
    je PRINT 386
   mov dx, offset OWNER UNKNOWN
   call PRINT_STRING
    call HEX WORD PRINT
    jmp AREA SIZE
PRINT FREE:
   mov dx, offset OWNER_FREE
   call PRINT STRING
    jmp AREA SIZE
PRINT XMS:
   mov dx, offset OWNER_XMS
   call PRINT STRING
```

jmp AREA SIZE

PRINT TM:

```
mov dx, offset OWNER TM
   call PRINT STRING
    jmp AREA_SIZE
PRINT DOS:
    mov dx, offset OWNER DOS
   call PRINT STRING
    jmp AREA SIZE
PRINT 386CB:
    mov dx, offset OWNER 386CB
   call PRINT STRING
    jmp AREA_SIZE
    mov dx, offset OWNER 386B
   call PRINT STRING
    jmp AREA SIZE
```

PRINT_386B:

PRINT 386:

mov dx, offset OWNER_386 call PRINT STRING

AREA SIZE:

mov dx, offset AREA_SIZE_INFO call PRINT STRING

mov ax, es:[3h]

mov bx, 10h

mul bx

call DEC_WORD_PRINT

mov dx, offset BYTES

call PRINT STRING

mov dx, offset OCCUPANT_INFO

call PRINT_STRING

mov ax, es:[8h]

cmp ax, 0h

je NO OCCUPANT

mov cx, 8

xor si, si

OCCUPANT:

mov dl, es:[si + 8h]

mov ah, 02h

int 21h

inc si

loop OCCUPANT

jmp PROCEEDING

NO OCCUPANT:

mov dx, offset OCCUPANT_UNKNOWN
call PRINT_STRING

PROCEEDING:

xor ax, ax

mov al, es:[0h]

cmp al, 5Ah

je ENDING

mov ax, es:[3h]

mov bx, es

add bx, ax

inc bx

mov es, bx

mov dx, offset END_LINE

call PRINT STRING

jmp NEXT_MCB

ENDING:

pop cx

pop si

pop es

pop dx

pop cx

pop bx

pop ax

ret

PRINT MCB ENDP

BEGIN:

call FREE_MEM

call PRINT_AVL_MEMORY

call PRINT_EXT_MEMORY

call PRINT MCB

xor al, al

mov ah, 4Ch

int 21h

PROGRAMM END:

LAB ends

end START

ПРИЛОЖЕНИЕ В

ИСХОДНЫЙ КОД ПРОГРАММЫ. NOFREE64.ASM

LAB segment

ASSUME cs: LAB, ds: LAB, es: NOTHING, ss: NOTHING

org 100h

START: jmp BEGIN

AVL_MEMORY_INFO db "Available memory: \$"

MCB INFO db "MCBs:", ODh, OAh, "\$"

MCB NUM INFO db "MCB number \$"

AREA SIZE INFO db ", size = \$"

OCCUPANT INFO db "; occupied by: \$"

END LINE db 0Dh, 0Ah, "\$"

BYTES db "bytes\$"

KBYTES db "kbytes", ODh, OAh, "\$"

OWNER_INFO db ODh, OAh, "Block is \$"

OWNER UNKNOWN db "owned by PSP = \$"

OWNER FREE db "free\$"

OWNER XMS db "occupied by OS XMS UMB\$"

OWNER TM db "occupied by driver's top memory\$" db "occupied by MS DOS\$" OWNER DOS OWNER 386CB db "busy by 386MAX UMB\$" OWNER 386B db "blocked by 386MAX\$" OWNER 386 db "occupied by 386MAX UMB\$" OCCUPANT UNKNOWN db "no info\$" FREEING ERROR db "Some error occures during memory freeing.", ODh, OAh, "\$" ALLOCATING ERROR db "Some error occures during memory allocating.", ODh, OAh, "\$" _____ PRINT STRING PROC NEAR; (DX: String) push ax mov ah, 09h int 21h pop ax ret

PRINT STRING ENDP

```
DEC_WORD_PRINT PROC NEAR ; (AX : short)
    push ax
    push cx
    push dx
    push bx
    mov bx, 10
    xor cx, cx
NUM:
    div bx
    push dx
    xor dx, dx
    inc cx
    cmp ax, 0h
    jnz NUM
PRINT_NUM:
    pop dx
    or dl, 30h
    mov ah, 02h
    int 21h
```

loop PRINT_NUM

```
bob px
```

pop dx

pop cx

pop ax

ret

DEC_WORD_PRINT ENDP

HEX_BYTE_PRINT PROC NEAR ; (AL : byte)

push ax

push bx

push dx

mov ah, 0

mov bl, 10h

div bl

mov dx, ax

mov ah, 02h

cmp dl, 0Ah

jl PRINT

add dl, 07h

PRINT:

add dl, '0'

```
int 21h;
    mov dl, dh
    cmp dl, 0Ah
    jl PRINT_EXT
    add dl, 07h
PRINT EXT:
    add dl, '0'
    int 21h;
    pop dx
    pop bx
    pop ax
    ret
HEX BYTE PRINT ENDP
HEX_WORD_PRINT PROC NEAR ; (AX : short)
    push ax
    push ax
    mov al, ah
    call HEX_BYTE_PRINT
    pop ax
    call HEX_BYTE_PRINT
```

```
pop ax
    ret
HEX_WORD_PRINT ENDP
_____
FREE MEM PROC NEAR
    push ax
   push bx
    push cx
    push dx
   mov bx, offset PROGRAMM_END
    mov cl, 4
    shr bx, cl
    add bx, 1
    mov ah, 4Ah
    int 21h
    jnc FREE_SUCCESS
FREE ERROR:
    mov dx, offset FREEING ERROR
```

call PRINT STRING

FREE SUCCESS:

pop dx

pop cx

pop bx

pop ax

ret

FREE MEM ENDP

ALLOC MEM PROC NEAR

push ax

push bx

push cx

push dx

mov bx, 1000h

mov ah, 48h

int 21h

jnc FREE_SUCCESS

ALLOC_ERROR:

mov dx, offset ALLOCATING_ERROR

call PRINT_STRING

```
ALLOC SUCCESS:
```

pop dx

pop cx

pop bx

pop ax

ret

ALLOC MEM ENDP

PRINT_AVL_MEMORY PROC NEAR

push ax

push bx

push dx

mov dx, offset AVL_MEMORY_INFO

call PRINT STRING

xor ax, ax

int 12h

xor dx, dx

call DEC_WORD PRINT

mov dx, offset KBYTES

call PRINT_STRING

```
pop dx
```

pop bx

pop ax

ret

PRINT AVL MEMORY ENDP

PRINT EXT MEMORY PROC NEAR

push ax

push bx

push dx

mov dx, offset EXT_MEMORY_INFO

call PRINT STRING

mov al, 30h

out 70h, al

in al, 71h

mov bl, al

mov al, 31h

out 70h, al

in al, 71h

mov ah, al

mov al, bl

xor dx, dx

call DEC WORD PRINT

mov dx, offset KBYTES

call PRINT_STRING

pop dx

pop bx

pop ax

ret

PRINT EXT MEMORY ENDP

PRINT_MCB PROC near

push ax

push bx

push cx

push dx

push es

push si

mov dx, offset MCB INFO

call PRINT_STRING

mov ah, 52h

int 21h

```
mov ax, es: [bx-2]
    mov es, ax
    xor cx, cx
   push cx
NEXT MCB:
   pop cx
   mov dx, offset MCB_NUM_INFO
   call PRINT STRING
   inc cx
   mov ax, cx
    xor dx, dx
   call DEC WORD PRINT
   push cx
OWNER START:
    mov dx, offset OWNER_INFO
    call PRINT_STRING
    mov ax, es:[1h]
    cmp ax, 0h
    je PRINT_FREE
    cmp ax, 6h
    je PRINT_XMS
```

```
cmp ax, 7h
```

je PRINT TM

cmp ax, 8h

je PRINT DOS

cmp ax, OFFFAh

je PRINT_386CB

cmp ax, 0FFFDh

je PRINT 386B

cmp ax, OFFFEh

je PRINT 386

mov dx, offset OWNER_UNKNOWN

call PRINT STRING

call HEX WORD PRINT

jmp AREA SIZE

PRINT_FREE:

mov dx, offset OWNER FREE

call PRINT STRING

jmp AREA SIZE

PRINT_XMS:

mov dx, offset OWNER XMS

call PRINT_STRING

jmp AREA SIZE

```
PRINT TM:
```

mov dx, offset OWNER TM

call PRINT_STRING

jmp AREA SIZE

PRINT DOS:

mov dx, offset OWNER DOS

call PRINT STRING

jmp AREA SIZE

PRINT 386CB:

mov dx, offset OWNER 386CB

call PRINT STRING

jmp AREA_SIZE

PRINT 386B:

mov dx, offset OWNER 386B

call PRINT_STRING

jmp AREA SIZE

PRINT_386:

mov dx, offset OWNER 386

call PRINT STRING

AREA_SIZE:

mov dx, offset AREA_SIZE_INFO

call PRINT STRING

```
mov ax, es:[3h]
```

mov bx, 10h

mul bx

call DEC_WORD_PRINT

mov dx, offset BYTES

call PRINT_STRING

mov dx, offset OCCUPANT_INFO

call PRINT_STRING

mov ax, es:[8h]

cmp ax, 0h

je NO_OCCUPANT

mov cx, 8

xor si, si

OCCUPANT:

mov dl, es:[si + 8h]

mov ah, 02h

int 21h

inc si

loop OCCUPANT

jmp PROCEEDING

NO OCCUPANT:

mov dx, offset OCCUPANT_UNKNOWN

call PRINT_STRING

PROCEEDING:

xor ax, ax

mov al, es:[0h]

cmp al, 5Ah

je ENDING

mov ax, es:[3h]

mov bx, es

add bx, ax

inc bx

mov es, bx

mov dx, offset END_LINE

call PRINT_STRING

jmp NEXT_MCB

ENDING:

pop cx

pop si

pop es

pop dx

pop cx

pop bx

pop ax

ret

PRINT MCB ENDP

BEGIN:

call FREE_MEM

call ALLOC MEM

call PRINT_AVL_MEMORY

call PRINT_EXT_MEMORY

call PRINT MCB

xor al, al

mov ah, 4Ch

int 21h

PROGRAMM_END:

LAB ends

end START

ПРИЛОЖЕНИЕ Г

ИСХОДНЫЙ КОД ПРОГРАММЫ. FREE64.ASM

LAB segment

ASSUME cs: LAB, ds: LAB, es: NOTHING, ss: NOTHING

org 100h

START: jmp BEGIN

AVL_MEMORY_INFO db "Available memory: \$"

MCB INFO db "MCBs:", ODh, OAh, "\$"

MCB NUM INFO db "MCB number \$"

AREA SIZE INFO db ", size = \$"

OCCUPANT INFO db "; occupied by: \$"

END LINE db 0Dh, 0Ah, "\$"

BYTES db "bytes\$"

KBYTES db "kbytes", ODh, OAh, "\$"

OWNER_INFO db ODh, OAh, "Block is \$"

OWNER UNKNOWN db "owned by PSP = \$"

OWNER FREE db "free\$"

OWNER_XMS db "occupied by OS XMS UMB\$"

OWNER TM db "occupied by driver's top memory\$" db "occupied by MS DOS\$" OWNER DOS OWNER 386CB db "busy by 386MAX UMB\$" OWNER 386B db "blocked by 386MAX\$" OWNER 386 db "occupied by 386MAX UMB\$" OCCUPANT UNKNOWN db "no info\$" FREEING ERROR db "Some error occures during memory freeing.", ODh, OAh, "\$" ALLOCATING ERROR db "Some error occures during memory allocating.", ODh, OAh, "\$" _____ PRINT STRING PROC NEAR; (DX: String) push ax mov ah, 09h int 21h pop ax ret

PRINT STRING ENDP

```
DEC_WORD_PRINT PROC NEAR ; (AX : short)
    push ax
    push cx
    push dx
    push bx
    mov bx, 10
    xor cx, cx
NUM:
    div bx
    push dx
    xor dx, dx
    inc cx
    cmp ax, 0h
    jnz NUM
PRINT_NUM:
    pop dx
    or dl, 30h
    mov ah, 02h
    int 21h
```

loop PRINT_NUM

```
pop bx
```

pop dx

pop cx

pop ax

ret

DEC_WORD_PRINT ENDP

HEX_BYTE_PRINT PROC NEAR ; (AL : byte)

push ax

push bx

push dx

mov ah, 0

mov bl, 10h

div bl

mov dx, ax

mov ah, 02h

cmp dl, 0Ah

jl PRINT

add dl, 07h

PRINT:

add dl, '0'

```
int 21h;
    mov dl, dh
    cmp dl, 0Ah
    jl PRINT_EXT
    add dl, 07h
PRINT EXT:
    add dl, '0'
    int 21h;
    pop dx
    pop bx
    pop ax
    ret
HEX BYTE PRINT ENDP
HEX_WORD_PRINT PROC NEAR ; (AX : short)
    push ax
    push ax
    mov al, ah
    call HEX_BYTE_PRINT
    pop ax
    call HEX_BYTE_PRINT
```

```
pop ax
    ret
HEX_WORD_PRINT ENDP
_____
FREE MEM PROC NEAR
    push ax
   push bx
    push cx
    push dx
   mov bx, offset PROGRAMM_END
    mov cl, 4
    shr bx, cl
    add bx, 1
    mov ah, 4Ah
    int 21h
    jnc FREE_SUCCESS
FREE ERROR:
    mov dx, offset FREEING ERROR
```

call PRINT STRING

FREE SUCCESS:

pop dx

pop cx

pop bx

pop ax

ret

FREE MEM ENDP

ALLOC MEM PROC NEAR

push ax

push bx

push cx

push dx

mov bx, 1000h

mov ah, 48h

int 21h

jnc FREE_SUCCESS

ALLOC_ERROR:

mov dx, offset ALLOCATING_ERROR

call PRINT_STRING

```
ALLOC SUCCESS:
```

pop dx

pop cx

pop bx

pop ax

ret

ALLOC MEM ENDP

PRINT_AVL_MEMORY PROC NEAR

push ax

push bx

push dx

mov dx, offset AVL_MEMORY_INFO

call PRINT STRING

xor ax, ax

int 12h

xor dx, dx

call DEC_WORD PRINT

mov dx, offset KBYTES

call PRINT_STRING

```
pop dx
```

pop bx

pop ax

ret

PRINT AVL MEMORY ENDP

PRINT EXT MEMORY PROC NEAR

push ax

push bx

push dx

mov dx, offset EXT_MEMORY_INFO

call PRINT STRING

mov al, 30h

out 70h, al

in al, 71h

mov bl, al

mov al, 31h

out 70h, al

in al, 71h

mov ah, al

mov al, bl

xor dx, dx

call DEC WORD PRINT

mov dx, offset KBYTES

call PRINT_STRING

pop dx

pop bx

pop ax

ret

PRINT EXT MEMORY ENDP

PRINT_MCB PROC near

push ax

push bx

push cx

push dx

push es

push si

mov dx, offset MCB INFO

call PRINT_STRING

mov ah, 52h

int 21h

```
mov ax, es: [bx-2]
    mov es, ax
    xor cx, cx
   push cx
NEXT MCB:
   pop cx
   mov dx, offset MCB_NUM_INFO
   call PRINT STRING
   inc cx
   mov ax, cx
    xor dx, dx
   call DEC WORD PRINT
   push cx
OWNER START:
    mov dx, offset OWNER_INFO
    call PRINT_STRING
    mov ax, es:[1h]
    cmp ax, 0h
    je PRINT_FREE
    cmp ax, 6h
    je PRINT_XMS
```

```
cmp ax, 7h
```

je PRINT TM

cmp ax, 8h

je PRINT DOS

cmp ax, OFFFAh

je PRINT_386CB

cmp ax, 0FFFDh

je PRINT 386B

cmp ax, OFFFEh

je PRINT 386

mov dx, offset OWNER_UNKNOWN

call PRINT STRING

call HEX WORD PRINT

jmp AREA SIZE

PRINT_FREE:

mov dx, offset OWNER FREE

call PRINT STRING

jmp AREA SIZE

PRINT_XMS:

mov dx, offset OWNER XMS

call PRINT_STRING

jmp AREA SIZE

```
PRINT TM:
```

mov dx, offset OWNER TM

call PRINT_STRING

jmp AREA SIZE

PRINT DOS:

mov dx, offset OWNER DOS

call PRINT STRING

jmp AREA SIZE

PRINT 386CB:

mov dx, offset OWNER 386CB

call PRINT STRING

jmp AREA_SIZE

PRINT 386B:

mov dx, offset OWNER 386B

call PRINT_STRING

jmp AREA SIZE

PRINT_386:

mov dx, offset OWNER 386

call PRINT STRING

AREA_SIZE:

mov dx, offset AREA_SIZE_INFO

call PRINT STRING

```
mov ax, es:[3h]
```

mov bx, 10h

mul bx

call DEC_WORD_PRINT

mov dx, offset BYTES

call PRINT_STRING

mov dx, offset OCCUPANT_INFO

call PRINT_STRING

mov ax, es:[8h]

cmp ax, 0h

je NO_OCCUPANT

mov cx, 8

xor si, si

OCCUPANT:

mov dl, es:[si + 8h]

mov ah, 02h

int 21h

inc si

loop OCCUPANT

jmp PROCEEDING

NO OCCUPANT:

mov dx, offset OCCUPANT_UNKNOWN

call PRINT_STRING

PROCEEDING:

xor ax, ax

mov al, es:[0h]

cmp al, 5Ah

je ENDING

mov ax, es:[3h]

mov bx, es

add bx, ax

inc bx

mov es, bx

mov dx, offset END_LINE

call PRINT_STRING

jmp NEXT_MCB

ENDING:

pop cx

pop si

pop es

pop dx

pop cx

pop bx

pop ax

ret

PRINT MCB ENDP

BEGIN:

call ALLOC_MEM

call FREE MEM

call PRINT_AVL_MEMORY

call PRINT_EXT_MEMORY

call PRINT MCB

xor al, al

mov ah, 4Ch

int 21h

PROGRAMM_END:

LAB ends

end START