





操作系统

Operating Systems

刘川意 教授

<u>liuchuanyi@hit.edu.cn</u>

哈尔滨工业大学(深圳)

2021年10月

- 1. Concurrency Introduction
- 2. Locks
- 3. 基于Lock的并发数据结构
- 4. Condition Variables 条件变量
- 5. Semaphore 信号量
- 6. 常见并发问题
- 7. 基于事件的并发



Concurrency为什么放到OS中讲?

■ History !

- OS Kernel是第一个并发程序,如:write()的设计,中断对shared structures的影响(page tables, process lists, file system structures, and virtually every kernel data structure has to be carefully accessed)
- 很多并发处理技术是在OS中发明和实现的
- multi-threade进程中,应用程序也需要考虑并发



并发相关的重要术语

- Critical Section, a piece of code that accesses a shared resource, usually a variable or data structure
- Race Condition arises if multiple threads of execution enter the critical section at roughly the same time; both attempt to update the shared data structure, leading to a surprising (and perhaps undesirable) outcome.
- Indeterminate, program consists of one or more race conditions; the output of the program varies from run to run, depending on which threads ran when. The outcome is thus not **deterministic**, something we usually expect from computer systems.
- Mutual Exclusion primitives, guarantee that only a single thread ever enters a critical section, thus avoiding races, and resulting in deterministic program outputs



Review: Thread

- 轻量化执行环境, new abstraction for <u>a single running process</u>
- Multi-threaded 程序的特点:
 - A multi-threaded program has more than one point of execution.

- Multiple PCs (Program Counter)
- They share the same address space.




Context switch between threads

- Each thread has its own program counter and set of registers.
 - One or more thread control blocks(TCBs) are needed to store the state of each thread.
- When switching from running one (T1) to running the other (T2),
 - The register state of T1 be saved.
 - The register state of T2 restored.
 - The address space remains the same.



The stack of the relevant thread

There will be one stack per thread.




The code segment: where instructions live

The heap segment: contains malloc'd data dynamic data structures (it grows downward)

(it grows upward) **The stack segment**:
contains local variables
arguments to routines,
return values, etc.

A Single-Threaded Address Space



Two threaded Address Space



badcnt.c: Improper Synchronization

```
7. /* Global shared variable */
8. volatile long cnt = 0; /* Counter */
                                           38. /* Thread routine */
                                           39. void *thread(void *vargp)
17. int main(int argc, char **argv)
                                           40. {
18. {
                                                   long i, niters =
                                           41.
19.
      long niters;
                                                                *((long *)vargp);
                                           42.
       pthread t tid1, tid2;
20.
                                           43.
                                                   for (i = 0; i < niters; i++)</pre>
                                           44.
       niters = atoi(argv[1]);
21.
                                           45.
                                                        cnt++:
       Pthread create(&tid1, NULL,
22.
                                           46.
           thread, &niters);
23.
                                                   return NULL:
       Pthread create(&tid2, NULL,
                                           47.
24.
           thread, &niters);
                                           48. }
25.
       Pthread join(tid1, NULL);
26.
       Pthread join(tid2, NULL);
                                           [zs cao@localhost conc] $ ./badcnt 10000
27.
                                           OK cnt=20000
                                           [zs cao@localhost conc]$ ./badcnt 10000
      /* Check result */
28.
                                           B00M! cnt = 17302
       if (cnt != (2 * niters))
29.
                                           [zs cao@localhost conc] $ ./badcnt 10000
           printf("B00M! cnt=%ld\n",
30.
                                           OK cnt=20000
   cnt);
       else
31.
           printf("OK cnt=%ld\n", cnt);
32.
                                              线程并发执行的问题
       exit(0);
33.
                                  badcnt.c
34. }
```



Assembly Code for Counter Loop

■ 编译:

- gcc –s badcnt.c –o badcnt.s
- vim badcnt.s

```
for (i = 0; i < niters; i++)
     cnt++;</pre>
```

```
94
              %rdi, -24(%rbp)
        movq
95
               -24(%rbp), %rax
        movq
96
        movq (%rax), %rax
97
        movq %rax, -8(%rbp)
98
        movq $0, -16(%rbp)
99
        jmp
              .L6
100 .L7:
101
        movq cnt(%rip), %rax
102
        addq $1, %rax
103
        movq %rax, cnt(%rip)
104
        addq $1, -16(%rbp)
105 .L6:
106
               -16(%rbp), %rax
        movq
               -8(%rbp), %rax
107
        cmpq
108
        jl
109
        movl
               $0, %eax
110
               %rbp
        popq
```

 H_i : Head

 L_i : Load cnt

U_i: Update cnt

 S_i : Store cnt

 T_i : Tail



 H_i

 T_i

for (i = 0; i < niters; i++)

cnt++;

%rbp

Assembly Code for Counter Loop

■ 汇编:

130:

131:

5d

c3

```
gcc –c badcnt.s –o badcnt.o
```

gee e badentis e badentie

```
objdump -dx badcnt.o
00000000000000ed <thread>:
```

```
ed:
        55
                                 push
                                         %rbp
        48 89 e5
                                         %rsp,%rbp
  ee:
                                 mov
  f1:
        48 89 7d e8
                                         %rdi,-0x18(%rbp)
                                 mov
  f5:
        48 8b 45 e8
                                         -0x18(%rbp), %rax
                                 mov
  f9:
        48 8b 00
                                         (%rax),%rax
                                 mov
  fc:
        48 89 45 f8
                                         %rax,-0x8(%rbp)
                                  mov
 100:
       48 c7 45 f0 00 00 00
                                         $0x0,-0x10(%rbp)
                                 movq
 107:
        00
108:
        eb 17
                                  jmp
                                         121 <thread+0x34>
        48 8b 05 00 00 00 00
                                                                # 111
10a:
                                 mov
                                         0x0(%rip),%rax
<thread+0x24>
                         10d: R_X86_64_PC32
                                                  cnt-0x4
 111:
        48 83 c0 01
                                  add
                                         $0x1,%rax
                                                                # 11c
115:
        48 89 05 00 00 00 00
                                         %rax,0x0(%rip)
                                 mov
<thread+0x2f>
                         118: R_X86_64_PC32
                                                  cnt-0x4
 11c:
        48 83 45 f0 01
                                  addq
                                         $0x1,-0x10(%rbp)
 121:
        48 8b 45 f0
                                         -0x10(%rbp), %rax
                                 mov
 125:
        48 3b 45 f8
                                         -0x8(\%rbp),%rax
                                  cmp
 129:
        7c df
                                  jl
                                         10a <thread+0x1d>
 12b:
        b8 00 00 00 00
                                         $0x0,%eax
                                 mov
```

pop

retq



Assembly Code for Counter Loop

■ 链接:

gcc –o badcnt.c –o badcnt -lpthread

for (i = 0; i < niters; i++)
 cnt++;</pre>

objdump -d badcnt

```
怎么计算?
0000000000000957 <thread>:
 957:
        55
                                   push
                                           %rbp
 958:
        48 89 e5
                                           %rsp,%rbp
                                   mov
                                           %rdi,-0x18(%/bp)
 95b:
        48 89 7d e8
                                   mov
 95f:
        48 8b 45 e8
                                           -0x18(%rbp/), %rax
                                   mov
963:
        48 8b 00
                                           (%rax),%rax
                                   mov
                                                                    H_i
        48 89 45 f8
 966:
                                           %rax, -0x8(%rbp)
                                   mov
 96a:
        48 c7 45 f0 00 00 00
                                           \$0x0, -0x10(\%rbp)
                                   movq
 971:
        00
 972:
        eb 17
                                   jmp
                                           98b < thread+0x34>
        48 8b 05 b5 06 20 00
 974:
                                           0x2006b5(%rip),%rax
                                   mov
  # 201030
           <cnt>
                                                                    U_iS_i
 97b:
        48 83 c0 01
                                           $0x1,%rax
                                   add
 97f:
        48 89 05 aa 06 20 00
                                           %rax,0x2006aa(%rip)
                                   mov
 # 201030 <cnt>
 986:
        48 83 45 f0 01
                                   addq
                                           $0x1,-0x10(%rbp)
 98b:
        48 8b 45 f0
                                           -0x10(%rbp),%rax
                                   mov
 98f:
        48 3b 45 f8
                                           -0x8(\%rbp),\%rax
                                   cmp
                                                                    T_i
 993:
        7c df
                                           974 <thread+0x1d>
                                   jl
 995:
        b8 00 00 00 00
                                           $0x0,%eax
                                   mov
 99a:
        5d
                                           %rbp
                                   pop
 99b:
        c3
                                   retq
```



Race condition

■ 把上述示例简化一下:

- counter = counter + 1 (default is 50)
- We expect the result is 52. However,

OS	Thread1		Thread2	2		er instr %eax	uction) counter
	before crit	cical section	า		100	0	50
	mov 0x8049a1c, %eax			105	50	50	
	add \$0x1, %	eax			108	51	50
interrupt save T1's st	ate						
restore T2's	state				100	0	50
		mov	0x8049	alc, %eax	105	50	50
		add	\$0x1,	%eax	108	51	50
		mov	%eax,	0x8049a1c	113	51	51
interrupt save T2's sta							
restore T1's	state				108	51	50
	mov %eax, 0)x8049a1c			113	51	51



Critical section

- A piece of code that accesses a shared variable and must not be concurrently executed by more than one thread.
 - Multiple threads executing critical section can result in a race condition.
 - Need to support atomicity for critical sections (mutual exclusion)

公爾濱之業大學 HARBIN INSTITUTE OF TECHNOLOG

Locks

Ensure that any such critical section executes as if it were a single atomic instruction (execute a series of instructions atomically).

```
1  lock_t mutex;
2  . . .
3  lock(&mutex);
4  balance = balance + 1;
5  unlock(&mutex);
Critical section
```



Concurrent Execution(并发执行)

- Key idea: In general, any sequentially consistent interleaving is possible, but some give an unexpected result!
 - I_i denotes that thread i executes instruction I
 - %rdx_i is the content of %rdx in thread i's context

i (thread)	instr _i	$%$ rdx $_{1}$	%rdx ₂	cnt	
1	H ₁	-	-	0	
1	L_1	0	-	0	
1	$U_\mathtt{1}$	1	-	0	
1	S_1	1	-	1	
2	H_2	-	-	1	
2	L ₂	-	1	1	
2	U_2	-	2	1	
2	S_2	-	2	2	
2	T_2	-	2	2	
1	T_1	1	-	2	ОК

Thread 1 critical section

Thread 2 critical section



Concurrent Execution (cont)

Incorrect ordering: two threads increment the counter, but the result is 1 instead of 2


	i (thread)	instr _i	$%$ rd x_1	$%$ rd x_2	cnt
	1	H ₁	-	-	0
	1	L_1	0	-	0
	1	$U_\mathtt{1}$	1	ı	0
_	2	H ₂			0
	2	L ₂	-	0	0
	1	S_1	1	-	1
	1	\overline{T}_1	1	-	1
	2	U_2	-	1	1
	2	S_2	ı	1	1
	2	T_2	-	1	1

S1应该在L2之前执行

Oops!



Progress Graphs(进度图)



A *progress graph* depicts the discrete *execution state space* of concurrent threads.


Each axis corresponds to the sequential order of instructions in a thread.

Each point corresponds to a possible *execution state* (Inst₁, Inst₂).

E.g., (L_1, S_2) denotes state where thread 1 has completed L_1 and thread 2 has completed S_2 .




Trajectories in Progress Graphs




Critical Sections and Unsafe Regions





Critical Sections and Unsafe Regions







Enforcing Mutual Exclusion

- Question: How can we guarantee a safe trajectory?
- Answer: We must *synchronize* (同步)the execution of the threads so that they can never have an unsafe trajectory.
 - i.e., need to guarantee mutually exclusive access (互斥地访问) for each critical section.
- Classic solution:
 - Semaphores(信号量) (Edsger Dijkstra)
- Other approaches (out of our scope)
 - Mutex and condition variables (Pthreads)
 - Monitors (Java)

信号处理



【例题1】子进程运行结束会向父进程发送_____信号。

【例题2】异步信号安全的函数要么是可重入的,要么不能被信号处理程序中断,包括I/O函数()

A.printf

B.sprintf

C.write

D.malloc

答案: SIGCHLD/17号 C

- 1. Concurrency Introduction
- 2. Locks
- 3. 基于Lock的并发数据结构
- 4. Condition Variables 条件变量
- 5. Semaphore 信号量
- 6. 常见并发问题
- 7. 基于事件的并发



Locks: The Basic Idea

- Ensure that any **critical section** executes as if it were a single atomic instruction. "全部或都不"
 - Eg. update of a shared variable

```
balance = balance + 1;
```

Add some code around the critical section

```
1 lock_t mutex; // some globally-allocated lock 'mutex'
2 ...
3 lock(&mutex);
4 balance = balance + 1;
5 unlock(&mutex);
```

Lock变量



- Lock variable holds the state of the lock.
 - available (or unlocked or free)
 - No thread holds the lock.
 - acquired (or locked or held)
 - Exactly one thread holds the lock and presumably is in a critical section.



lock()原语的语义(semantics)

- lock()
 - Try to acquire the lock.
 - If no other thread holds the lock, the thread will acquire the lock.
 - Enter the critical section.
 - ▶ This thread is said to be the owner of the lock.
 - Other threads are prevented from entering the critical section while the first thread that holds the lock is in there.



Pthread Locks - mutex

- The name that the POSIX library uses for a <u>lock</u>.
 - Used to provide mutual exclusion between threads.

```
pthread_mutex_t lock = PTHREAD_MUTEX_INITIALIZER;

Pthread_mutex_lock(&lock); // wrapper for pthread_mutex_lock()
balance = balance + 1;
Pthread_mutex_unlock(&lock);
```

 We may be using different locks to protect different variables → Increase concurrency (a more fine-grained approach).



Lock如何实现?

- <u>Efficient locks</u> provided mutual exclusion at low cost.
- Building a lock need some help from the hardware and the OS.



如何评价lock原语?

■ Mutual exclusion 正确性

Does the lock work, preventing multiple threads from entering a critical section?

■ Fairness 公平性

 Does each thread contending for the lock get a fair shot at acquiring it once it is free? (Starvation)

■ Performance 性能

The time overheads added by using the lock

Controlling Interrupts 基于中断控制的锁实现

- **Disable Interrupts** for critical sections
 - One of the earliest solutions used to provide mutual exclusion
 - Invented for <u>single-processor</u> systems.

```
1  void lock() {
2    DisableInterrupts();
3  }
4  void unlock() {
5    EnableInterrupts();
6 }
```

Problem:

- Require too much trust in applications
 - Greedy (or malicious) program could monopolize the processor.
- ▶ Do not work on multiprocessors 多处理器体系结构这种方式不work
- Code that masks or unmasks interrupts be executed slowly by modern CPUs



Why hardware support needed?

- **First attempt**: Using a *flag* denoting whether the lock is held or not.
 - The code below has problems.

```
typedef struct lock t { int flag; } lock t;
    void init(lock t *mutex) {
         // 0 \rightarrow lock is available, 1 \rightarrow held
         mutex - > flag = 0;
6
    void lock(lock t *mutex) {
8
         while (mutex->flag == 1) // TEST the flag
9
                  ; // spin-wait (do nothing)
10
         mutex->flag = 1; // now SET it !
11
12
13
14
    void unlock(lock t *mutex) {
15
         mutex - > flag = 0;
16
```

Why hardware support needed? (Cont.)

Problem 1: No Mutual Exclusion (assume flag=0 to begin)

Thread1 Thread2

```
call lock()
while (flag == 1)
interrupt: switch to Thread 2
```

```
call lock()
while (flag == 1)
flag = 1;
interrupt: switch to Thread 1
```

• **Problem 2**: Spin-waiting wastes time waiting for another thread.

```
flag = 1; // set flag to 1 (too!)
```

- So, we need an atomic instruction supported by Hardware!
 - test-and-set instruction, also known as atomic exchange



基于Test-and-set硬件指令实现

An instruction to support the creation of simple locks

- return(testing) old value pointed to by the ptr.
- Simultaneously update(setting) said value to new.
- This sequence of operations is performed atomically.

A Simple Spin Lock using test-and-set

```
typedef struct lock t {
         int flag;
    } lock t;
    void init(lock t *lock) {
6
         // 0 indicates that lock is available,
         // 1 that it is held
         lock - > flag = 0;
10
11
    void lock(lock t *lock) {
12
         while (TestAndSet(&lock->flag, 1) == 1)
13
                           // spin-wait
14
15
16
    void unlock(lock t *lock) {
17
         lock - > flaq = 0;
18
```

- Note: To work correctly on a single processor, it requires a preemptive scheduler.
- 在单处理器体系结构中,需要OS kernel实现抢占式调度策略来支持



Evaluating Spin Locks

- Correctness: yes
 - The spin lock only allows a single thread to entry the critical section.
- **Fairness**: no
 - Spin locks don't provide any fairness guarantees.
 - Indeed, a thread spinning may spin forever.

Performance:

- In the single CPU, performance overheads can be quire painful.
- If the number of threads roughly equals the number of CPUs, spin locks work reasonably well.

HARB



基于Compare-And-Swap硬件指令实现

- Test whether the value at the address(ptr) is equal to expected.
 - If so, update the memory location pointed to by ptr with the new value.
 - In either case, return the actual value at that memory location.

Compare-and-Swap hardware atomic instruction (C-style)

```
void lock(lock_t *lock) {
while (CompareAndSwap(&lock->flag, 0, 1) == 1)
; // spin
}
```

Spin lock with compare-and-swap



Compare-And-Swap (Cont.)

C-callable x86-version of compare-and-swap

```
char CompareAndSwap(int *ptr, int old, int new) {
1
       unsigned char ret;
3
4
       // Note that sete sets a 'byte' not the word
         asm volatile (
               " lock\n"
6
               " cmpxchgl %2, %1\n"
               " sete %0\n"
8
9
               : "=q" (ret), "=m" (*ptr)
               : "r" (new), "m" (*ptr), "a" (old)
10
11
               : "memory");
12
     return ret;
13
```



```
哈爾濱Z業大學
HARBIN INSTITUTE OF TECHNOLOGY
```

```
int LoadLinked(int *ptr) {
    return *ptr;
}

int StoreConditional(int *ptr, int value) {
    if (no one has updated *ptr since the LoadLinked to this address) {
        *ptr = value;
        return 1; // success!
    } else {
        return 0; // failed to update
}
```

Load-linked And Store-conditional

- The store-conditional only succeeds if no intermittent store to the address has taken place.
 - success: return 1 and update the value at ptr to value.
 - fail: the value at ptr is not updates and 0 is returned.

Load-Linked and Store-Conditional (Cont.)

Using LL/SC To Build A Lock

```
void lock(lock_t *lock) {
    while (LoadLinked(&lock->flag)||!StoreConditional(&lock->flag, 1))
    ; // spin
}
```

A more concise form of the lock() using LL/SC



Fetch-And-Add

Atomically increment a value while returning the old value at a particular address.

```
1  int FetchAndAdd(int *ptr) {
2    int old = *ptr;
3    *ptr = old + 1;
4    return old;
5  }
```

Fetch-And-Add Hardware atomic instruction (C-style)



Ticket Lock

- Ticket lock can be built with <u>fetch-and add</u>.
 - Ensure progress for all threads. → fairness

```
typedef struct lock t {
         int ticket;
        int turn;
    } lock t;
    void lock init(lock t *lock) {
         lock - > ticket = 0;
         lock -> turn = 0;
10
11
    void lock(lock t *lock) {
12
         int myturn = FetchAndAdd(&lock->ticket);
13
        while (lock->turn != myturn)
14
                  ; // spin
15
16
    void unlock(lock t *lock) {
17
        FetchAndAdd(&lock->turn);
18
```



52

So Much Spinning

- Hardware-based spin locks are simple and they work.
- In some cases, these solutions can be quite inefficient.
 - Any time a thread gets caught spinning, it wastes an entire time slice doing nothing but checking a value.

How To Avoid *Spinning*? We'll need OS Support too!



- When you are going to spin, give up the CPU to another thread.
 - OS system call moves the caller from the running state to the ready state.
 - The cost of a context switch can be substantial and the starvation problem still exists.

```
1  void init() {
2    flag = 0;
3  }
4
5  void lock() {
6   while (TestAndSet(&flag, 1) == 1)
7       yield(); // give up the CPU
8  }
9  
10  void unlock() {
11   flag = 0;
12 }
```

Lock with Test-and-set and Yield

办法2: Using Queues: Sleeping, not Spinning

- Queue to keep track of which threads are <u>waiting</u> to enter the lock.
- park()
 - Put a calling thread to sleep
- unpark(threadID)
 - Wake a particular thread as designated by threadID.

54

Using Queues: Sleeping Instead of Spinning

```
typedef struct lock t { int flag; int guard; queue t *q; } lock t;
3
    void lock init(lock t *m) {
        m->flaq = 0;
        m->quard = 0;
        queue init(m->q);
    void lock(lock t *m) {
10
        while (TestAndSet(&m->quard, 1) == 1)
            ; // acquire guard lock by spinning
11
12
        if (m->flag == 0) {
13
            m->flag = 1; // lock is acquired
            m->quard = 0;
14
15
        } else {
16
            queue add(m->q, gettid());
17
            m->quard = 0;
18
            park();
19
20
21
```

Lock With Queues, Test-and-set, Yield, And Wakeup

Using Queues: Sleeping Instead of Spinning



```
22
   void unlock(lock t *m) {
23
        while (TestAndSet(&m->quard, 1) == 1)
2.4
            ; // acquire quard lock by spinning
25
        if (queue empty (m->q))
2.6
            m->flag = 0; // let go of lock; no one wants it
2.7
       else
28
            unpark(queue remove(m->q)); // hold lock (for next thread!)
29
        m->quard = 0;
30
```

Lock With Queues, Test-and-set, Yield, And Wakeup (Cont.)

56



Futex (Cont.)

```
16
                  if (v >= 0)
                           continue;
17
18
                  futex wait(mutex, v);
19
20
2.1
2.2
    void mutex unlock(int *mutex) {
23
         /* Adding 0x80000000 to the counter results in 0 if and only if
24
            there are not other interested threads */
2.5
         if (atomic add zero(mutex, 0x80000000))
26
                  return:
27
         /* There are other threads waiting for this mutex,
28
            wake one of them up */
29
         futex wake(mutex);
30
```

Linux-based Futex Locks (Cont.)



Two-Phase Locks

■ A two-phase lock realizes that spinning can be useful if the lock *is about to* be released.

First phase

- ▶ The lock spins for a while, *hoping that* it can acquire the lock.
- If the lock is not acquired during the first spin phase, a second phase is entered,

Second phase

- ▶ The caller is put to sleep.
- ▶ The caller is only woken up when the lock becomes free later.

- 1. Concurrency Introduction
- 2. Locks
- 3. 基于Lock的并发数据结构
- 4. Condition Variables 条件变量
- 5. Semaphore 信号量
- 6. 常见并发问题
- 7. 基于事件的并发

Lock-based Concurrent Data structure

- Adding locks to a data structure makes the structure thread safe.
 - How locks are added determine both the correctness and performance of the data structure.

Example: Concurrent Counter without Lock

Simple but not scalable

```
1
       typedef struct counter t {
               int value;
       } counter t;
       void init(counter t *c) {
               c->value = 0;
8
       void increment(counter t *c) {
10
               c->value++;
11
12
13
       void decrement(counter t *c) {
14
               c->value--;
15
16
17
       int get(counter_t *c) {
               return c->value;
18
19
```

Add a single lock




acquired when calling a routine manipulating the data structure.

```
1
         typedef struct counter t {
                  int value;
3
                  pthread lock t lock;
         } counter t;
6
         void init(counter t *c) {
                  c \rightarrow value = 0;
8
                  Pthread mutex init(&c->lock, NULL);
9
10
11
         void increment(counter t *c) {
                  Pthread mutex lock(&c->lock);
12
13
                  c->value++;
14
                  Pthread mutex unlock(&c->lock);
15 }
17
         void decrement(counter t *c) {
18
                  Pthread mutex lock(&c->lock);
19
                  c->value--;
20
                  Pthread mutex unlock(&c->lock);
21
22
23
         int get(counter t *c) {
24
                  Pthread mutex lock(&c->lock);
25
                  int rc = c->value;
26
                  Pthread mutex unlock(&c->lock);
27
                  return rc;
28
```

The performance cost of the simple approach

- Each thread updates a single shared counter.
 - Each thread updates the counter one million times.
 - iMac with four Intel 2.7GHz i5 CPUs.



Performance of Traditional vs. Sloppy Counters (Threshold of Sloppy, S, is set to 1024)

Synchronized counter scales poorly.



Perfect Scaling

- Even though more work is done, it is **done in parallel**.
- The time taken to complete the task is not increased.



Sloppy counter

- The sloppy counter works by representing ...
 - A single logical counter via numerous local physical counters, on per <u>CPU core</u>
 - A single global counter
 - There are locks:
 - One fore each local counter and one for the global counter
- Example: on a machine with four CPUs
 - Four local counters
 - One global counter



The basic idea of sloppy counting

- When a thread running on a core wishes to increment the counter.
 - It increment its local counter.
 - Each CPU has its own local counter:
 - ▶ Threads across CPUs can update local counters *without contention*.
 - Thus counter updates are scalable.
 - The local values are periodically transferred to the global counter.

69

- Acquire the global lock
- Increment it by the local counter's value
- The local counter is then reset to zero.

The basic idea of sloppy counting (Cont.)



- How often the local-to-global transfer occurs is determined by a threshold, S (sloppiness).
 - The smaller S:
 - The more the counter behaves like the non-scalable counter.
 - The bigger S:
 - The more scalable the counter.
 - ▶ The further off the global value might be from the actual count.



Sloppy counter example

- Tracing the Sloppy Counters
 - The threshold S is set to 5.
 - There are threads on each of 4 CPUs
 - Each thread updates their local counters $L_1 \dots L_4$.


Time	L_1	L ₂	L_3	$\mathbf{L_4}$	G
0	0	0	0	0	0
1	0	0	1	1	0
2	1	0	2	1	0
3	2	0	3	1	0
4	3	0	3	2	0
5	4	1	3	3	0
6	5 → 0	1	3	4	5 (from L_1)
7	0	2	4	5 → 0	10 (from L_4)

Importance of the threshold value \$\overline{S}\$





- Each four threads increments a counter 1 million times on four CPUs.
 - Low S → Performance is **poor**, The global count is always quire accurate.
 - High S → Performance is excellent, The global count lags.



Scaling Sloppy Counters



Sloppy Counter Implementation

```
1
      typedef struct counter t {
          int global;
                             // global count
          int local[NUMCPUS]; // local count (per cpu)
          pthread mutex t llock[NUMCPUS]; // ... and locks
6
          int threshold;  // update frequency
      } counter t;
8
9
      // init: record threshold, init locks, init values
10
              of all local counts and global count
      void init(counter t *c, int threshold) {
11
12
          c->thres hold = threshold;
13
14
          c->global = 0;
15
          pthread mutex init(&c->glock, NULL);
16
17
          int i;
          for (i = 0; i < NUMCPUS; i++) {</pre>
18
19
              c->local[i] = 0;
20
              pthread mutex init(&c->llock[i], NULL);
21
22
23
```

Sloppy Counter Implementation (Cent) 新原之業大學

```
(Cont.)
      // update: usually, just grab local lock and update local
24
amount
25
      //
                 once local count has risen by 'threshold', grab
global
26
                 lock and transfer local values to it
27
       void update(counter t *c, int threadID, int amt) {
28
           pthread mutex lock(&c->llock[threadID]);
29
           c->local[threadID] += amt; // assumes amt > 0
30
           if (c->local[threadID] >= c->threshold) { // transfer
to global
31
               pthread mutex lock(&c->glock);
32
               c->qlobal += c->local[threadID];
33
               pthread mutex unlock(&c->glock);
34
               c->local[threadID] = 0;
35
36
          pthread mutex unlock(&c->llock[threadID]);
37
38
39
       // get: just return global amount (which may not be perfect)
40
       int get(counter t *c) {
           pthread mutex lock(&c->glock);
41
42
           int val = c->global;
43
           pthread mutex unlock(&c->glock);
44
           return val; // only approximate!
45
```



Concurrent Linked Lists

```
// basic node structure
1
       typedef struct   node t {
3
               int key;
4
               struct _ node t *next;
5
        } node t;
       // basic list structure (one used per list)
8
       typedef struct list t {
9
               node t *head;
10
               pthread mutex t lock;
11
       } list t;
12
13
       void List Init(list t *L) {
               L->head = NULL;
14
15
               pthread mutex init(&L->lock, NULL);
16
17
(Cont.)
```

Concurrent Linked Lists



```
(Cont.)
18
        int List Insert(list t *L, int key) {
19
                pthread mutex lock(&L->lock);
20
                node t *new = malloc(sizeof(node t));
2.1
                if (new == NULL) {
2.2
                         perror("malloc");
23
                         pthread mutex unlock(&L->lock);
24
                return -1; // fail
26
                new->kev = kev;
2.7
                new->next = L->head;
28
                L->head = new;
29
                pthread mutex unlock(&L->lock);
                return 0; // success
30
31 }
32
        int List Lookup(list t *L, int key) {
                pthread mutex lock(&L->lock);
33
34
                node t *curr = L->head;
35
                while (curr) {
36
                         if (curr->key == key) {
37
                                 pthread mutex unlock(&L->lock);
                                 return 0; // success
38
39
40
                         curr = curr->next;
41
42
                pthread mutex unlock(&L->lock);
                return -1; // failure
43
44
```



Concurrent Linked Lists (Cont.)

- The code **acquires** a lock in the insert routine upon entry.
- The code **releases** the lock upon exit.
 - If malloc() happens to fail, the code must also release the lock before failing the insert.
 - This kind of exceptional control flow has been shown to be quite error prone.
 - **Solution**: The lock and release *only surround* the actual critical section in the insert code



Concurrent Linked List: Rewritten

```
void List Init(list t *L) {
               L->head = NULL;
3
               pthread mutex init(&L->lock, NULL);
5
6
       void List Insert(list t *L, int key) {
                // synchronization not needed
               node t *new = malloc(sizeof(node_t));
8
9
                if (new == NULL) {
10
                       perror("malloc");
11
                        return:
12
13
               new->key = key;
14
15
               // just lock critical section
               pthread mutex lock(&L->lock);
16
               new->next = L->head;
17
18
               L->head = new;
19
               pthread mutex unlock(&L->lock);
20
21
```



Concurrent Linked List: Rewritten (Cont.)

```
(Cont.)
       int List Lookup(list t *L, int key) {
22
23
               int rv = -1;
24
               pthread mutex lock(&L->lock);
               node t *curr = L->head;
25
26
               while (curr) {
27
                       if (curr->key == key) {
2.8
                                rv = 0;
29
                               break;
30
31
                        curr = curr->next;
32
33
               pthread mutex unlock(&L->lock);
               return rv; // now both success and failure
34
35
```



Scaling Linked List

- Hand-over-hand locking (lock coupling)
 - Add a lock per node of the list instead of having a single lock for the entire list.
 - When traversing the list,
 - First grabs the next node's lock.
 - And then releases the current node's lock.
 - Enable a high degree of concurrency in list operations.

80

▶ However, in practice, the overheads of acquiring and releasing locks for each node of a list traversal is *prohibitive*.

Michael and Scott Concurrent Queues

- There are two locks.
 - One for the **head** of the queue.
 - One for the tail.
 - The goal of these two locks is to enable concurrency of enqueue and dequeue operations.
- Add a dummy node
 - Allocated in the queue initialization code
 - Enable the separation of head and tail operations



Concurrent Queues (Cont.)

```
typedef struct   node t {
1
               int value;
3
               struct node t *next;
       } node t;
6
       typedef struct   queue t {
               node t *head;
8
               node t *tail;
9
               pthread mutex t headLock;
               pthread mutex t tailLock;
10
11
        } queue t;
12
13
       void Queue Init(queue t *q) {
14
               node t *tmp = malloc(sizeof(node t));
15
               tmp->next = NULL;
16
               q->head = q->tail = tmp;
17
               pthread mutex init(&q->headLock, NULL);
18
               pthread mutex init(&q->tailLock, NULL);
19
20
(Cont.)
```

Concurrent Queues (Cont.)



```
(Cont.)
        void Queue Enqueue(queue t *q, int value) {
21
2.2
                node t *tmp = malloc(sizeof(node t));
23
                 assert(tmp != NULL);
24
25
                tmp->value = value;
26
                tmp->next = NULL;
2.7
28
                pthread mutex lock(&q->tailLock);
                q->tail->next = tmp;
29
30
                q->tail = tmp;
31
                 pthread mutex unlock(&q->tailLock);
32
33
        int Queue Dequeue(queue t *q, int *value) {
34
                pthread mutex lock(&q->headLock);
35
                node t *tmp = q->head;
36
                node t *newHead = tmp->next;
37
                if (newHead == NULL) {
38
                         pthread mutex unlock(&q->headLock);
39
                         return -1; // queue was empty
40
41
                 *value = newHead->value;
42
                q->head = newHead;
                pthread mutex unlock(&q->headLock);
43
44
                free (tmp);
45
                return 0;
46
```




Concurrent Hash Table

- Focus on a simple hash table
 - The hash table does not resize.
 - Built using the concurrent lists
 - It uses a lock per hash bucket each of which is represented by a list.



Performance of Concurrent Hash Table

- From 10,000 to 50,000 concurrent updates from each of four threads.
 - iMac with four Intel 2.7GHz i5 CPUs.



The simple concurrent hash table scales magnificently.

Concurrent Hash Table



```
#define BUCKETS (101)
       typedef struct hash t {
               list t lists[BUCKETS];
        } hash t;
       void Hash Init(hash t *H) {
               int i;
               for (i = 0; i < BUCKETS; i++) {</pre>
10
                       List Init(&H->lists[i]);
11
12
13
14
       int Hash Insert(hash t *H, int key) {
15
               int bucket = key % BUCKETS;
16
               return List Insert(&H->lists[bucket], key);
17
18
19
       int Hash Lookup(hash t *H, int key) {
20
               int bucket = key % BUCKETS;
2.1
               return List Lookup(&H->lists[bucket], key);
22
```

- 1. Concurrency Introduction
- 2. Locks
- 3. 基于Lock的并发数据结构
- 4. Condition Variables 条件变量
- 5. Semaphore 信号量
- 6. 常见并发问题
- 7. 基于事件的并发

Condition Variables 条件变量的引入



- There are many cases where a thread wishes to <u>check</u> whether a **condition** is true before continuing its execution. 一个线程需要检查另一个的状态, 并据此决定自己是否继续执行
- Example:
 - A parent thread might wish to check whether a child thread has completed.

88

This is often called a join().



Condition Variables (Cont.)

A Parent Waiting For Its Child

```
void *child(void *arg) {
1
            printf("child\n");
3
             // XXX how to indicate we are done?
            return NULL;
         int main(int argc, char *argv[]) {
             printf("parent: begin\n");
9
            pthread t c;
10
             Pthread create (&c, NULL, child, NULL); // create child
             // XXX how to wait for child?
11
12
            printf("parent: end\n");
13
            return 0;
14
```

What we would like to see here is:

```
parent: begin
child
parent: end
```

89

Parent waiting fore child: Spin-based Approach

```
volatile int done = 0;
3
       void *child(void *arg) {
4
            printf("child\n");
            done = 1;
6
            return NULL;
8
9
        int main(int argc, char *argv[]) {
10
            printf("parent: begin\n");
11
            pthread t c;
12
            Pthread create (&c, NULL, child, NULL); // create child
13
            while (done == 0)
14
                ; // spin
15
            printf("parent: end\n");
16
            return 0;
17
```

This is hugely inefficient as the parent spins and wastes CPU time.

90



How to wait for a condition

- Condition variable 本质上是一个队列及对该队列的操作原语
 - Waiting on the condition
 - An explicit queue that threads can put themselves on when some state of execution is not as desired.
 - Signaling on the condition
 - Some other thread, when it changes said state, can wake one of those waiting threads and allow them to continue.



Definition and Routines

Declare condition variable

```
pthread cond t c;
```

- Proper initialization is required.
- Operation (the POSIX calls)

- The wait() call takes a <u>mutex</u> as a parameter.
 - ▶ The wait() call release the lock and put the calling thread to sleep.
 - ▶ When the thread wakes up, it must re-acquire the lock.



Parent waiting for Child: Use a condition variable

```
int done = 0;
1
        pthread mutex t m = PTHREAD MUTEX INITIALIZER;
3
        pthread cond t c = PTHREAD COND INITIALIZER;
5
        void thr exit() {
6
                 Pthread mutex lock(&m);
                 done = 1;
8
                 Pthread cond signal(&c);
9
                 Pthread mutex unlock(&m);
10
11
12
        void *child(void *arg) {
13
                printf("child\n");
14
                 thr exit();
15
                 return NULL;
16
17
18
        void thr join() {
19
                Pthread mutex lock(&m);
20
                 while (done == 0)
21
                         Pthread cond wait(&c, &m);
22
                Pthread mutex unlock(&m);
23
24
```



Create the child thread and continues running itself.

Parent waiting for Child: Use a condition variable

Parent:

- Create the child thread and continues running itself.
- Call into thr join() to wait for the child thread to complete.
 - Acquire the lock
 - Check if the child is done
 - Put itself to sleep by calling wait ()
 - Release the lock

Child:

- Print the message "child"
- Call thr_exit() to wake the parent thread
 - Grab the lock
 - Set the state variable done
 - Signal the parent thus waking it.

The importance of the state variable done

```
1  void thr_exit() {
2     Pthread_mutex_lock(&m);
3     Pthread_cond_signal(&c);
4     Pthread_mutex_unlock(&m);
5   }
6
7  void thr_join() {
8     Pthread_mutex_lock(&m);
9     Pthread_cond_wait(&c, &m);
10     Pthread_mutex_unlock(&m);
11 }
```

thr_exit() and thr_join() without variable done

- Imagine the case where the child runs immediately.
 - ▶ The child will signal, but there is no thread asleep on the condition.
 - When the parent runs, it will call wait and be stuck.
 - No thread will ever wake it.



Another poor implementation

- The issue here is a subtle race condition.
 - ▶ The parent calls thr join().
 - The parent checks the value of done.
 - It will see that it is 0 and try to go to sleep.
 - Just before it calls wait to go to sleep, the parent is interrupted and the child runs.
 - ▶ The child changes the state variable done to 1 and signals.
 - But no thread is waiting and thus no thread is woken.
 - When the parent runs again, it sleeps forever.

The Producer/Consumer (Bound Buffer) Problem

Producer

- Produce data items
- Wish to place data items in a buffer

Consumer

- Grab data items out of the buffer consume them in some way
- Example: Multi-threaded web server
 - A producer puts HTTP requests in to a work queue
 - Consumer threads take requests out of this queue and process them



Bounded buffer

- A bounded buffer is used when you <u>pipe the output</u> of one program into another.
 - Example: grep foo file.txt | wc -l
 - ▶ The grep process is the producer.
 - ▶ The wc process is the consumer.
 - ▶ Between them is an in-kernel bounded buffer.
 - Bounded buffer is Shared resource → Synchronized access is required.





```
int buffer;
       int count = 0; // initially, empty
4
       void put(int value) {
5
               assert(count == 0);
6
               count = 1;
               buffer = value;
8
9
10
       int get() {
11
               assert(count == 1);
12
               count = 0;
13
               return buffer;
14
```

- Only put data into the buffer when count is zero.
 - ▶ i.e., when the buffer is *empty*.
- Only get data from the buffer when count is one.
 - ▶ i.e., when the buffer is full.

Producer/Consumer Threads (Version 1)

```
void *producer(void *arg) {
1
                int i;
                int loops = (int) arg;
                for (i = 0; i < loops; i++) {
                       put(i);
8
9
       void *consumer(void *arg) {
10
                int i;
11
                while (1) {
12
                        int tmp = get();
13
                        printf("%d\n", tmp);
14
15
```

Producer puts an integer into the shared buffer loops number of times.

101

Consumer gets the data out of that shared buffer.

Producer/Consumer: Single CV and If Statem

```
f State ment
```

```
cond t cond;
         mutex t mutex;
         void *producer(void *arg) {
             int i;
             for (i = 0; i < loops; i++) {</pre>
                 Pthread mutex lock(&mutex);
                                                                // p1
                 if (count == 1)
                                                                 // p2
                      Pthread cond wait (&cond, &mutex);
                                                                // p3
10
                 put(i);
                                                                // p4
11
                 Pthread cond signal (&cond);
                                                                // p5
                 Pthread mutex unlock(&mutex);
12
                                                                // p6
13
14
15
16
        void *consumer(void *arg) {
17
             int i;
18
             for (i = 0; i < loops; i++) {
19
                 Pthread mutex lock(&mutex);
                                                                // c1
                 if (count == 0)
20
                                                                 // c2
21
                     Pthread cond wait (&cond, &mutex);
                                                                // c3
22
                 int tmp = get();
                                                                // c4
23
                 Pthread cond signal (&cond);
                                                                // c5
24
                 Pthread mutex unlock (&mutex);
                                                                // c6
25
                 printf("%d\n", tmp);
26
27
```

If we have more than one of producer and consumer?

Thread Trace: Broken Solution (Version 1) NINSTITUTE OF TECH

T_{c1}	State	T_{c2}	State	T_p	State	Count	Comment
c1	Running		Ready		Ready	0	
c2	Running		Ready		Ready	0	
c3	Sleep		Ready		Ready	0	Nothing to get
	Sleep		Ready	р1	Running	0	
	Sleep		Ready	p2	Running	0	
	Sleep		Ready	p4	Running	1	Buffer now full
	Ready		Ready	р5	Running	1	T_{c1} awoken
	Ready		Ready	p6	Running	1	
	Ready		Ready	p1	Running	1	
	Ready		Ready	p2	Running	1	
	Ready		Ready	рЗ	Sleep	1	Buffer full; sleep
	Ready	c1	Running		Sleep	1	T_{c2} sneaks in
	Ready	c2	Running		Sleep	1	
	Ready	c4	Running		Sleep	0	and grabs data
	Ready	c5	Running		Ready	0	T_p awoken
	Ready	c6	Running		Ready	0	
c4	Running		Ready		Ready	0	Oh oh! No data

103

10.

Thread Trace: Broken Solution (Version 1)

- The problem arises for a simple reason:
 - After the producer woke T_{c1} , but before T_{c1} ever ran, the state of the bounded buffer *changed by* T_{c2} .
 - There is no guarantee that when the woken thread runs, the state will still be as desired → Mesa semantics.
 - Virtually every system ever built employs Mesa semantics.
 - Hoare semantics provides a stronger guarantee that the woken thread will run immediately upon being woken.

Producer/Consumer: Single CV and While

```
cond t cond;
1
2
         mutex t mutex;
        void *producer(void *arg) {
5
             int i;
             for (i = 0; i < loops; i++) {
                 Pthread mutex lock(&mutex);
                                                                // p1
                 while (count == 1)
8
                                                                // p2
9
                      Pthread cond wait (&cond, &mutex);
                                                                // p3
10
                 put(i);
                                                                // p4
11
                 Pthread cond signal (&cond);
                                                                // p5
12
                 Pthread mutex unlock (&mutex);
                                                                // p6
13
14
16
        void *consumer(void *arg) {
17
             int i;
18
             for (i = 0; i < loops; i++) {
                 Pthread mutex lock(&mutex);
19
                                                                // c1
                 while (count == 0)
20
                                                                // c2
21
                      Pthread cond wait (&cond, &mutex);
                                                                // c3
22
                 int tmp = get();
                                                                // c4
23
                 Pthread cond signal (&cond);
                                                                // c5
24
                 Pthread mutex unlock (&mutex);
                                                                // c6
                 printf("%d\n", tmp);
25
26
27
```

Thread Trace: Broken Solution (Version 2)

T_{c1}	State	T_{c2}	State	T_p	State	Count	Comment
c1	Running		Ready		Ready	0	
c2	Running		Ready		Ready	0	
c3	Sleep		Ready		Ready	0	Nothing to get
	Sleep	c1	Running		Ready	0	
	Sleep	c2	Running		Ready	0	
	Sleep	c3	Sleep		Ready	0	Nothing to get
	Sleep		Sleep	p1	Running	0	
	Sleep		Sleep	p2	Running	0	
	Sleep		Sleep	p4	Running	1	Buffer now full
	Ready		Sleep	p5	Running	1	T_{c1} awoken
	Ready		Sleep	р6	Running	1	
	Ready		Sleep	p1	Running	1	
	Ready		Sleep	p2	Running	1	
	Ready		Sleep	рЗ	Sleep	1	Must sleep (full)
c2	Running		Sleep		Sleep	1	Recheck condition
c4	Running		Sleep		Sleep	0	T_{c1} grabs data
c5	Running		Ready	106	Sleep	0	Oops! Woke T_{c2}

Thread Trace: Broken Solution (Version 2) (Cont.)

T_{c1}	State	T_{c2}	State	T_p	State	Count	Comment
							(cont.)
с6	Running		Ready		Sleep	0	
c1	Running		Ready		Sleep	0	
c2	Running		Ready		Sleep	0	
c3	Sleep		Ready		Sleep	0	Nothing to get
	Sleep	c2	Running		Sleep	0	
	Sleep	c3	Sleep		Sleep	0	Everyone asleep

 A consumer should not wake other consumers, only producers, and viceversa.

The single Buffer Producer/Consumer Solution

- Use two condition variables and while
 - Producer threads wait on the condition empty, and signals fill.

Consumer threads wait on fill and signal empty.

```
cond t empty, fill;
         mutex t mutex;
3
         void *producer(void *arg) {
             int i;
             for (i = 0; i < loops; i++) {</pre>
                  Pthread mutex lock(&mutex);
                  while (count == 1)
9
                      Pthread cond wait (&empty, &mutex);
10
                  put(i);
11
                  Pthread cond signal (&fill);
12
                  Pthread mutex unlock (&mutex);
13
14
16
         void *consumer(void *arg) {
17
             int i;
18
             for (i = 0; i < loops; i++) {</pre>
                  Pthread mutex lock(&mutex);
19
20
                  while (count == 0)
21
                      Pthread cond wait(&fill, &mutex);
22
                  int tmp = get();
23
                  Pthread cond signal (&empty);
24
                  Pthread mutex unlock (&mutex);
                  printf("%d\n", tmp);
25
26
```

The Final Producer/Consumer Solution

- More concurrency and efficiency → Add more buffer slots.
 - Allow concurrent production or consuming to take place.
 - Reduce context switches.

```
int buffer[MAX];
1
         int fill = 0;
         int use = 0;
4
         int count = 0;
         void put(int value) {
             buffer[fill] = value;
             fill = (fill + 1) % MAX;
             count++;
10
11
12
         int get() {
13
             int tmp = buffer[use];
             use = (use + 1) % MAX;
14
15
             count--;
16
             return tmp;
17
```

The Final Put and Get Routines

The Final Producer/Consumer Solution

```
cond t empty, fill;
         mutex t mutex;
3
4
         void *producer(void *arg) {
             int i;
             for (i = 0; i < loops; i++) {</pre>
                  Pthread mutex lock(&mutex);
                                                                 // p1
                  while (count == MAX)
                                                                 // p2
9
                      Pthread cond wait (&empty, &mutex);
                                                                 // p3
10
                 put(i);
                                                                 // p4
11
                  Pthread cond signal(&fill);
                                                                 // p5
                 Pthread mutex unlock(&mutex);
12
                                                                 // p6
13
14
15
16
         void *consumer(void *arg) {
17
             int i;
18
             for (i = 0; i < loops; i++) {</pre>
19
                  Pthread mutex lock(&mutex);
                                                                 // c1
                  while (count == 0)
20
                                                                 // c2
21
                      Pthread cond wait (&fill, &mutex);
                                                                 // c3
22
                 int tmp = get();
                                                                 // c4
23
                  Pthread cond signal (&empty);
                                                                 // c5
24
                  Pthread mutex unlock (&mutex);
                                                                 // c6
                 printf("%d\n", tmp);
25
26
27
```



Covering Conditions

- Assume there are zero bytes free
 - Thread T_a calls allocate (100).
 - Thread T_b calls allocate (10).
 - Both T_a and T_b wait on the condition and go to sleep.
 - Thread T_c calls free (50).

Which waiting thread should be woken up?



Covering Conditions (Cont.)

```
// how many bytes of the heap are free?
1
         int bytesLeft = MAX HEAP SIZE;
3
        // need lock and condition too
        cond t c;
        mutex t m;
        void *
9
         allocate(int size) {
10
             Pthread mutex lock(&m);
11
             while (bytesLeft < size)</pre>
12
                 Pthread cond wait(&c, &m);
13
            void *ptr = ...;
                                             // get mem from heap
            bytesLeft -= size;
14
15
             Pthread mutex unlock (&m);
16
             return ptr;
17
18
19
        void free(void *ptr, int size) {
20
             Pthread mutex lock(&m);
2.1
             bytesLeft += size;
22
             Pthread cond signal(&c); // whom to signal??
23
             Pthread mutex unlock(&m);
24
```



Covering Conditions (Cont.)

- Solution (Suggested by Lampson and Redell)
 - Replace pthread_cond_signal() with pthread_cond_broadcast()
 - pthread cond broadcast()
 - Wake up all waiting threads.
 - Cost: too many threads might be woken.
 - Threads that shouldn't be awake will simply wake up, re-check the condition, and then go back to sleep.

- 1. Concurrency Introduction
- 2. Locks
- 3. 基于Lock的并发数据结构
- 4. Condition Variables 条件变量
- 5. Semaphore 信号量
- 6. 常见并发问题
- 7. 基于事件的并发



Semaphore: A definition

- An object with an integer value
 - We can manipulate with two routines; sem wait() and sem post().
 - Initialization

```
1 #include <semaphore.h>
2 sem_t s;
3 sem_init(&s, 0, 1); // initialize s to the value 1
```

- Declare a semaphore s and initialize it to the value 1
- ▶ The second argument, 0, indicates that the semaphore is <u>shared</u> between *threads in the same process*.



Semaphore: wait原语

sem_wait()

```
1 int sem_wait(sem_t *s) {
2    decrement the value of semaphore s by one
3    wait if value of semaphore s is negative
4 }
```

- 减1, 若大于0, 则返回, 否则挂起等待被post唤醒
- If the value of the semaphore was one or higher when called sem wait(), return right away.
- It will cause the caller to <u>suspend execution</u> waiting for a subsequent post.
- When negative, the value of the semaphore is equal to the number of waiting threads.

Semaphore: Interact with semaphore (Cont.)

■ sem post()

```
1 int sem_post(sem_t *s) {
2    increment the value of semaphore s by one
3    if there are one or more threads waiting, wake one
4 }
```

- 加1, 若有等待线程, 则唤醒一个
- Simply increments the value of the semaphore.
- If there is a thread waiting to be woken, wakes one of them up.

117



Binary Semaphores (Locks)

- What should **x** be?
 - The initial value should be 1.

```
1  sem_t m;
2  sem_init(&m, 0, X); // initialize semaphore to X; what should X be?
3
4  sem_wait(&m);
5  //critical section here
6  sem_post(&m);
```

Thread Trace: Single Thread Using A Semaphore

Value of Semaphore	Thread 0	Thread 1
1		
1	<pre>call sema_wait()</pre>	
0	sem_wait() returns	
0	(crit sect)	
0	<pre>call sem_post()</pre>	
1	sem_post() returns	

Thread Trace: Two Threads Using A Semantions

	Value	Thread 0	State	Thread 1	State
-	1		Running		Ready
	1	call sem_wait()	Running		Ready
	0	sem_wait() retruns	Running		Ready
	0	(crit set: begin)	Running		Ready
	0	Interrupt; Switch → T1	Ready		Running
	0		Ready	call sem_wait()	Running
	-1		Ready	decrement sem	Running
	-1		Ready	(sem < 0)→sleep	sleeping
	-1		Running	Switch → TO	sleeping
	-1	(crit sect: end)	Running		sleeping
	-1	call sem_post()	Running		sleeping
	0	increment sem	Running		sleeping
	0	wake(T1)	Running		Ready
	0	sem_post() returns	Running		Ready
	0	Interrupt; Switch → T1	Ready		Running
	0		Ready	sem_wait() retruns	Running
	0		Ready	(crit sect)	Running
	0	in the second second	Ready	call sem_post()	Running
	1		Ready	sem_post() returns	Running 120



```
sem t s;
    void *
    child(void *arg) {
        printf("child\n");
         sem post(&s); // signal here: child is done
         return NULL;
10
     int
11
     main(int argc, char *argv[]) {
12
         sem init(&s, 0, X); // what should X be?
        printf("parent: begin\n");
13
        pthread t c;
14
15
         pthread create(c, NULL, child, NULL);
16
         sem wait(&s); // wait here for child
17
        printf("parent: end\n");
        return 0;
18
19
```

A Parent Waiting For Its Child

parent: begin
child
parent: end

The execution result

- What should x be?
 - ▶ The value of semaphore should be set to is 0.

121

Thread Trace: Parent Waiting For Child Case

■ The parent call sem_wait() before the child has called sem_post().

Value	Parent	State	Child	State
0	Create(Child)	Running	(Child exists; is runnable)	Ready
0	call sem_wait()	Running		Ready
-1	decrement sem	Running		Ready
-1	(sem < 0)→sleep	sleeping		Ready
-1	Switch→Child	sleeping	child runs	Running
-1		sleeping	call sem_post()	Running
0		sleeping	increment sem	Running
0		Ready	wake(Parent)	Running
0		Ready	sem_post() returns	Running
0		Ready	Interrupt; Switch→Parent	Ready
0	sem_wait() retruns	Running		Ready

122

Thread Trace: Parent Waiting For Child Case 2)

The child runs to completion before the parent call sem wait().

Value	Parent	State	Child	State
0	Create(Child)	Running	(Child exists; is runnable)	Ready
0	Interrupt; switch→Child	Ready	child runs	Running
0		Ready	call sem_post()	Running
1		Ready	increment sem	Running
1		Ready	wake (nobody)	Running
1		Ready	sem_post() returns	Running
1	parent runs	Running	Interrupt; Switch→Parent	Ready
1	call sem_wait()	Running		Ready
0	decrement sem	Running		Ready
0	(sem<0)→awake	Running		Ready
0	sem_wait() retruns	Running		Ready

123

The Producer/Consumer (Bounded-Buffer) Problem

- **Producer**: put() interface
 - Wait for a buffer to become empty in order to put data into it.
- Consumer: get() interface
 - Wait for a buffer to become filled before using it.

```
1  int buffer[MAX];
2  int fill = 0;
3  int use = 0;
4
5  void put(int value) {
6    buffer[fill] = value;  // line f1
7    fill = (fill + 1) % MAX;  // line f2
8  }
9
10  int get() {
11    int tmp = buffer[use];  // line g1
12    use = (use + 1) % MAX;  // line g2
13    return tmp;
14 }
```

124

The Producer/Consumer (Bounded-Buffer) Problem

```
sem t empty;
     sem t full;
     void *producer(void *arg) {
         int i;
         for (i = 0; i < loops; i++) {</pre>
6
                  sem wait(&empty);
                                              // line P1
                  put(i);
                                              // line P2
                                              // line P3
9
                  sem post(&full);
10
11
12
13
     void *consumer(void *arg) {
         int i, tmp = 0;
14
         while (tmp != -1) {
15
16
                  sem wait(&full);
                                              // line C1
17
                  tmp = get();
                                              // line C2
18
                  sem post(&empty);
                                              // line C3
19
                  printf("%d\n", tmp);
20
2.1
22
```

First Attempt: Adding the Full and Empty Conditions

The Producer/Consumer (Bounded-Buffer) Problem

First Attempt: Adding the Full and Empty Conditions (Cont.)

- Imagine that MAX is greater than 1 .
 - ▶ If there are multiple producers, race condition can happen at line f1.
 - It means that the old data there is overwritten.

- We've forgotten here is mutual exclusion.
 - The filling of a buffer and incrementing of the index into the buffer is a critical section.





```
sem t empty;
    sem t full;
   sem t mutex;
4
   void *producer(void *arg) {
        int i;
        for (i = 0; i < loops; i++) {</pre>
                 sem wait(&mutex);
                                      // line p0 (NEW LINE)
                 sem wait(&empty);
                                        // line p1
10
                put(i);
                                          // line p2
                 sem post(&full);
                                        // line p3
11
12
                 sem post(&mutex);
                                      // line p4 (NEW LINE)
13
14
15
(Cont.)
```

Adding Mutual Exclusion (Incorrectly)



```
哈爾濱Z業大學
HARBIN INSTITUTE OF TECHNOLOGY
```

```
(Cont.)
  void *consumer(void *arg) {
17
        int i;
18
        for (i = 0; i < loops; i++) {</pre>
19
                sem wait(&mutex);
                                 // line c0 (NEW LINE)
20
                sem wait(&full);
                                       // line c1
21
                int tmp = get();
                                        // line c2
22
                sem post(&empty);
                                      // line c3
23
                sem post(&mutex);
                                        // line c4 (NEW LINE)
24
                printf("%d\n", tmp);
25
26
```

Adding Mutual Exclusion (Incorrectly)

A Solution: Adding Mutual Exclusion 公司 (Cont.)

- Imagine two thread: one producer and one consumer.
 - The consumer acquire the mutex (line c0).
 - The consumer calls sem wait() on the full semaphore (line c1).
 - The consumer is blocked and yield the CPU.
 - ▶ The consumer <u>still holds the mutex</u>!
 - The producer calls sem_wait() on the binary mutex semaphore (line p0).
 - The producer is now stuck waiting too. a classic deadlock.



Finally, A Working Solution

```
sem t empty;
   sem t full;
   sem t mutex;
   void *producer(void *arg) {
       int i;
       for (i = 0; i < loops; i++) {</pre>
               sem wait(&mutex);
                                     // line p1.5 (MOVED MUTEX HERE...)
                                     // line p2
10
               put(i);
               sem post(&mutex); // line p2.5 (... AND HERE)
11
12
               sem post(&full);
                                     // line p3
13
14
15
(Cont.)
```

Adding Mutual Exclusion (Correctly)

130



Finally, A Working Solution

```
(Cont.)
16
    void *consumer(void *arg) {
17
        int i;
        for (i = 0; i < loops; i++) {</pre>
18
19
                sem wait(&full);
                                        // line c1
20
                                        // line c1.5 (MOVED MUTEX HERE...)
                sem wait(&mutex);
2.1
                int tmp = get();
                                        // line c2
22
                sem post(&mutex);
                                       // line c2.5 (... AND HERE)
23
                24
                printf("%d\n", tmp);
25
26
27
28
    int main(int argc, char *argv[]) {
29
        // ...
30
        sem init(&empty, 0, MAX); // MAX buffers are empty to begin with ...
        sem init(&full, 0, 0); // ... and 0 are full
31
32
        sem init(&mutex, 0, 1); // mutex=1 because it is a lock
33
        // ...
34
```

Adding Mutual Exclusion (Correctly)

131



Reader-Writer Locks

- Imagine a number of concurrent list operations, including inserts and simple lookups.
 - insert:
 - Change the state of the list
 - ▶ A traditional <u>critical section</u> makes sense.
 - lookup:
 - Simply read the data structure.
 - As long as we can guarantee that no insert is on-going, we can allow many lookups to proceed concurrently.

This special type of lock is known as a reader-write lock.



A Reader-Writer Locks

- Only a single writer can acquire the lock.
- Once a reader has acquired a read lock,
 - More readers will be allowed to acquire the read lock too.
 - A writer will have to wait until all readers are finished.

```
typedef struct rwlock t {
        sem t lock;
                          // binary semaphore (basic lock)
        sem t writelock; // used to allow ONE writer or MANY readers
        int readers; // count of readers reading in critical section
    } rwlock t;
    void rwlock init(rwlock t *rw) {
        rw->readers = 0;
        sem init(&rw->lock, 0, 1);
10
        sem init(&rw->writelock, 0, 1);
11
12
13
    void rwlock acquire readlock(rwlock t *rw) {
14
        sem wait(&rw->lock);
15
```



A Reader-Writer Locks (Cont.)

```
15
         rw->readers++;
16
         if (rw->readers == 1)
17
                  sem wait(&rw->writelock); // first reader acquires writelock
18
         sem post(&rw->lock);
19
20
21
    void rwlock release readlock(rwlock t *rw) {
22
         sem wait(&rw->lock);
        rw->readers--;
23
24
         if (rw->readers == 0)
25
                  sem post(&rw->writelock); // last reader releases writelock
26
         sem post(&rw->lock);
27
28
29
    void rwlock acquire writelock(rwlock t *rw) {
         sem wait(&rw->writelock);
30
31
32
33
    void rwlock release writelock(rwlock t *rw) {
34
         sem post(&rw->writelock);
35
```



A Reader-Writer Locks (Cont.)

- The reader-writer locks have fairness problem.
 - It would be relatively easy for reader to starve writer.

135

How to <u>prevent</u> more readers from entering the lock once a writer is waiting?



The Dining Philosophers

- Assume there are five "philosophers" sitting around a table.
 - Between each pair of philosophers is a single fork (five total).
 - The philosophers each have times where they think, and don't need any forks, and times where they eat.
 - In order to eat, a philosopher needs two forks, both the one on their left and the one on their right.

The contention for these forks.

f2

P1

f1

P2

P0

f3

f4

P4

136



The Dining Philosophers (Cont.)

- Key challenge
 - There is no deadlock.
 - No philosopher starves and never gets to eat.
 - Concurrency is high.

```
while (1) {
         think();
         getforks();
         eat();
         putforks();
}
```

Basic loop of each philosopher

```
// helper functions
int left(int p) { return p; }
int right(int p) {
          return (p + 1) % 5;
}
```

Helper functions (Downey's solutions)

▶ Philosopher p wishes to refer to the fork on their left \rightarrow call left(p).

137

Philosopher p wishes to refer to the fork on their right → call right (p).



The Dining Philosophers (Cont.)

We need some semaphore, one for each fork: sem t forks[5].

```
void getforks() {
    sem_wait(forks[left(p)]);
    sem_wait(forks[right(p)]);

void putforks[right(p)]);

sem_post(forks[left(p)]);
    sem_post(forks[right(p)]);

sem_post(forks[right(p)]);

}
```

The getforks() and putforks() Routines (Broken Solution)

138

- Deadlock occur!
 - If each philosopher happens to **grab the fork on their left** before any philosopher can grab the fork on their right.
 - ▶ Each will be stuck *holding one fork* and waiting for another, *forever*.

A Solution: Breaking The Dependency

- Change how forks are acquired.
 - Let's assume that philosopher 4 acquire the forks in a different order.

139

There is no situation where each philosopher grabs one fork and is stuck waiting for another. **The cycle of waiting is broken**.



How To Implement Semaphores

Build our own version of semaphores called Zemaphores

```
typedef struct Zem t {
        int value;
        pthread cond t cond;
        pthread mutex t lock;
    } Zem t;
    // only one thread can call this
    void Zem init(Zem t *s, int value) {
9
         s->value = value;
10
        Cond init(&s->cond);
11
        Mutex init(&s->lock);
12
13
14
    void Zem wait(Zem t *s) {
15
        Mutex lock(&s->lock);
16
        while (s->value <= 0)
17
        Cond wait(&s->cond, &s->lock);
18
         s->value--;
19
        Mutex unlock(&s->lock);
20
21
```

How To Implement Semaphores (Cont.)

```
22  void Zem_post(Zem_t *s) {
23     Mutex_lock(&s->lock);
24     s->value++;
25     Cond_signal(&s->cond);
26     Mutex_unlock(&s->lock);
27 }
```

141

- Zemaphore don't maintain the invariant that the value of the semaphore.
 - ▶ The value never be lower than zero.
 - This behavior is easier to implement and matches the current Linux implementation.

例题




【例题】当 V 操作唤醒一个等待进程时,被唤醒进程变为()态。

- A. 运行
- B. 阻塞
- C. 就绪
- D. 完成

答案: C

等待唤醒的进程处于阻塞态,被唤醒后进入就绪态。只有就绪进程能获得处理器资源,被唤醒的进程并不能直接转化为运行态。



进程:状态转换





【例题】有三个进程共享同一程序段,而每次只允许两个进程进入该程序段,若用 PV 操作同步机制,则信号量 S 的取值范围是()

- A. 2, 1, 0, -1
- B. 3, 2, 1, 0
- C. 2, 1, 0, -1, -2
- D. 1, 0, -1, -2

答案: A

因为每次允许两个进程进入该程序段,信号量最大值取2(否则三个进程可以同时进入程序段)。至多有三个进程申请,则信号量最小为-1。