## 1. Coulomb's Law

Coulomb's Law describes the force between two charged particles. If the charges have the same sign, they repel, if they are opposite, they attract. The **electrostatic force** is given by:

$$\vec{F} = k \frac{q_1 q_2}{r^2} \hat{r}$$
 (Coulomb's Law, 1-1)

where:

- $\vec{F}$  is the force.
- $q_1$  and  $q_2$  are the charges,
- r is the distance between them,
- k is a constant (electrostatic constant),
- $\hat{r}$  is a unit vector along the line connecting the charges.

Coulomb's Law is similar to **Newton's Law of Gravitation**, which gives the gravitational force between two masses as:

$$\vec{F} = G \frac{m_1 m_2}{r^2} \hat{r}$$
 (Newton's Law of Gravitation, 1-2)

Both laws follow an inverse-square relationship, meaning the force decreases with the square of the distance between the objects. However, unlike gravitational forces (which are always attractive), electrostatic forces can be either attractive or repulsive depending on the charges.

Coulomb's law has been experimentally validated and works even at the atomic level, explaining the forces between atomic nuclei and electrons. It also accounts for the forces that bind atoms and molecules together.

In the **SI unit system**, the unit of charge is the coulomb (C), and **electric current** i is defined as the rate at which charge flows:

$$i = \frac{dq}{dt}$$
 (Electric Current, 1-3)

where i is the current (in ampères) and dq is the charge (in coulombs) passing through a point in time dt. Rearranging in **SI** tells us that:

$$1C = (1A)(1s)$$

For historical reasons the constant k is usually written as  $1/4\pi\varepsilon_0$ , therefore the magnitude in Coulomb's Law becomes

$$\mathbf{F} = \frac{1}{4\pi\varepsilon_0} \frac{|q_1||q_2|}{r^2}$$
 (Coulomb's Law, 1-4)

The constants in Eqs. 1.1 and 1.4 have values:

$$k = \frac{1}{4\pi\varepsilon_0} = 8.99 \cdot 10^9 \frac{N \cdot m^2}{C^2}$$

The quantity  $\varepsilon_0$  is called **permittivity constant of free space**:

$$\varepsilon_0 = 8.85 \cdot 10^{-12} \frac{C^2}{N \cdot m^2}$$

Another parallel between the gravitational force and the electrostatic force is that they both obey the principle of superposition. Given n charged particles we can say that the net force is given by the vector sum:

$$\vec{F_{1,net}} = \vec{F_{1,2}} + \vec{F_{1,3}} + \vec{F_{1,4}} + \dots + \vec{F_{1,n}}$$
(1-5)

## 1.1 Charge is Quantized

By experimental means we know that **charge** q is **quantized**, thus any positive or negative charge that can be detected can be written as

$$q=n\cdot e, \hspace{1cm} n=\pm 1, \pm 2, \pm 3, \dots$$

in which e, the **elementary charge**, has the approximate value:

$$e = 1.602 \cdot 10^{-19}C$$

# 2. The Electric Field

The **electric field** is a vector field that consists of a distribution of vectors around a charged object. We can define the electric field around a point P by placing a certain charge  $q_0$  at the point and then we measure the electrostatic force  $\vec{F}$  that acts on the charge. We define the electric field  $\vec{E}$  at a point P due to a charged object as

$$\vec{E} = \frac{\vec{F}}{q_0}$$
 (Electric Field 2-1)

Electric Field Lines are graphical visual aid which consists of imaginary integral curves that are tangent to the field vector at any point along their length.



Figure 1: Electric Field Lines

## 2.1 Electric Fiels due to a Point Charge

To find an electric charge due to a point q at any point to a distance r, we put a positive charge  $q_0$ . The **electrostatic force** acting on  $q_0$  is:

$$\vec{F} = \frac{1}{4\pi\varepsilon_0} \frac{qq_0}{r^2} \hat{r}$$

The direction of  $\vec{F}$  points directly away from the point charge is q is positive, towards the point charge if q is negative. The **electric field vector** is:

$$\vec{E} = \frac{\vec{F}}{q_0} = \frac{1}{4\pi\varepsilon_0} \frac{q}{r^2}$$
 (Point Charge, 2-2)

 $\vec{E}$  and  $\vec{F}$  have same direction.

We can quickly find the resultant electric field due to more than one point charge by placing a positive charge  $q_0$  near n point charges  $q_1, q_2, ..., q_n$ , then, from Eq. 1-5, the net force from the n point charges acting on the test charge is:

$$\vec{F_0} = \vec{F_{01}} + \vec{F_{02}} + \vec{F_{03}} + \dots + \vec{F_{0n}}.$$

Therefore the net electric field at the position of the charge is:

$$\vec{E} = \frac{\vec{F_0}}{q_0} = \frac{\vec{F_{01}}}{q_0} + \frac{\vec{F_{02}}}{q_0} + \dots + \frac{\vec{F_{0n}}}{q_0} = \sum_{i=1}^n \frac{\vec{F_{0i}}}{q_0} = \sum_{i=1}^n \vec{E_i}$$
 (2-3)

## 2.2 Electric Field due to an Electric Dipole

An **Electric Dipole** consists of two charges of magnitude q, but opposite signs, separated by a distance d. The point of interest P is located along the the **Dipole Axis** at a distance z from the dipole's midpoint.

Due to the simmetry of this setup, the electric field components from the two charges  $(E_+ \text{ and } E_-)$  must lie along the dipole axis which we have taken to be z axis. Applying the **superposition principle** for electric fields, we find that the magnitude  $\mathbf{E}$  at a point P is:

$$\mathbf{E} = E_{+} + E_{-}$$

$$= \frac{1}{4\pi\varepsilon_{0}} \frac{q}{r_{(+)}^{2}} - \frac{1}{4\pi\varepsilon_{0}} \frac{q}{r_{(-)}^{2}}$$

$$= \frac{q}{4\pi\varepsilon_{0}(z - \frac{1}{2}d)^{2}} - \frac{q}{4\pi\varepsilon_{0}(z + \frac{1}{2}d)^{2}}.$$

With a little algebra:

$$\mathbf{E} = \frac{q}{4\pi\epsilon_0 z^2} \left( \frac{1}{(1 - \frac{d}{2z})^2} - \frac{1}{(1 + \frac{d}{2z})^2} \right).$$

$$\mathbf{E} = \frac{q}{4\pi\epsilon_0 z^2} \frac{2d/z}{(1 - (\frac{d}{2z})^2)^2} = \frac{q}{2\pi\epsilon_0 z^3} \frac{d}{(1 - (\frac{d}{2z})^2)^2}$$
(2-4)



Figure 2: An Electric Dipole

We are usually interested in the electrical effect of the dipole only at distances larger than the dipole, such distances as  $z \gg d$ . At such distances, we have  $d/2z \ll 1$  in Eq. 2-4. Given this approximation, we can rewrite 2-4 as:

$$\mathbf{E} = \frac{1}{2\pi\varepsilon_0} \frac{qd}{z^3} \tag{2-5}$$

The product qd is the magnitude **p** of a vector called **Electric Dipole Moment**  $(\vec{p} = q\vec{d})$ . Thus we can rewrite 2-5 as:

$$\mathbf{E} = \frac{1}{2\pi\varepsilon_0} \frac{p}{z^3}$$
 (Electric Dipole, 2-6)

The direction of  $\vec{p}$  is taken to be from the negative to the positive side of the dipole.

## 2.3 Electric Field due to a Line of Charge

We now consider **continuous** charge distributions. Given a ring of radius R of uniform positive linear charge density  $\lambda$  around its circumference, a differential element of charge occupies a length ds. This element sets up an electrical field  $d\vec{E}$  at a point P. The component of  $d\vec{E}$  along the central axis can be intercepted by  $dE\cos\theta$ . Therefore every element ds has a charge of magnitude

| Name                   | Symbol    | SI Unit |
|------------------------|-----------|---------|
| - $Charge$             | q         | C       |
| Linear Charge Density  | $\lambda$ | C/m     |
| Surface Charge Density | $\sigma$  | $C/m^2$ |
| Volume Charge Density  | ho        | $C/m^3$ |

Table 1: Some Measures of Electric Charge

$$dq = \lambda ds \tag{2-6}$$

This differential charge sets up a differential electric field  $\vec{E}$  at a point P, which is at a distance r from the point. Using Eq. 2-6 we can rewrite Eq. 2-2:

$$dE = \frac{1}{4\pi\varepsilon_0} \frac{dq}{r^2} = \frac{1}{4\pi\varepsilon_0} \frac{\lambda ds}{r^2}$$
 (22-7)

From Figure 3 we can rewrite Eq. 2-7:

$$dE = \frac{1}{4\pi\varepsilon_0} \frac{\lambda ds}{(z^2 + R^2)} \tag{2-8}$$

Every  $d\vec{E}$  has a component perpendicular to the central axis z  $(d\vec{E}\cos\theta)$  with equal magnitude but different direction. Therefore:

$$\begin{cases}
\cos \theta = \frac{z}{r} = \frac{z}{(z^2 + R^2)^{1/2}} \\
dE = \frac{1}{4\pi\varepsilon_0} \frac{\lambda ds}{(z^2 + R^2)}
\end{cases}$$

Multiplying the first expression for the second gives us:

$$d\vec{E}\cos\theta = \frac{z\lambda}{4\pi\varepsilon_0(z^2 + R^2)^{3/2}}ds$$
 (2-9) Figure 3: A Ring of Uniform Positive Charge

To add the parallel components  $(dE \cos \theta)$  produced by all elements we integrate Eq. 2-9 around the circumference of the ring, from s = 0 to  $s = 2\pi R$ :

$$E = \int dE \cos \theta = \frac{z\lambda}{4\pi\varepsilon_0(z^2 + R^2)^{3/2}} \cdot \int_0^{2\pi R} ds = \frac{z\lambda(2\pi R)}{4\pi\varepsilon_0(z^2 + R^2)^{3/2}}$$
(2-10)

Since  $\lambda$  is the charge per length of a ring, the term  $\lambda 2\pi R$  is just q  $[q = \lambda(2\pi R)]$ :

$$E = \frac{qz}{4\pi\varepsilon_0(z^2 + R^2)^{3/2}}$$
 (Charged Ring, 2-11)

This equation yields the same results even if q is negative.

If we assume that  $z \gg R$ ,  $z^2 + R^2$  can be approximated as  $z^2$  and 2-11 becomes:

$$E = \frac{qz}{4\pi\varepsilon_0 z^2}$$
 (Charged Ring ad Large Distances, 2-12)

## 2.3.1 A Field Guide for Lines of Charge

Finding the electric field  $\vec{E}$  produced at a point P by a line of uniform charge, either circular or straight. The strategy is to pick on an element dq of charge, find  $d\vec{E}$  due to that element and integrate  $d\vec{E}$  over the entire line of charge.

- **Step 1.** If the line of charge is circular, let ds be the arc length of an element of the distribution. If the line is straight, sum on x axis along it and let dx be the length of an element.
- Step 2. Relate dq of the element to the length of the element with either  $dq = \lambda ds$  or  $dq = \lambda dx$ . Consider dq and  $\lambda$  positive even if the charge is actually negative.
- **Step 3.** Express the field  $d\vec{E}$  produced at P by dq with  $\vec{E} = \frac{\vec{F}}{q_0} = \frac{q}{4\pi\epsilon_0 r^2}$ , replacing q with either  $q = \lambda ds$  or  $q = \lambda dx$ . If the charge on the line is positive then at P draw a vector  $d\vec{E}$  that points directly away from dq, opposite if the charge is negative.
- Step 4. Always look for any simmetry in the situation. If P is on an axis of simmetry of the charge distribution, resolve the field  $d\vec{E}$  produced by dq into components that are perpendicular and parallel to the axis of simmetry. Repeat with the simmetric element dq' and draw the vector  $d\vec{E}'$  at P. One of the components produced by dq is a cancelling component, cancelled by the corrisponding component produced by dq', we have a similar concept in adding components. Integration is a way to add them up.
- Step 5. There are four general types of uniform charge distribution:

Ring: With point P on the central axis of simmetry. In the expression for  $d\vec{E}$  replace  $r^2 = z^2 + R^2$ . Express the adding components of  $d\vec{E}$  in terms of  $\theta$ . That introduces  $\cos \theta$ , but  $\theta$  is identical to all the elements, therefore is not a variable. Replace  $\cos \theta = \frac{z}{r} = \frac{z}{(z^2 + R^2)^{1/2}}$  and integrate over s around the circumference.

Circular Arc: Point P at the center of the curvature. Express the adding component of  $d\vec{E}$  in terms of  $\theta$ . That introduces either  $\sin\theta$  or  $\cos\theta$ . Reduce the two resulting variables s and  $\theta$  by replacing  $ds = rd\theta$  from one end of the arc to the other.



Figure 4

Straight Line: with point P on an extension of the line (as in Fig. 4a). In the expression for dE, replace r with x. Integrate over x from end to end.

Straight Line: with point P at perpendicular distance y from the line of charge (Fig. 4b). In the expression for dE replace r with an expression involving x and y. If P is on the perpendicular bisector of the line of charge, find an expression for the adding component of  $d\vec{E}$ . That will introduce either  $\sin\theta$  or  $\cos\theta$ . Reduce the resulting two variables x and  $\theta$  to one, x, by replacing the trigonometric function with an expression involving x and y. Integrate over x from end to end of the line of charge. If P (Fig. 4c) is not on the line of simmetry, set up an integral to sum the components  $dE_x$  and integrate over x to find  $E_x$ . Also set up an integral to sum the components  $dE_y$ , integrate over x again to find  $E_y$ . Now use  $E_x$  and  $E_y$  to find magnitude and direction of  $\vec{E}$ .

Step 6. One arrangement of the integration limits gives a positive result. The reverse gives the same result with a minus sign. Discard the minus sign. If the result is to be stated in terms of the total charge Q of the distribution, replace  $\lambda = Q/L$  in which L is the length of the distribution.

## 2.4 Point Charge in an Electric Field

Figure 4 shows a circular plastic disk of  $radius\ R$  that has a positive surface charge of uniform density  $\sigma$  on its upper surface. We need to find the electric field at point P, with distance z from the disk along its central axis. We divide the disk into concentric flat rings and then calculate the electric field at point P by adding up (integrating) the contribution of all rings. Fig. 4 shows one such ring, with radius r and radial width dr. The charge on the ring is:

$$dq = \sigma dA = \sigma(2\pi r dr) \tag{2-13}$$

where dA is the differential area of the ring. Substituting dq from Eq. 2-13 for q in Eq. 2-11:

$$dE = \frac{z\sigma 2\pi r dr}{4\pi\varepsilon_0(z^2 + r^2)^{3/2}}$$



Figure 5: A disk of uniform positive charge

which we can rewrite as

$$dE = \frac{\sigma z}{4\varepsilon_0} \frac{2rdr}{(z^2 + r^2)^{3/2}} \tag{2-14}$$

We can now find E by integrating 2-14 over the surface of the disk, with respect to the variable r from r = 0 to r = R. We get

$$E = \int dE = \frac{\sigma z}{4\varepsilon_0} \int_0^R (z^2 + r^2)^{-3/2} (2r) dr$$
 (2-15)

This is easily solvable by casting the integral in the form  $\int X^m dX$ , by setting  $X = (z^2 + r^2)$ , dX = (2rdr) and  $m = -\frac{3}{2}$ , we have

$$\int X^m dX = \frac{X^{m+1}}{m+1}$$

The solved integral becomes

$$E = \frac{\sigma z}{4\varepsilon_0} \left[ \frac{(z^2 + r^2)^{-1/2}}{-\frac{1}{2}} \right]_0^R$$
 (2-16)

Taking the limits and rearranging we obtain:

$$\mathbf{E} = \frac{\sigma}{2\varepsilon_0} \left( 1 - \frac{z}{\sqrt{z^2 + R^2}} \right)$$
 (Charged Disk, 2-17)

If we let  $R \to \infty$  while keeping z finite, the equation reduces to

$$E = \frac{\sigma}{2\varepsilon_0}$$

This is the electric field produced by an infinite sheet of uniform charge. We get the same result by letting  $z \to 0$  while keeping R finite.

## 2.5 Point Charge in an Electric Field

$$\vec{F} = q\vec{E} \tag{2-18}$$

The electrostatic force  $\vec{F}$  acting on a charged particle located in an external electric field  $\vec{E}$  has the direction of  $\vec{E}$  if the charge q of the particle is positive and has the opposite direction if q is negative.

# 2.6 A Dipole in an Electric Field

We have defined Dipole Moment  $(\vec{p} = q\vec{d})$  as a vector that point from the negative to the positive end of the dipole. A dipole in an Electric Field  $\vec{E}$  consists of a rigid structure with two center of opposite charge and magnitude q. The dipole moment  $\vec{p}$  makes an angle  $\theta$  with  $\vec{E}$ . Electrostatic forces act on the charged ends of the dipole. Since  $\vec{E}$  is uniform, those forces act in opposite directions with magnitude F = qE. Thus, since the field is uniform, the *net force* on the dipole is = 0. However the forces on the charged ends produce a **net torque**  $\vec{\tau}$  on the dipole in his center of mass, which lies in the line connecting the charged ends at some distance x from one end and thus a distance x



Figure 6: Dipole in an uniform external electric field  $\vec{E}$ 

from the other end.

Given  $\tau = rF \sin \phi$  we can write the magnitude of the net torque as:

$$\tau = Fx\sin\theta + F(d-x)\sin\theta = Fd\sin\theta \tag{2-19}$$

or, by substituting F = qE and d = p/q we can find the magnitude of  $\vec{\tau}$ :

$$\tau = pE\sin\theta \tag{2-20}$$

In a generalized vector form:

$$\vec{\tau} = \vec{p} \times \vec{E}$$
 (Torque on a Dipole, 2-21)

## 2.7 Potential Energy of an Electric Dipole

We can associate potential energy with the orientation of an electric dipole in an electric field.

The dipole has less potential energy when it's in equilibrium orientation. Therefore when  $\vec{\tau} = \vec{p} \times \vec{E} = 0$ . The dipole is like a pendulum, which has the least gravitational potential energy in its equilibrium orientation. In any situation involvint potential energy we are free to define the 0 potential energy configuration. Given  $\Delta U = -W$  and  $W = \int \tau d\theta$  we find the potential energy at any angle  $\theta$  to be:

$$U = -W = -\int_{90^{\circ}}^{\theta} \tau d\theta = \int_{90^{\circ}}^{\theta} pE \sin \theta d\theta \qquad (2-22)$$

Evaluating the integral leads to:

$$U = -pE\cos\theta\tag{2-23}$$

We can generalize this equation in vectorial form as

$$U = -\vec{p} \cdot \vec{E}$$
 (Potential Energy of a Dipole, 2-24)

## 3. Gauss' Law

Gauss' law relates the electric fields at points on a (closed) Gaussian surface to the net charge enclosed by that surface.

### 3.1 Flux

Let's suppose a wide airstream of uniform velocity  $\vec{v}$  at a small square loop of area A. Let  $\Phi$  represent the *volume flow rate* at which the air flows thorugh the loop and let  $\theta$  be the angle between the velocity  $\vec{v}$  and the area vector  $\vec{A}$  (a vector whose magnitude is equal to A and whose direction is normal to the plane of the area A). We can now say that:

$$\Phi = (v\cos\theta)A = \vec{v}\cdot\vec{A} \tag{3-1}$$



Figure 7: An airstream  $\vec{v}$  going through a square of area A

#### 3.2 Flux of an Electric Field

To define the flux of an electric field, we can take an arbitrary (asymmetric) Gaussian Surface immersed in a nonuniform electric field. Let us divide the surface into small squares of area  $\Delta A$ , small enough to neglect the curvature of the surface. We represent each of such element with an area vector  $\Delta \vec{A}$ . Given the small dimension of each square, we can treat the electric field  $\vec{E}$  as constant over any given square. The vector  $\Delta \vec{A}$  and  $\vec{E}$  for each square make some angle  $\theta$  with each other. A first definition for the flux of the electric field for a Gaussian Surface can be:

$$\Phi = \sum \vec{E} \cdot \Delta \vec{A} \tag{3-2}$$

If we allow the area of each square to become smaller and smaller, we can approach a differential limit dA. The area vectors will therefore approach a differential limit  $d\vec{A}$ .



The sum 3-2 becomes a closed surface integral:

$$\Phi = \oint \vec{E} \cdot d\vec{A}$$
 (Electric Flux through a Gaussian Surface, 3-3)

The Flux of an Electric Field is a scalar, and its **SI** unit is the newton-square-meter per coulomb  $[N \cdot m^2/C]$ 

### 3.2.1 Flux through a Closed Cylinder, Uniform Field

Given a **Cylinder**-shaped Gaussian Surface, with radius R immersed in an **uniform** electric field  $\vec{E}$ , with the cylider axis parallel to the field. What is the flux  $\Phi$  of the electric field through this closed surface?


We can find the flux  $\Phi$  by **integrating** the scalar product  $\vec{E} \cdot d\vec{A}$  over the surface. We can do the integration by writing the flux as the sum of three terms: left cylinder cap a, the cylindrical surface b, right cylinder cap c. Thus:

$$\Phi = \oint \vec{E} \cdot d\vec{A} = \int_{a} \vec{E} \cdot d\vec{A} + \int_{b} \vec{E} \cdot d\vec{A} + \int_{c} \vec{E} \cdot d\vec{A}$$

$$\int_{a} \vec{E} \cdot d\vec{A} = \int_{a} E(\cos 180^{\circ}) dA = E \cdot A = -\pi R^{2} E$$

$$\int_{b} \vec{E} \cdot d\vec{A} = \int_{b} E(\cos 90^{\circ}) dA = 0$$

$$\int_{c} \vec{E} \cdot d\vec{A} = \int_{a} E(\cos 90^{\circ}) dA = E \cdot A = \pi R^{2} E$$
Substituting into 3-4 yields:
$$\Phi = -\pi R^{2} E + 0 + \pi R^{2} E = 0$$
(Answer)



The net flux is zero because the field lines that represent the electric field all pass entirely through the Gaussian surface, from the left to the right.

#### 3.3 Gauss' Law

Gauss' Law relates the net flux  $\Phi$  of an electric field through a closed surface (a Gaussian Surface) to the net charge  $q_{enc}$  that is enclosed by that surface. It tells us that:

$$\varepsilon_0 \Phi = q_{enc}$$
 (Gauss' Law, 3-5)

By substituting 3-5 into the definition of Flux, we can also write Gauss' Law as:

$$\varepsilon_0 \oint \vec{E} \cdot d\vec{A} = q_{enc}$$
 (Gauss' Law, 3-6)

These equations holds when the net charge is located in the void or in the air. The net charge  $q_{enc}$  is the algebraic sum of all *enclosed* positive and negative charges.

If  $q_{enc} > 0$  the net flux is *outward*;

if  $q_{enc} < 0$  the net flus is *inward*.

Charges outside the surface are not included in the term  $q_{enc}$  in Gauss' Law. The exact form and location of the charges of the Gaussian Surface are also irrelevant. The only thing that matters on the right side of the equations are the magnitude and sign of the net enclosed charge.

However the quantity  $\vec{E}$  on the left side of Eq. 3-6 is the electric field resulting from all charges, both those inside and those outside the Gaussian Surface, this is due to the fact that the electric field due to a charge outside the Gaussian surface contributes zero net flux through the surface, because as many field lines due to that charge enter the surface as leave it.

In Fig. 8 we have an example of two charges of **equal magnitude**, but **opposite sign**. Four Gaussian Surfaces are shown in cross section:

Surface  $S_1: \vec{E}$  is outward for all points, thus flux  $\Phi > 0$  and  $q_{enc} > 0$ .

Surface  $S_2$ :  $\vec{E}$  is inward for all points, thus flux  $\Phi < 0$  and  $q_{enc} < 0$ .

Surface  $S_3$ : This surface encloses no charge, thus  $q_{enc}=0$ , by Gauss' Law also requires that net flux  $\Phi=0$ .

Surface  $S_4$ : This surface encloses no *net* charge, because the enclosed positive and negative charges have equal magnitudes  $(q_{enc} = q_1 - q_2 = 0)$ . Gauss' Law requires that net flux  $\Phi = 0$ .




Figure 8

#### 3.4 Gauss' Law and Coulomb's Law

Since Coulomb's Law and Gauss' Law are different ways of describing the relationship between **electric charge** and **electric field** in static situations, we should be able to derive each from the other.

Taken a positive point charge q around which we drawn a concentric

Gaussian surface of radius r. We can divide the surface into differential areas dA. By definition the area vector  $d\vec{A}$  is perpendicular and pointed outwards at any point of the surface. From the simmetry of the situation, we know that the field  $\vec{E}$  is also perpendicular to the urface and directed outward. Thus, since the angle  $\theta$  between  $\vec{E}$  and  $d\vec{A}$  is zero, we can rewrite Eq. 3-6 for Gauss' Law as:

$$\varepsilon_0 \oint \vec{E} \cdot d\vec{A} = \varepsilon_0 \oint E dA = q_{enc} \tag{3-7}$$

Here,  $q_{enc}=q$ . Although E varies radially with distance from q, it has same value everywhere on the spherical surface. We can draw the conclusion that E is constant, therefore:

$$\varepsilon_0 E \oint dA = q.$$

The integral now is just the sum of all the points on the surface of the sphere, we can then rewrite the differential dA over the surface of the sphere as  $(4\pi r^2)$ :

$$\varepsilon_0 E(4\pi r^2) = q$$

or, rearranging:

$$E = \frac{1}{4\pi\varepsilon_0} \frac{q}{r^2} \tag{3-8}$$

We can observe that the resulting equation is coherent with Coulomb's Law.

### 3.5 A Charged Isolated Conductor

If an excess charge is placed on an isolated conductor, that amount of charge will move entirely to the surface of the conductor, thus none of the excess charge will be found within the body of the conductor ( Given by the fact that charges with same sign repel one another ).

We take a Gaussian Surface just under the Conductor's Surface

$$E = 0 \rightarrow \Phi = 0 \rightarrow q_{int} = 0$$

The excess charge over an Isolated Conductor lays completely over the external surface.

The same principle applies to an Isolated Conductor with a cavity, its surface has no excess charge.

#### 3.6 External Electric Field

Overall, the charge does not distribute evenly over the Surface of a Conductor.


Eventhough there's a direct relationship between the field  $\vec{E}$  and the (surface) Charge Density  $\sigma$ .

We take a small cylinder that enccapsulates an element of the Surface. The field  $\vec{E}$  is **perpendicular** to the surface (the charge would move otherwise). Therefore the charge  $q_{int}$  enclosed by the Gaussian surface lies on the conductor's surface in an area A. Knowing that  $\sigma$  is the charge per unit area, then  $q_{int}$  is equal to  $\sigma A$ . Substituting  $\sigma A$  for  $q_{int}$  and EA for  $\Phi$ , Gauss' law becomes:

$$\varepsilon_0 E A = \sigma A \tag{3-9}$$

from which we find:

$$E = \frac{\sigma}{\varepsilon_0}$$
 (Conducting Surface, 3-10)



3.7 Gauss' Law: Cylindrical Symmetry