# Foundations of Physics 2A Electromagnetism

Professor D P Hampshire
Epiphany Term 2018

## Contents

Lecture	1		4	
1.1	Maxw	ell's Equations and Classical Physics	4	
	1.1.1	General Comments	4	
1.2	Maxw	Maxwell's Equations and Vector Fields		
	1.2.1	The Flux of a Vector Field	4	
		Comments	5	
	1.2.2	The Divergence Theorem	5	
	1.2.3	Stoke's Theorem	5	
	1.2.4	Vector Identities	5	
Lecture	2		6	
2.1	Maxw	ell 1	6	
	2.1.1	Deriving Gauss' law and Maxwell 1 from Coulomb's Law	6	
Lecture	3		7	
3.1	Apply	ing M1 to a Capacitor Plate	7	
	3.1.1	Comments	7	
3.2	Maxwell 2 (No magnetic monopole)			
	3.2.1	Ampere's Law	7	
	3.2.2	Maxwell 2 from the Biot-Savart Law	8	
Lecture	4		9	
4.1	Maxw	ell 3 from Faraday's Law	9	
	4.1.1	Faraday's Fabulous Experiments	9	
	4.1.2	Using Faraday's Law to find Maxwell 3	9	
	4.1.3	Comments	10	
Lecture	5		11	
5.1	Maxw	ell 4 from Ampere's Law	11	
	5.1.1	Maxwell's Correction to Ampere's Law	11	
5.2	Trans	verse Electromagnetic Waves and Charge Conservation	11	
	5.2.1	Electromagnetic wave in a vacuum	11	

Lecture	6	13
6.1	The Vectorial Nature of Electromagnetic Waves	13
	6.1.1 Implication	13
6.2	Dispersive and Ballistic Motion of Waves	13
6.3	Electromagnetic Waves in Insulators and Conductors	14
Lecture	7	15
7.1	The continuity equation and charge conservation	15
7.2	Maxwell and Einstein	16
	7.2.1 The Collapse of Newtonian/Galilean Physics	16
Lecture	8	17
8.1	Bulk Properties of Conductors, Dielectrics, and Magnetic Materials	17
	8.1.1 Electrical Conductors	17
Lecture	9	19
9.1	Dielectrics	19
	9.1.1 Microscopic Properties and Definitions for Dielectrics	19
	9.1.2 Current Density and Charge Density in Dielectrics	19
Lecture	10	21
10.1	Magnetic Materials	21
	10.1.1 Microscopic Properties and Definitions	21
Lecture	11	23
11.1	Propagation of Transverse EM Waves in Materials	23
	11.1.1 General Dispersion Relation for an Infinite Linear Isotropic Homogeneous Medium .	23
Lecture	12	25
12.1	Advanced Microscopic Descriptions of Normal Conductors, Superconductors, and Dielectrics	26
	12.1.1 Conducting Materials - Metal and Plasma	26
Lecture	13	27
13.1	Superconducting Materials	28
Lecture	14	29
14.1	The material properties and definitions for superconductors	29
14.2	Dielectrics	29

Lecture	15	32
15.1	Auxiliary Fields and the Poynting vector	32
	15.1.1 Electric Displacement Field	32
	15.1.2 Magnetic Field Strength	32
15.2	The Poynting Vector	32
	15.2.1 General Proof	33
Lecture	16	34
16.1	Radiation and Communication	34
	16.1.1 Maxwell's equations rewritten using potentials	34
	16.1.2 Hertzian dipoles/oscillating electric dipoles	34
Lecture	17	36
17.1	Production of a wave	36
17.2	The angular dependence of the power radiated by a Hertzian dipole	37
Lecture	18	38
18.1	The total time-averaged power radiated by a Hertzian dipole	38
18.2	Electromagnetic fields and wave crossing interfaces	38
	18.2.1 Boundary conditions across the interfacial plane between two dielectrics	38
Lecture	19	40
19.1	Boundary conditions across the interfacial plane between two magnetic materials	40
19.2	The laws of geometrical optics	41
Lecture	20	43
20.1	Fresnel's Equations	43
	20.1.1 Perpendicular Equations	43
	20.1.2 Parallel Equations	44
20.2	Coefficient of reflection and transmission	45
Lecture	21	46
21.1	Coefficients of relection and transmission	46
21.2	Wave guides	46
	21.2.1 Waves propagating in a hollow rectangular waveguide	46
	21.2.2 Phase velocity	47

Summary sheets are provided on DUO to go with these

#### Maxwell's Equations and Classical Physics 1.1

Feynman claims that there are seven equations that describe all of classical physics; the first four of these are Maxwell's Equations:

1. From Coulomb's Law:

$$\underline{\nabla} \cdot \underline{\mathcal{E}} = \frac{\rho}{\epsilon_0} \tag{MI}$$

2. Given no magnetic monopoles have been observed:

$$\nabla \cdot \underline{\mathcal{B}} = 0 \tag{MII}$$

3. From Faraday's Law of Induction:

$$\underline{\nabla} \times \underline{\mathcal{E}} = -\frac{\partial \mathcal{B}}{\partial t} \tag{MIII}$$

4. From Ampere's Law:

$$\underline{\nabla} \times \underline{\mathcal{B}} = \mu_0 \underline{J} + \mu_0 \epsilon_0 \frac{\partial \mathcal{E}}{\partial t}$$
(MIV)

where the symbol  $\nabla$  denotes the vector operator 'del':

$$\underline{\nabla} = \hat{i}\frac{\partial}{\partial x} + \hat{j}\frac{\partial}{\partial v} + \hat{k}\frac{\partial}{\partial z}$$
 (1.1)

 $\triangleright \underline{\mathcal{E}}$  - electric field  $(V m^{-1})$ 

 $\blacktriangleright$   $\underline{\mathcal{B}}$  - magnetic field (T)

ightharpoonup 
ho - total charge density ( $C m^{-3}$ ) ightharpoonup J - total current density ( $A m^{-2}$ )

5. Force on a moving charge in a magnetic and electric field:

$$F = q(\mathcal{E} + v \times \mathcal{B}) \tag{1.2}$$

6. Newton's Law of Motion:

$$\underline{F} = \frac{d\underline{p}}{dt}, \ \underline{p} = \frac{m\underline{v}}{\sqrt{1 - \frac{v^2}{c^2}}} \tag{1.3}$$

7. Newton's Law of Gravity:

$$\underline{F} = -\frac{Gm_1m_2}{r^2}\hat{r}_{1\to 2} \tag{1.4}$$

#### 1.1.1 General Comments

- ➤ There is no agreed order for Maxwell's equations.
- ➤ Maxwell's equations are completely general and valid at every point in space and time.
- ▶ There is a divergence equation (i.e.  $\nabla$ ·) for both  $\mathcal{E}$  and  $\mathcal{B}$  and a curl equation (i.e.  $\nabla$ ×) for each as well.
- $\triangleright$   $\mathcal{E}$  and  $\mathcal{B}$  always refer to the net field.

#### 1.2 Maxwell's Equations and Vector Fields

#### **1.2.1** The Flux of a Vector Field

A vector field is fully characterised by knowing its magnitude and direction at every point in space and time.

An arbitrarily shaped three-dimensional 'closed surface' is the surface of the volume. A smooth 'open surface' is also shown which does not enclose volume and has edges.

$$d\underline{S} = \hat{n} \cdot dS \tag{1.5}$$

The vector  $\hat{n}$  is the outward normal unit vector to the surface and  $\underline{h}$  is an arbitrary vector field.

By definition, the surface area element,  $d\underline{S}$ , is  $d\underline{S} = \hat{n} \cdot dS$ , where dS is the scalar area of the element. In general, we can say "the flux of a vector h through the surface is

$$\phi = \int \underline{h} \cdot \hat{n} dS = \int \underline{h} \cdot d\underline{S}.$$
 (1.6)

#### Comments

- ➤ The flux of charge density is current.
- ➤ Flux is a useful concept for describing conservation laws energy, momentum, charge, etc.

Be careful the joys of the English word 'density':

- ➤ Mass density  $kg m^{-3}$
- $\triangleright$  Current density  $A m^{-2}$

#### **1.2.2** The Divergence Theorem

The divergence theorem is a vector calculus identity:

$$\int \underline{h} \cdot d\underline{S} = \int \underline{\nabla} \cdot \underline{h} dV \tag{1.7}$$

where h is any arbitrary vector field.

#### 1.2.3 Stoke's Theorem

$$\int \underline{h} \cdot d\underline{l} = \int (\underline{\nabla} \times \underline{h}) \cdot d\underline{S}$$
 (1.8)

Note that l and S are vectors, V is scalar.

- ➤ Divergence theorem: volume integral to surface integral
- ➤ Stoke's theorem: surface integral to line integral

#### 1.2.4 Vector Identities

$$\underline{\nabla} \times (\underline{\nabla} \times \underline{A}) = \underline{\nabla}(\underline{\nabla} \cdot \underline{A}) - \underline{\nabla}^2 \underline{A} \tag{1.9}$$

$$\underline{\nabla} \cdot (\underline{A} \times \underline{B}) = \underline{B} \cdot (\underline{\nabla} \times \underline{A}) - \underline{A} \cdot (\underline{\nabla} \times \underline{B}) \tag{1.10}$$

#### 2.1 Maxwell 1

#### 2.1.1 Deriving Gauss' law and Maxwell 1 from Coulomb's Law

The cone first passes through a sphere centred about the charge and then through the surface of the arbitrary closed shape.

Consider first the sphere:

The electric field, E(r'), has constant magnitude over the surface of the sphere and is everywhere parallel to  $d\underline{S}'$ , i.e.  $\hat{n} dS'$  so we have:

$$\int \underline{\mathcal{E}}(r') \cdot d\underline{S}' = \frac{q}{4\pi\epsilon_0(r')^2} \cdot 4\pi(r')^2 = \frac{q}{\epsilon_0}$$
 (2.1)

Consider now the flux through the elemental area dS, which is part of the surface of the arbitrary shape surrounding the charge. We have:



$$\underline{\mathcal{E}}(\underline{r}) \cdot \hat{n} \, dS = |E(r)||\hat{n}||\cos\theta|dS \tag{2.2}$$

Since dS is a projection of dS' (because they are both bound by the same cone), we can relate the two of them using:

$$\frac{dS'}{\pi(r')^2} = \frac{dS}{\pi r^2} \cos \theta \tag{2.3}$$

Substituting, we have:

$$\underline{\mathcal{E}}(r) \cdot \hat{n} \, dS = E(r) \frac{r^2}{(r')^2} dS' \tag{2.4}$$

$$=\frac{q}{4\pi\epsilon_0 r^2} \frac{r^2}{(r')^2} dS' \tag{2.5}$$

$$=\frac{q}{4\pi\epsilon_0(r')^2}dS' \tag{2.6}$$

Hence the flux through the surface dS is the same as the flux through dS'. Integrating gives:

$$\int \underline{\mathcal{E}} \cdot d\underline{S} = \frac{q}{\epsilon_0} \tag{2.7}$$

Applying superposition to a collection of charges inside the arbitrary shape gives:

$$\int \underline{\mathcal{E}} \cdot d\underline{S} = \frac{\sum q}{\epsilon_0} = \frac{1}{\epsilon_0} \int \rho \, dV$$
 (Gauss' Law)

Where  $\rho$  is the charge density and then we can use the divergence theorem:

$$\int \underline{\nabla} \cdot \underline{\mathcal{E}} dV = \frac{1}{\epsilon_0} \int \rho \, dV \tag{2.8}$$

Since the volume integrals are equal for any arbitrary volume, the integrands must also be equal so:

$$\underline{\nabla} \cdot \underline{\mathcal{E}} = \frac{\rho}{\epsilon_0} \tag{MI}$$

We conclude that Maxwell's 1st equation is a differential form of Gauss' Law, which in turn is a form of Coulomb's Law.

Coulomb's Law (or equivalently Gauss' Law) is only true under static conditions. Just as with Hooke's Law, experimentation shows us that MI is true under all conditions.

The  $\underline{\mathcal{E}}$ -field resulting from any charge distribution gives  $\underline{\nabla} \cdot \underline{\mathcal{E}} = 0$  in the local regions where there is no charge.

#### 3.1 Applying M1 to a Capacitor Plate

There is no charge density so:

$$\underline{\nabla} \cdot \underline{\mathcal{E}} = \frac{\partial E_x}{\partial x} + \frac{\partial E_y}{\partial y} + \frac{\partial E_z}{\partial z}$$

$$\underline{\nabla} \cdot \underline{\mathcal{E}} = \frac{1}{r^2} \frac{\partial}{\partial r} \left( \underbrace{r^2 E_r}_{=0 \text{ (Coulomb)}} \right) + \frac{1}{r \sin \theta} \frac{\partial}{\partial \theta} \left[ E_{\theta} \sin \theta \right] + \frac{1}{r \sin \theta} \frac{\partial}{\partial \phi} (E_{\phi}) = 0$$
(3.1)
$$(3.2)$$

#### 3.1.1 Comments

- ▶  $\underline{\nabla} \cdot \underline{\mathcal{E}}$  describes the spatial dependence of the  $\underline{\mathcal{E}}$ -field
- ▶  $\overline{\nabla} \cdot \underline{\mathcal{E}} = 0$  is true at every point where there is no charge
- $ightharpoonup \overline{\nabla} \cdot \overline{\mathcal{E}} = 0$  does not necessarily imply  $\underline{\mathcal{E}} = 0$
- ▶  $\underline{\nabla} \cdot \underline{\mathcal{E}} = 0$  can result from any superposition of diverging  $\underline{\mathcal{E}}$ -fields from isolated charges where  $\underline{\mathcal{E}}$  is exactly proportional to  $\frac{1}{r^2}$
- ➤ Understanding the physics helps to understand the mathematics

#### 3.2 Maxwell 2 (No magnetic monopole)

#### 3.2.1 Ampere's Law

Ampere found that two parallel straight wires carrying currents  $I_1$  and  $I_2$  in the same direction lead to a force  $F_2$  on a length L of the wire carrying  $I_2$  where

$$\underline{F}_2 = -\frac{\mu_0 I_1 I_2 L}{2\pi d} \hat{r}_{1 \to 2} \tag{A}$$

and d is the separation between the wires.

We can introduce a magnetic field, where

$$\underline{F} = q(\underline{v} \times \underline{\mathcal{B}}). \tag{B}$$

Given that the definition of current is the charge that passes per second,

$$I = Q_L \cdot v \tag{C}$$

where  $Q_L$  is the charge per unit length, and v is the velocity of charges.

Comparing A and B with C:

$$\int \underline{\mathcal{B}} \cdot d\underline{l} = \mu_0 I$$
 (Ampere's Law)

where I is the current that passes through the surface that is bounded by the path integral of the magnetic field.

$$\int \underline{\mathcal{B}} \cdot d\underline{l} = \underline{\mathcal{B}} \cdot 2\pi r = \mu_0 I \tag{3.3}$$

$$\Longrightarrow \underline{\mathcal{B}} = \frac{\mu_0 I}{2\pi r} \hat{\phi} \tag{3.4}$$

(3.5)

#### **3.2.2** Maxwell 2 from the Biot-Savart Law

Ampere's Law can be written in the form of the Biot-Savart Law that describes the small field ( $\delta \underline{\mathcal{B}}$ ) produced by a small length of a current element ( $I d\underline{l}$ ) where:

$$\delta \underline{\mathcal{B}} = \frac{\mu_0 I}{4\pi r^2} \delta \underline{l} \times \hat{r} = \frac{\mu_0 I}{4\pi r^2} \sin\theta \, dl \, \hat{\phi} \tag{3.6}$$

$$\underline{\nabla} \cdot (\delta \underline{\mathcal{B}}) = \frac{1}{\rho} \frac{\partial (\rho \, \delta B_{\rho})}{\partial \rho} + \frac{1}{\rho} \underbrace{\frac{\partial \, \delta B_{\phi}}{\partial \phi}}_{=0 \text{ (B-S)}} + \frac{1}{r \sin \theta} \frac{\partial}{\partial \theta} (\delta B_z) = 0 \tag{3.7}$$

$$\underline{\nabla} \cdot (\delta \underline{\mathcal{B}}) = 0 \tag{3.8}$$

$$\sum \delta \underline{\mathcal{B}} = \underline{\mathcal{B}} \tag{3.9}$$

This leads to Maxwell's second equation:

$$\nabla \cdot \underline{\mathcal{B}} = 0 \tag{MII}$$

The net flux through both surfaces is zero.

Integrating Maxwell II:

$$\int \underline{\nabla} \cdot \underline{\mathcal{B}} \, dV = \int 0 \cdot dV \implies \int \underline{\mathcal{B}} \cdot d\underline{S} = 0 \tag{3.10}$$

Hence in all experiments to date, we have found that the net magnetic flux through any closed surface is zero.

#### 4.1 Maxwell 3 from Faraday's Law

#### 4.1.1 Faraday's Fabulous Experiments

#### ➤ <u>Inductive Electromotive Force</u>:

The voltage difference across a single loop wrapped around a coil (or solenoid) is:

$$V = \frac{d\mathcal{B}}{dt}\underline{S} = \frac{\partial \phi_{\mathcal{B}}}{\partial t},$$
 (Faraday's Law of Induction)

where  $\phi_{\mathcal{B}}$  is the flux of the magnetic field. Outside the loop, the  $\underline{\mathcal{B}}$ -field is zero, but the changing magnetic field inside the solenoid generates an  $\underline{\mathcal{E}}$ -field outside and inside the solenoid.

#### ➤ Motional Electromotive Force:

A loop of wire moving with velocity,  $\underline{u}$ , down through the homogeneous field produced between the two magnetic pole pieces. Using Faraday's Law of Induction,

$$V = \frac{\partial \phi_{\mathcal{B}}}{\partial t} = \mathcal{B} \frac{\partial S(t)}{\partial t} = \mathcal{B} \underline{u} \omega, \tag{4.1}$$

where S(t) is the instantaneous partial area of the loop with magnetic field,  $\underline{\mathcal{B}}$ , passing through it. Alternatively, we can think about the Lorentz force on the free positive charges in the wire in the horizontal (bottom) part of the loop of wire. The charges build up at one end of wire and the net force on free positive charges is

$$\underline{F} = q(\underline{\mathcal{E}} + \underline{v} \times \underline{\mathcal{B}}). \tag{4.2}$$

In equilibrium,

$$\mathcal{E} = -v \times \mathcal{B}. \tag{4.3}$$

Therefore the net voltage produced is

$$V = -\omega \mathcal{E} = \mathcal{B}u\omega \tag{4.4}$$

Maxwell was the first to point out (leading Einstein to relativity) that the voltage generated in the experiment can be explained using two completely different physical explanations.

Faraday's experiments demonstrate that the law of induction is correct no matter why the flux changes; whether the loop moves or the pole pieces move.

#### **4.1.2** Using Faraday's Law to find Maxwell 3

Faraday's Law:

$$\xi_t = -\frac{\partial \phi_{\mathcal{B}}}{\partial t} \tag{4.5}$$

$$\xi_t = \int \underline{\mathcal{E}} \cdot d\underline{l} = -V, \tag{4.6}$$

where  $\xi_t$  is the electromotive force (the tangential force per unit charge, integrated over length, once around the complete circuit).

Using Faraday's Law,

$$\xi_t = \int \underline{\mathcal{E}} \cdot d\underline{l} = -\frac{\partial \phi_{\mathcal{B}}}{\partial t} = -\frac{\partial}{\partial t} \int \underline{\mathcal{B}} \cdot d\underline{S}. \tag{4.7}$$

Then using Stoke's Theorem:

$$\int (\underline{\nabla} \times \underline{\mathcal{E}}) \cdot d\underline{S} = -\frac{\partial}{\partial t} \int \underline{\mathcal{B}} \cdot d\underline{S}$$
(4.8)

Therefore, the integrands can be equated to get:

$$\underline{\nabla} \times \underline{\mathcal{E}} = -\frac{\partial \underline{\mathcal{B}}}{\partial t} \tag{MIII}$$

## 4.1.3 Comments

- 1. The curl of  $\underline{\mathcal{E}}$  is zero outside the coil, but  $\underline{\mathcal{E}}$  is not zero. 2. Maxwell III is true at all space and time.


#### 5.1 Maxwell 4 from Ampere's Law

#### **5.1.1** Maxwell's Correction to Ampere's Law

The surfaces bounded by path A and C each have a current I that threads through them. Path B has no current threading through it.

If Paths A, B, and C are distant from the wire and capacitor, one finds experimentally that the magnetic field is the same at all three

Hence if the moving charges generate both an  $\underline{\mathcal{E}}$ -field and a  $\underline{\mathcal{B}}$ -field (as in the circuit shown), Ampere's Law breaks down. Using Gauss' Law for the  $\underline{\mathcal{E}}$ -field inside the capacitor and consider the volume D that encloses the capacitor plate:



$$\int \underline{\mathcal{E}} \cdot d\underline{S} = \int \frac{\rho}{\epsilon_0} dV = \frac{Q}{\epsilon_0}$$
 (5.1)

For the capacitor, using conservation of charge:

$$I = \frac{dQ}{dt} \tag{5.2}$$

Consider Path B:

$$\oint \mathcal{E} \cdot dS = \int \mathcal{E} \cdot dS \tag{5.3}$$

$$\implies \frac{\partial}{\partial t} \int \underline{\mathcal{E}} \cdot d\underline{S} = \frac{1}{\epsilon_0} \frac{\partial Q}{\partial t} = \frac{I}{\epsilon_0}$$
 (5.4)

Hence, a general equation for Paths A, B, and C is of the form

$$\int \underline{\mathcal{B}} \cdot d\underline{l} = \mu_0 \int \underline{J} \cdot d\underline{S} + \mu_0 \varepsilon_0 \frac{\partial}{\partial t} \int \underline{\mathcal{E}} \cdot d\underline{S}$$
 (5.5)

Using Stokes' Theorem:

$$\int \underline{\nabla} \times \underline{\mathcal{B}} \cdot d\underline{S} = \mu_0 \int \underline{I} \cdot d\underline{S} + \mu_0 \varepsilon_0 \frac{\partial}{\partial t} \int \underline{\mathcal{E}} \cdot d\underline{S}$$
 (5.6)

Given this is true for any surface:

$$\underline{\nabla} \times \underline{\mathcal{B}} = \mu_0 \underline{J} + \mu_0 \epsilon_0 \frac{\partial \underline{\mathcal{E}}}{\partial t}$$
 (MIV)

where by definition,  $\underline{\underline{J}_{disp}} = \epsilon_0 \frac{\partial \underline{\mathcal{E}}}{\partial t}$ , and  $\underline{\underline{J}_{disp}}$  is defined as the displacement current density.

From Maxwell's four equations, if we know the charges present and the currents flowing, we can calculate all the  $\mathcal{E}$ -fields and  $\mathcal{B}$ -fields in a system.

#### 5.2 Transverse Electromagnetic Waves and Charge Conservation

#### **5.2.1** Electromagnetic wave in a vacuum

If we assume that there are no charges or currents present,

$$\underline{\nabla} \cdot \underline{\mathcal{E}} = \frac{\rho}{\epsilon_0} = 0 \tag{5.7}$$

$$\underline{\nabla} \cdot \underline{\mathcal{B}} = 0 \tag{5.8}$$

$$\underline{\nabla} \times \underline{\mathcal{E}} = -\frac{\partial \underline{\mathcal{B}}}{\partial t}$$

$$\underline{\nabla} \times \underline{\mathcal{B}} = \mu_0 \epsilon_0 \frac{\partial \underline{\mathcal{E}}}{\partial t}$$

$$(5.9)$$

$$\underline{\nabla} \times \underline{\mathcal{B}} = \mu_0 \epsilon_0 \frac{\partial \mathcal{E}}{\partial t} \tag{5.10}$$

Take the curl of Maxwell III:

$$\underline{\nabla} \times \underline{\nabla} \times \underline{\mathcal{E}} = -\frac{\partial}{\partial t} \underline{\nabla} \times \underline{\mathcal{B}}$$
 (5.11)

Use the vector identity:

$$\underline{\nabla} \times \underline{\nabla} \times \underline{\mathcal{E}} = \underline{\nabla}(\underline{\nabla} \cdot \underline{\mathcal{E}}) - \nabla^2 \underline{\mathcal{E}}$$
 (5.12)

$$\nabla^2 = \frac{\partial^2}{\partial x^2} + \frac{\partial^2}{\partial y^2} + \frac{\partial^2}{\partial z^2}$$
 (5.13)

$$\Longrightarrow \nabla^2 \underline{\mathcal{E}} = \mu_0 \frac{\partial^2 \underline{\mathcal{E}}}{\partial t^2} \tag{5.14}$$

$$\implies c = \frac{1}{\sqrt{\mu_0 \epsilon_0}} \tag{5.15}$$

Maxwell used measurements from Weber and Kohlrausch available and found that

$$c_{Maxwell} = 3.11 \times 10^8 \, m \, s^{-1} \tag{5.16}$$

The best optical data (Foucault) gave

$$c_{Foucault} = 2.98 \times 10^8 \, m \, s^{-1} \tag{5.17}$$

Using the curl of Maxwell IV:

$$\nabla^2 \underline{\mathcal{B}} = \mu_0 \epsilon_0 \frac{\partial^2 \underline{\mathcal{B}}}{\partial t^2} \tag{6.1}$$

#### 6.1 The Vectorial Nature of Electromagnetic Waves

Given that  $\mathcal{E}$  and  $\mathcal{B}$  are plane waves of the form:

$$\underline{\mathcal{E}}(\underline{r},t) = \underline{\mathcal{E}}_0 \exp(i[\underline{k} \cdot \underline{r} - \omega t]) \tag{6.2}$$

$$\underline{\mathcal{B}}(\underline{r},t) = \underline{\mathcal{B}}_0 \exp(i[\underline{k} \cdot \underline{r} - \omega t]) \tag{6.3}$$

 $\underline{\mathcal{E}}_0$  and  $\underline{\mathcal{B}}_0$  are the polarisation vectors for  $\underline{\mathcal{E}}$  and  $\underline{\mathcal{B}}$ , and  $\underline{k}$  gives the magnitude of the wave-vector and direction of propagation.

There are non-trivial (i.e. real) solutions only if  $\omega$  and  $\underline{k}$  are the same for  $\underline{\mathcal{E}}$  and  $\underline{\mathcal{B}}$ . The solution for the wave equation for electromagnetic waves can be written as:

$$\underline{k} \cdot \underline{k} = k^2 = \omega^2 \mu_0 \epsilon_0 \tag{6.4}$$

$$\implies v_{phase} = f \lambda = \frac{\omega}{k} = \sqrt{\frac{1}{\mu_0 \epsilon_0}} \tag{6.5}$$

Substituting the plane wave solutions into Maxwell III:

$$\underline{\nabla} \times \underline{\mathcal{E}} = i\underline{k} \times \underline{\mathcal{E}} = -\frac{\partial \underline{\mathcal{B}}}{\partial t} = i\omega\underline{\mathcal{B}}$$
(6.6)

$$\implies i\underline{k} \times \underline{\mathcal{E}}_0 = i\omega\underline{\mathcal{B}}_0 \tag{6.7}$$

Similarly from Maxwell IV:

$$\underline{k} \times \underline{\mathcal{B}}_0 = -\mu_0 \varepsilon_0 \omega \underline{\mathcal{E}}_0 \tag{6.8}$$

#### **6.1.1** Implication

- $\triangleright$   $\mathcal{E}, \mathcal{B}$ , and k are all orthogonal to each other in a vacuum
- $ightharpoonup |\overline{\underline{\mathcal{B}}_0}|$  is a factor of c smaller than  $|\underline{\mathcal{E}}_0|$
- $\triangleright$   $\underline{\mathcal{E}}_0 \times \underline{\mathcal{B}}_0$  is in the direction of  $\underline{k}$  which is the direction of propagation

#### 6.2 Dispersive and Ballistic Motion of Waves

- ➤ Ballistic motion does not change as it moves through space (ball flying through air)
- ➤ Dispersive motion changes as it moves through space (ripple on pond)
- 1. The phase velocity (of each component of a disturbance) is:

$$v_{phase} = f \lambda = \frac{\omega}{k}, \ k \in \mathbb{R}$$
 (6.9)

2. The group velocity for a disturbance is determined by how the peak of the disturbance moves through space as a function of time.

$$v_{group} = \frac{\partial \omega}{\partial k} \bigg|_{k=k_0}$$
,  $k_0 = \text{average value}$  (6.10)

3. If the motion is ballistic:

$$\frac{\partial^2 \omega}{\partial k^2} = 0 \tag{6.11}$$

If the motion is dispersive:

$$\frac{\partial^2 \omega}{\partial k^2} \neq 0 \tag{6.12}$$

#### 6.3 Electromagnetic Waves in Insulators and Conductors

We can use Maxwell's equations and Ohm's Law to describe electromagnetic waves propagating through metals.

Taking the curl of Maxwell III:

$$\underline{\nabla} \times \underline{\nabla} \times \underline{\mathcal{E}} = -\frac{\partial}{\partial t} \underline{\nabla} \times \underline{\mathcal{B}}$$
 (6.13)

Substituting Ohm's Law ( $\underline{I} = \sigma_N \underline{\mathcal{E}}$ ) into Maxwell IV gives:

$$\underline{\nabla} \times \underline{\mathcal{B}} = \mu_0 \underline{J} + \mu_0 \varepsilon_0 \frac{\partial \mathcal{E}}{\partial t} \tag{6.14}$$

$$=\mu_0 \sigma_N \underline{\mathcal{E}} + \mu_0 \epsilon_0 \frac{\partial \underline{\mathcal{E}}}{\partial t} \tag{6.15}$$

$$\underline{\nabla} \times \underline{\nabla} \times \underline{\mathcal{E}} = -\mu_0 \sigma_N \frac{\partial \underline{\mathcal{E}}}{\partial t} - \mu_0 \varepsilon_0 \frac{\partial^2 \underline{\mathcal{E}}}{\partial t^2}$$
(6.16)

Using the vector identity:

$$\nabla \times \nabla \times \mathcal{E} = \nabla(\nabla \cdot \mathcal{E}) - \nabla^2 \mathcal{E} \tag{6.17}$$

$$\implies \nabla^2 \underline{\mathcal{E}} = \mu_0 \sigma_N \frac{\partial \underline{\mathcal{E}}}{\partial t} + \mu_0 \varepsilon_0 \frac{\partial^2 \underline{\mathcal{E}}}{\partial t}$$
 (6.18)

We assume:

$$\underline{\mathcal{E}}(\underline{r},t) = \underline{\mathcal{E}}_0 \exp(i[\underline{k} \cdot \underline{r} - \omega t]) \tag{6.19}$$

Note:  $\omega$  is always real and constant.

We allow  $\underline{k}$  to be a complex vector. When  $\underline{k}$  has both real and imaginary parts, the wave is both oscillating and decaying.

Substituting into the wave equation:

$$k^2 = \mu_0 \epsilon_0 \omega^2 + i\omega \mu_0 \sigma_N$$
 (Dispersion Relation)

A dispersion relation is one that gives us  $\omega$  vs  $\underline{k}$ .

1. For a highly insulating material,

$$\sigma_N \to 0$$
 (6.20)

$$\implies k^2 = \mu_0 \epsilon_0 \omega^2 \tag{6.21}$$

$$\implies k = \sqrt{\mu_0 \epsilon_0} \omega \tag{6.22}$$

$$\implies v_{phase} = \frac{\omega}{k} = \frac{1}{\sqrt{\mu_0 \epsilon_0}} \tag{6.23}$$

2. For a highly conducting material,

$$\sigma_N \to \infty$$
 (6.24)

$$\implies k^2 = i\omega\mu_0\sigma_N \tag{6.25}$$

$$\sqrt{i} = \frac{1+i}{\sqrt{2}} \tag{6.26}$$

$$\implies k = (1+i)\sqrt{\frac{\omega\mu_0\sigma_N}{2}} = \frac{1+i}{\delta}, \ \delta = \sqrt{\frac{2}{\omega\mu_0\sigma_N}}$$
 (6.27)

The solution is found by simply substituting back into the plane wave equation:

$$\underline{\mathcal{E}} = \underline{\mathcal{E}}_0 \exp\left[i\left(\left(\frac{1+i}{\delta}\right)x - \omega t\right)\right] \tag{6.28}$$

$$= \underline{\mathcal{E}}_0 \exp\left[i\left(\frac{x}{\delta} - \omega t\right)\right] \exp\left(-\frac{x}{\delta}\right) \tag{6.29}$$

$$k = (1+i)\sqrt{\frac{\omega\mu_0\sigma_N}{2}} = \frac{1+i}{\delta} \tag{7.1}$$

$$\underline{\mathcal{E}} = \underline{\mathcal{E}}_0 \exp\left[i(kx - \omega t)\right] \tag{7.2}$$

$$= \underline{\mathcal{E}}_0 \exp\left[i\left(\frac{1+i}{\delta}x - \omega t\right)\right] \tag{7.3}$$

$$= \underline{\mathcal{E}}_0 \exp\left[i\left(\frac{x}{\delta} - \omega t\right)\right] \exp\left(-\frac{x}{\delta}\right) \tag{7.4}$$

We extract the important physics by taking the real of imaginary part of  $\underline{\mathcal{E}}$ .

The real part:

$$\underline{\mathcal{E}} = \underline{\mathcal{E}}_0 \cos\left(\frac{x}{\delta} - \omega t\right) \exp\left(-\frac{x}{\delta}\right) \tag{7.5}$$

The wavelength,  $\lambda=\frac{2\pi}{k_{real}}=2\pi\delta$ , and the decay length (known as the 'skin depth' for highly conducting materials),  $\delta=\frac{1}{k_{\Gamma}}$ 

For copper at optical frequencies:

$$\delta = \sqrt{\frac{2}{\omega \mu_0 \sigma_N}} = 4 \, nm \tag{7.6}$$

#### 7.1 The continuity equation and charge conservation

Maxwell IV:

$$\underline{\nabla} \times \underline{\mathcal{B}} = \mu_0 \underline{J} + \mu_0 \epsilon_0 \frac{\partial \underline{\mathcal{E}}}{\partial t} \tag{7.7}$$

$$\underline{\nabla} \cdot \underline{\nabla} \times \underline{\mathcal{B}} = \mu_0 \underline{\nabla} \cdot \underline{J} + \mu_0 \epsilon_0 \frac{\partial}{\partial t} \underline{\nabla} \cdot \underline{\mathcal{E}}$$
 (7.8)

$$\Longrightarrow \underline{\nabla} \cdot \underline{\underline{I}} = -\mu_0 \epsilon_0 \frac{\partial}{\partial t} \underbrace{\underline{\nabla} \cdot \underline{\mathcal{E}}}_{ML} \tag{7.9}$$

$$\underline{\nabla} \cdot \underline{J} = -\frac{\partial \rho}{\partial t}$$
 (Continuity Equation)

Take the volume integral of both sides:

$$\int \underline{\nabla} \cdot \underline{I} \, dV = -\int \frac{\partial \rho}{\partial t} \, dV \tag{7.10}$$

$$\int \underline{J} \cdot d\underline{S} = -\int \frac{\partial \rho}{\partial t} dV \tag{7.11}$$

Charge flowing out through the surface every second = Change in total charge inside the volume every second (7.12)

Hence the continuity equation is equivalent to conservation of charge  $\implies$  Maxwell's equations require the conservation of charge.

#### 7.2 Maxwell and Einstein

#### 7.2.1 The Collapse of Newtonian/Galilean Physics

1. observer P: stationary with respect to positive charges, sits on positive charges and watches negative charges move past with velocity, v

$$\underline{F} = q(\underline{\mathcal{E}} + \underline{v} \times \underline{\mathcal{B}}) \tag{7.13}$$

For a charge-neutral wire and an external charge that is not moving,  $\underline{F} = 0$ , this implies the test charge does not move.

2. observer N: stationary with respect to the negative charges, observes positive charges move past with velocity, v

$$\underline{F} = q(\underline{\mathcal{E}} + \underline{v} \times \underline{\mathcal{B}}) \tag{7.14}$$

For a charge-neutral wire, we again assume the electric field is zero. However,  $\underline{v}$  and  $\underline{\mathcal{B}}$  are non-zero, so N concludes that Maxwell's equations predict the positive test charge moves towards the wire.

If we assume the wire is charge-neutral in both frames, Maxwell's equations give a contradiction. Assume that for observer N, the wire is charge-neutral (i.e. in the rest frame of the battery).

$$I = n_1 e v (7.15)$$

$$\underline{\mathcal{B}} = \frac{\mu_0 I}{2\pi r} \hat{\phi} = \frac{\mu_0 n_1 e v}{2\pi r} \hat{\phi} \tag{7.16}$$

$$F = q\underline{v} \times \underline{\mathcal{B}} \tag{7.17}$$

$$\Longrightarrow \underline{F}_N = -\frac{\mu_0 q n_1 e v^2}{2\pi r} \hat{r} \tag{7.18}$$

For Observer P, there is a Lorentz contraction of the moving negative charges:

$$\lambda_{-\nu e} = -\gamma n_2 e \tag{8.1}$$

where  $\lambda$  is the charge per unit length,  $\gamma = \frac{1}{\sqrt{1 - \frac{v^2}{c^2}}}$ .

Observer P also says that given there is charge neutralily for Observer N,

$$\lambda_{+\nu e} = \frac{n_1 e}{\gamma} \tag{8.2}$$

$$\implies \lambda_{total} = -\gamma n_2 e \left( 1 - \frac{1}{\gamma^2} \right) = -\gamma n_2 e \frac{v^2}{c^2}$$
(8.3)

From Gauss' Law:

$$\Longrightarrow \underline{\mathcal{E}}_p = \frac{\lambda_{total}\hat{r}}{2\pi\epsilon_0 r} \Longrightarrow \underline{\mathcal{E}}_p = -\frac{\gamma\mu_0 n_2 e v^2}{2\pi r}\hat{r}$$
(8.4)

$$\Longrightarrow F_p = q\underline{\mathcal{E}}_p = \gamma q\underline{v} \times \underline{\mathcal{B}} = \gamma \underline{F}_n \tag{8.5}$$

The force that was purely magnetic for observer N is purely electrostatic for observer P. They both agree the positive charge crashes into the wire.

Observer N is in the non-accelerating rest frame:

$$\delta t_N = \gamma \delta t_P \tag{8.6}$$

$$F_p = \frac{\partial P_p}{\partial t_p} \; ; \; F_N = \frac{\partial P_N}{\partial t_N}$$
 (8.7)

$$\implies \delta P_p = \delta P_N \tag{8.8}$$

The two observers agreees that the change in momentum is the same in the direction orthogonal to the motion, as required by relativity.

There are parallels between the roles of the charges and the battery with Einstein's twin paradox. Observer N is in the rest frame of the battery. This is analogous to the twin that stays at home.

Coulomb's law can be regarded as fundamental with magnetic forces and induced EMF being relativistic corrections to this.

#### 8.1 Bulk Properties of Conductors, Dielectrics, and Magnetic Materials

#### 8.1.1 Electrical Conductors

#### Microscopic properties for conductors

- ➤ Drude Model is that the electric field accelerates the charges which then collide with the scattering sites.
- $\blacktriangleright$  Take N to be the number of charges per unit volume; q to be the charge on each carrier; and  $\tau$  as the scattering time:

$$\rho_N = \frac{m}{N q^2 \tau} \tag{8.9}$$

#### Extensive and Intensive Variables

$$V = IR$$
 (Ohm's Law)

R - extensive property which depends on the amount and the shape of the material being measured.

Rewriting Ohm's Law:

$$\frac{V}{L} = \frac{I}{A} \cdot \frac{RA}{L} \tag{8.10}$$

$$E = J\rho_N \tag{8.11}$$

This defines resistivity as an intensive variable By definition,  $\rho_N = \frac{1}{\sigma_N}$ , where  $\sigma_N$  is the conductivity.

#### **Current Densities and Charge Densities**

$$J = \sigma_N \underline{\mathcal{E}}$$
 (Current Density)

In general, the movement of bulk charge density in conductors is so fast that we can assume to a good approximation that  $\rho = 0$ .

Using Ohm's Law, Maxwell I, and the continuity equation, we can use a dimensionality argument to find

$$\tau = \rho_N \epsilon_0 \tag{8.12}$$

For copper,  $\rho_N \approx 10^{-8}\,\Omega$  m, we find that  $\tau$  (characteristic time for charge density to change) is  $\approx 10^{-20}\,s$ . This can be compared to the inverse frequency for light -  $3\times 10^{-15}\,s$ 

#### 9.1 Dielectrics

- 9.1.1 Microscopic Properties and Definitions for Dielectrics
  - 1. Polar Dielectrics: e.g. water
    - ➤ A permanent dipole moment.
    - ▶ Increasing the  $\underline{\mathcal{E}}$ -field increases the number of dipoles that overcome the randomising effects of temperature so they rotate into the direction of the applied field.
  - 2. Non-Polar Dielectrics: e.g. Ar, CO<sub>2</sub>
    - $\blacktriangleright$  Increasing the  $\mathcal{E}$ -field causes separation of positive and negative charges.

Dielectrics produce their own electric field, with the fundamental response of a dialectric:

$$p = q\underline{d} \tag{9.1}$$

This is the definition of the elementary dipole moment, p

$$\underline{P} = Np \tag{9.2}$$

This is the definition of polarisation ( $C m^{-2}$ ), where N is the number of dipole moments per unit volume.

How we characterise bulk dialectric materials is a matter of taste:

1. Definition of relative dialectric constant,  $\epsilon_r$  (dimensionless)

$$P = \epsilon_0(\epsilon_r - 1)\mathcal{E} \tag{9.3}$$

2. Definition of electric susceptibility,  $\chi_e$  (dimensionless)

$$\underline{P} = \epsilon_0 \chi_e \mathcal{E} \tag{9.4}$$

<u>D</u> is a useful shorthand used in many calculations (no new Physics)

$$D = \epsilon_0 \mathcal{E} + P \tag{9.5}$$

This is the definition of  $\underline{D}$ , the electric displacement field

9.1.2 Current Density and Charge Density in Dielectrics

In an applied  $\underline{\mathcal{E}}$ -field, we can consider negative charges as displaced. The positive in the sheet at  $(x + \delta x, y, z)$  is:

$$Q_{+ve} = \underbrace{Nq}_{C/V} \underbrace{Sd}_{V \text{ of } +ve}$$

$$\tag{9.6}$$

which can be written in terms of surgave charge density,  $\sigma$ :

$$\sigma = \frac{Q_{+ve}}{S} = Nqd = \underline{P} \tag{9.7}$$

More generally, the surface charge density is:

$$\sigma = P \cdot \hat{n} \tag{9.8}$$

Consider a cube of non-uniform polarisation:

The negative charge that leaves the cube across the interface at x is given by:

$$Q_{out} = -P(x)\Delta y \Delta z \tag{9.9}$$

The negative charge that moves into the cube from the neighbouring cube is:


$$Q_{in}(x + \delta x) = -P(x + \delta x) \Delta y \Delta z \tag{9.10}$$

The net increase in (positive) charge in the cube is:

$$Q_{net} = -[P(x_{\delta}x) - P(x)] \Delta y \Delta z = -\frac{\partial P}{\partial x} \delta x \, \delta y \, \delta z \qquad (9.11)$$

Using similar logic for the y and z directions, the (bound) charge density is:

$$\rho = -\frac{\partial P_x}{\partial x} - \frac{\partial P_y}{\partial y} - \frac{\partial P_z}{\partial z} = -\underline{\nabla} \cdot \underline{P}$$
 (9.12)



$$\underbrace{\rho_b}_{\text{bound}} = -\underline{\nabla} \cdot \underline{P} \tag{10.1}$$

Consider an arbitrary volume of polarised material. If the polarisation changes as a function of time, the moving charges are equivalent to the current. The charge flowing out of the arbitrary volume is

$$\frac{\partial Q_{out}}{\partial t} = -\int \frac{\partial \rho_{in}}{\partial t} dV \tag{10.2}$$

$$= \frac{\partial}{\partial t} \int \underline{\nabla} \cdot \underline{P} \, dV = \frac{\partial}{\partial t} \int \underline{P} \cdot d\underline{S}$$
 (10.3)

$$= \frac{\partial}{\partial t} \int \underline{P} \cdot d\underline{S} - \int \underline{J}_b \cdot d\underline{S}, \ \underline{J}_b - \frac{\partial \underline{P}}{\partial t}$$
 (10.4)

Summary:

For a dielectric, once we have  $\underline{P}$ , we have

$$\sigma = \underline{P}\hat{n} = \epsilon_0(\epsilon_r - 1)\underline{\mathcal{E}} \cdot \hat{n} \tag{10.5}$$

$$\rho_b = -\nabla \cdot \underline{P} = -\epsilon_0 (\epsilon_r - 1) \nabla \cdot \underline{\mathcal{E}}$$
(10.6)

$$\underline{J}_b = \frac{\partial \underline{P}}{\partial t} = \epsilon_0 (\epsilon_r - 1) \frac{\partial \underline{\mathcal{E}}}{\partial t}$$
(10.7)

How are these results useful? MIII & IV:

$$\underline{\nabla} \times \underline{\mathcal{E}} = -\frac{\partial \underline{\mathcal{B}}}{\partial t} \tag{10.8}$$

$$\underline{\nabla} \times (\underline{\nabla} \times \underline{\mathcal{E}}) = -\frac{\partial}{\partial t} \underline{\nabla} \times \underline{\mathcal{B}}$$
(10.9)

$$\underline{\nabla} \times \underline{\mathcal{B}} = \mu_0 \underline{J} + \mu_0 \varepsilon_0 \frac{\partial \mathcal{E}}{\partial t} \tag{10.10}$$

$$= \mu_0 \left( \sigma_N \underline{\mathcal{E}} + \epsilon_0 (\epsilon_r - 1) \frac{\partial \underline{\mathcal{E}}}{\partial t} \right) + \mu_0 \epsilon_0 \frac{\partial \underline{\mathcal{E}}}{\partial t}$$
 (10.11)

Substituting and using the vector identity for  $\underline{\nabla} \times \underline{\nabla} \times \underline{\mathcal{E}} \Longrightarrow$ 

$$\underline{\nabla}^{2}\underline{\mathcal{E}} = \mu_{o}\sigma_{N}\frac{\partial\underline{\mathcal{E}}}{\partial t} + \mu_{0}\epsilon_{0}\epsilon_{r}\frac{\partial^{2}\underline{\mathcal{E}}}{\partial t^{2}}$$
(10.12)

This is the wave equation for a conducting dielectric.

#### 10.1 Magnetic Materials

#### **10.1.1** Microscopic Properties and Definitions

A magnetic material produces its own magnetic field.

Consider Ampere's model for a magnetic material:

- ➤ Each atom has electrons orbiting that produce a small magnetic field
- $\triangleright$  Applying a magnetic field tends to align the magnetic moments with the applied  $\underline{\mathcal{B}}$ -field

A quantum mechanical picture gives some similar ideas where we consider the occupation of quantum states with different magnetic properties.

$$m = IS\hat{n} \tag{10.13}$$

Note: m is the magnetic moment, be careful of getting confused with other ms in Physics.

The fundamental response of magnetic material:

$$m = IS\,\hat{n} \tag{10.14}$$

This is the definition of the magnetic dipole moment, where a current *I* flows around a loop of area *S*.

$$\underline{M} = N\underline{m} \tag{10.15}$$

This is the definition of magnetisation (M), where N is the number of dipoles per unit volume.

Note: H is a useful shorthand commonly used in calculations (no new Physics).

$$\underline{\mathcal{B}} = \mu_0(\underline{H} + \underline{M}) \tag{10.16}$$

This is the definition of  $\underline{H}$ , the magnetic field strength.

How we characterise bulk magnetic materials is a matter of taste:

1. Definition of susceptibility,  $\chi$ :

$$\underline{M} = \chi \underline{H} \tag{10.17}$$


2. Definition of permeability,  $\mu_r$ :

$$\underline{\mathcal{B}} = \mu_0 \mu_r \underline{H} \tag{10.18}$$

For a magnetised cylinder,

$$\underline{\mathcal{B}} = \underline{\mathcal{B}}_{\text{applied}} + \underbrace{\mu_0 \underline{M}}_{\text{material field}}$$
(10.19)

$$\implies \mu_0 \underline{H} = \underline{\mathcal{B}}_{\text{applied}}$$
 (10.20)



Consider the currents flowing:

$$m_z(x) = M_z(x) \Delta x \Delta y \Delta z \tag{10.21}$$

$$= I_1(x)S = I_1(x)\Delta x \Delta y \tag{10.22}$$

$$\implies I_1(x) = M_z(x) \Delta z \tag{10.23}$$

$$m_z(x) = M_z(x) \Delta x \Delta y \Delta z \tag{11.1}$$

$$= I_1(x)S = I_1(x)\Delta x \Delta y \tag{11.2}$$

$$\implies I_1(x) = M_z(x) \Delta z \tag{11.3}$$

The current flowing along the interface between the cubes ( $I_{net}$ ):

$$I_{net} = M_z \Delta z - [M_z(x + \Delta x) \Delta z] = -\Delta M_z \Delta z$$
(11.4)

$$= -\frac{\Delta M_z}{\Delta x} \Delta x \, \Delta z \tag{11.5}$$

$$\implies J_y = \frac{I_{net}}{\Delta x \, \Delta z} = -\frac{\Delta M_z}{\Delta x} \tag{11.6}$$

$$\implies J_y = -\frac{\partial M_z}{\partial x} \tag{11.7}$$

There is also a contribution to  $J_y$  if  $M_x$  varies given by:

$$J_{y} = \frac{\partial M_{x}}{\partial z} \tag{11.8}$$

Hence, in general,

$$\underline{J} = \underline{\nabla} \times \underline{M} \tag{11.9}$$

For a uniformly magnetised material, there is a discontinuous change in  $\underline{M}$  at the surface. The current through the rectangle can equally well be considered as a surface current per unit length or a bulk current density (I) where:

$$\int \underline{I} \cdot d\underline{S} = I_L L \tag{11.10}$$

$$J = \nabla \times \underline{M} \tag{11.11}$$

$$\underline{J} = \underline{\nabla} \times \underline{M}$$

$$\int \underline{J} \cdot d\underline{S} = \int (\underline{\nabla} \times \underline{M}) \cdot d\underline{S} = \int \underline{M} \cdot d\underline{l}$$
(11.11)
(11.12)

$$=ML=I_{L}L \tag{11.13}$$

$$\implies M = I_L \tag{11.14}$$

$$\implies \underline{I}_L = \underline{M} \times \hat{n} \tag{11.15}$$

Hence, if we know  $\underline{M}$ , we know the surface current per unit length,  $\underline{M} \times \hat{n}$ , and the bulk current density,  $\underline{\nabla} \times \underline{M}$ 

#### Propagation of Transverse EM Waves in Materials 11.1

#### General Dispersion Relation for an Infinite Linear Isotropic Homogeneous Medium

We can derive the general dispersion relation using Maxwell IV:

$$\underline{\nabla} \times \underline{\mathcal{B}} = \mu_0 \underline{J} + \mu_0 \epsilon_0 \frac{\partial \underline{\mathcal{E}}}{\partial t}$$
(11.16)

The total current density (for ILIH):

$$\underline{\underline{J}}_{\text{total}} = \underline{\underline{J}}_{\text{free}} + \underline{\underline{J}}_{\text{bound}} \tag{11.17}$$

$$\underline{J}_{\text{free}} = \underline{J}_{\text{Ohm}} + \underline{J}_{\text{experiment}} \tag{11.18}$$

$$\underline{J}_{\text{bound}} = \frac{\partial \underline{P}}{\partial t} + \underline{\nabla} \times \underline{M}$$
 (11.19)

Charge density  $(C m^{-3})$ : Insulating dielectrics give a surface charge density  $(\underline{P} \cdot \hat{n})$  and a volume charge density  $(-\nabla \cdot P)$ .

For a wave travelling through an ILIH medium, in general we can write:

$$\underline{\nabla} \cdot \underline{\mathcal{E}} = \frac{\rho_{\text{free}} + \rho_{\text{bound}}}{\epsilon_0} = \frac{\rho_{\text{free}}}{\epsilon_0} - (\epsilon_r - 1)\underline{\nabla} \cdot \underline{\mathcal{E}}$$
(11.20)

$$\Longrightarrow \underline{\nabla} \cdot \underline{\mathcal{E}} = \frac{\rho_{\text{free}}}{\epsilon_r \epsilon_0} = 0 \tag{11.21}$$

This condition holds as long as the frequency of the wave is sufficiently low that the charge density associated with the conducting medium is zero.

Maxwell IV can be written as

$$\underline{\nabla} \times \underline{\mathcal{B}} = \mu_0 \underbrace{\left(\sigma_N \underline{\mathcal{E}} + \frac{\partial \underline{P}}{\partial t} + \underline{\nabla} \times \underline{M}\right)}_{\underline{I}_{\text{total}}} + \mu_0 \epsilon_0 \frac{\partial \underline{\mathcal{E}}}{\partial t}$$
(11.22)

This can be rearranged:

$$\underline{\nabla} \times (\underline{\mathcal{B}} - \mu_0 \underline{M}) = \mu_0 \sigma_N \underline{\mathcal{E}} + \mu_0 \frac{\partial}{\partial t} (\underline{P} + \epsilon_0 \underline{\mathcal{E}})$$
(11.23)

Using the materials' definitions:

$$\underline{P} = \epsilon_0(\epsilon_r - 1)\underline{\mathcal{E}} \tag{11.24}$$

$$\underline{\mathcal{B}} = \mu_0(\underline{H} + \underline{M}) = \mu_0 \mu_r \underline{H} \tag{11.25}$$

Maxwell IV can be rewritten as

$$\underline{\nabla} \times \frac{\underline{\mathcal{B}}}{\mu_r} = \mu_0 \sigma_N \underline{\mathcal{E}} + \mu_0 \frac{\partial}{\partial t} (\epsilon_0 \epsilon_r \underline{\mathcal{E}})$$
(11.26)

Now substitute this into the curl of Maxwell III to find:

$$\underline{\nabla} \times (\underline{\nabla} \times \underline{\mathcal{E}}) = -\frac{\partial}{\partial t} (\underline{\nabla} \times \underline{\mathcal{B}}) = -\frac{\partial}{\partial t} \left[ \mu_0 \mu_r \left( \sigma_N \underline{\mathcal{E}} + \epsilon_0 \epsilon_r \frac{\partial \underline{\mathcal{E}}}{\partial t} \right) \right]$$
(11.27)

Using  $\underline{\nabla} \times \underline{\nabla} \times \underline{\mathcal{E}} = \underline{\nabla} (\underline{\nabla} \cdot \underline{\mathcal{E}}) - \underline{\nabla}^2 \underline{\mathcal{E}}$ :

$$\underline{\nabla}^{2}\underline{\mathcal{E}} - \mu_{0}\mu_{r}\sigma_{N}\frac{\partial\underline{\mathcal{E}}}{\partial t} - \mu_{0}\mu_{r}\epsilon_{0}\epsilon_{r}\frac{\partial^{2}\underline{\mathcal{E}}}{\partial t^{2}} = 0$$
(11.28)

 $\blacktriangleright \mu_0 \mu_r \rightarrow \mu$   $\blacktriangleright \epsilon_0 \epsilon_r to \epsilon$ 

$$\underline{\nabla}^{2}\underline{\mathcal{E}} - \mu\sigma_{N}\frac{\partial\underline{\mathcal{E}}}{\partial t} - \mu\varepsilon\frac{\partial^{2}\underline{\mathcal{E}}}{\partial t^{2}} = 0$$
(12.1)

Equally taking the curl of MIV gives:

$$\underline{\nabla}^2 \underline{\mathcal{B}} - \mu \sigma_N \frac{\partial \underline{\mathcal{B}}}{\partial t} - \mu \epsilon \frac{\partial^2 \underline{\mathcal{B}}}{\partial t^2} = 0$$
 (12.2)

We can substitute a plane wave solution into the wave equation:

$$\mathcal{E} = \mathcal{E}_0 \exp(i[kx - wt]) \tag{12.3}$$

$$\implies -k^2 = iw\mu\sigma_N + \mu\epsilon w^2 = 0 \tag{12.4}$$

$$\implies k^2 = \mu \epsilon w^2 + i w \mu \sigma_N \tag{12.5}$$

This is the general dispersion relation for an infinite, linear, isotropic, homogeneous medium.

#### Example: Electromagnetic Waves in Conducting/Dielectric/Magnetic Materials

Use the general dispersion relation to calculate the approximate decay length, wave-vector, and wavelength of a wave of frequency  $10^{15}Hz$  propagating through Tungsten ( $\rho_N = 1\,m\Omega\,cm$ ). Tungsten is neither magnetic nor a dielectric.

Given  $f = 10^{15} Hz$ ,  $\rho_N \approx 10^{-5} \Omega m$ ,  $\sigma_N = 10^5 \Omega^{-1} m^{-1}$ ,  $\mu = \mu_0$ ,  $\epsilon = \epsilon_0$ :

$$k^{2} = 4\pi \times 10^{-7} \cdot 8.85 \times 10^{-12} \cdot (2\pi \times 10^{15})^{2} + i(2\pi \times 10^{15}) \cdot 4\pi \times 10^{-7} \times 10^{5}$$
(12.6)

$$=4.4\times10^{14}+i7.9\times10^{14}\tag{12.7}$$

Note: Tungsten cannot be considered either as a good insulator or as a good conductor Use an argand diagram and find the magnitude of k:

$$\tan \phi = \frac{7.9}{4.4} \implies \phi = 60.8^{\circ} \implies \frac{\phi}{2} = 30.4^{\circ}$$
 (12.8)

$$|k| = \left| (4.4 \times 10^{1} 4)^{2} + (7.9 \times 10^{14})^{2} \right|^{1/4} = 3.0 \times 10^{7}$$
(12.9)

$$k = |k|\cos\frac{\phi}{2} + i|k|\sin\frac{\phi}{2} \tag{12.10}$$

$$= 2.59 \times 10^7 + i \, 1.52 \times 10^7 \tag{12.11}$$

$$\underline{\mathcal{E}} = \mathcal{E}_0 \exp(i[(2.59 \times 10^7 + i \, 1.52 \times 10^7)x - wt]) \tag{12.12}$$

$$= \mathcal{E}_0 \exp(i[2.59 \times 10^7 x - wt]) \exp(-1.52 \times 10^7 x)$$
(12.13)

Taking either the real or imaginary parts gives:

$$\underline{\mathcal{E}} = \mathcal{E}_0 \cos(2.59 \times 10^7 - wt) \exp(-1.52 \times 10^7 x) \tag{12.14}$$

The wave-vector is the real part of k,  $2.59 \times 10^7 m^{-1}$  and wavelength,  $\lambda = \frac{2\pi}{k_{real}} = 2.4 \times 10^{-7} m$ . The decay length is the distance for  $\underline{\mathcal{E}}$  to decrease by  $\frac{1}{e} \implies \delta = \frac{1}{k_{imag}} = 66 \, nm$ 

# 12.1 Advanced Microscopic Descriptions of Normal Conductors, Superconductors, and Dielectrics

#### 12.1.1 Conducting Materials - Metal and Plasma

We use a stable one-dimensional, scalar, Drude model to describe the scattering of charge carriers. In the Drude model, the charge carriers accelerate for an average time,  $\tau$ . They then scatter and instantaneously stop. The fraction of charge carriers that scatter in a time  $\delta t$  is  $\frac{\delta t}{\tau}$ , and the remaining fraction that don't scatter is  $\left(1 - \frac{\delta t}{\tau}\right)$ . Hence, the momentum of the charge carriers at time  $t + \delta t$  is given by:

$$p(t+\delta t) = \left(1 - \frac{\delta t}{\tau}\right)p(t) + \left(1 - \frac{\delta t}{\tau}\right)f(t)\,\delta t + f(t)\delta t\frac{\delta t}{\tau} \tag{12.15}$$

Three terms:

- 1. Initial momentum at time t of the charge are not scattered
- 2. Increase in momentum during the time interval of  $\delta t$  of the unscattered carriers
- 3. An upper bound for the momentum of the carriers scattered at some point in time during  $\delta t$

$$\delta p = p(t + \delta t) - p(t) \tag{12.16}$$

$$\frac{\delta p}{\delta t} = -\frac{p(t)}{\tau} + f(t) + O(\delta t) \tag{12.17}$$

The general expression for the force on a charge carrier:

$$\underline{F} = m \frac{dp}{dt} = q(\underline{\mathcal{E}} + \underline{v} \times \underline{\mathcal{B}})$$
 (12.18)

In an electromagnetic wave,  $\underline{\mathcal{B}} \approx \frac{|\mathcal{E}|}{c}$ , so  $\underline{v} \times \underline{\mathcal{B}} \ll \underline{\mathcal{E}}$  unless the charge carriers are moving close to the speed of light. Hence, we neglect the  $\underline{v} \times \underline{\mathcal{B}}$  term in the expression for the Lorentz force. Using F = qE and p = mv:

$$m\frac{dv}{dt} = qE - \frac{mv}{\tau}$$
 (Equation of Motion)

where  $\frac{mv}{\tau}$  can be considered as a frictional damping term

Using  $\underline{I} = N q \underline{v}$ , where N is the number of charges per unit volume, q is the charge on each carrier, and  $\underline{v}$  is the velocity of the carriers, can rewrite as

$$m\frac{dJ}{dt} = Nq^2E - \frac{m}{\tau}J\tag{13.1}$$

We assume complex oscillating solutions of the form:

$$\underline{\mathcal{E}} = \underline{\mathcal{E}}_0 \exp(-i\omega t), \ \underline{J} = \underline{J}_0 \exp(-i(\omega t - \delta))$$
(13.2)

where  $\delta$  is the phase shift between  $\underline{\mathcal{E}}$  and J. The differential equation of motion gives

$$\underline{J} = \frac{Nq^2}{m(\tau^{-1} - i\omega)}\underline{\mathcal{E}} \tag{13.3}$$

Comaparing this expression to the definition for conductivity:  $J = \sigma_N \mathcal{E}$ , gives a complex conductivity:

$$\sigma_N = \frac{Nq^2}{m(\tau^{-1} - i\omega)} \tag{13.4}$$

Metals (short scattering time): In the short scattering time limit ( $\tau \ll \omega^{-1}$ ), we find the Drude expression:

$$\sigma_N = \frac{Nq^2\tau}{m} \tag{13.5}$$

➤ Plasma (long scattering time- low density plasma)

A low density plasma is a net neutral system of charged particle (ions and electrons) in which the density of the charged carriers is sufficiently small that the charged carriers don't often collide Examples:

- Ionised gas in fluorescent lights;
- ⇒ the ionosphere which is a region 100 km to 600 km above the Earth's surface, which is ionised by the radiation from the sun;
- the plasma in a fusion energy tokamak;

Usually, we ignore the response of ions because they are much slower than the electrons to react. In the long scattering time limit:

$$\sigma_N = \frac{-Nq^2}{m_e i\omega} = +\frac{iNq^2}{m_e\omega} \tag{13.6}$$

Using the dispersion relation

$$k^2 = \mu \epsilon \omega^2 + i\omega \mu \sigma_N \tag{13.7}$$

Since the plasma is not contained in a magnetic or dielectric medium so  $\epsilon_r = 1$  and  $\mu_r = 1$ . Hence,

$$k^2 = \mu_0 \epsilon_0 \omega^2 + i\omega \mu_0 \frac{iNe^2}{m_e \omega} = \mu_0 \epsilon_0 \omega^2 - \frac{\mu_0 N e^2}{m_e}$$
(13.8)


$$=\frac{\omega^2}{c^2}\left(1-\left(\frac{\omega_p}{\omega}\right)^2\right), \ \omega_p=\sqrt{\frac{Ne^2}{m_e\epsilon_0}}$$
(13.9)

The dispersion relation has two regimes:

1.  $\omega > \omega_p$ : k is real and the electromagnetic waves propagate without attentuation through the plasma

$$v_{phase} = \frac{c}{\sqrt{1 - \left(\frac{\omega_p}{\omega}\right)^2}} > c \tag{13.10}$$

2.  $\omega < \omega_p$ : k is imaginary and there is an attenuated propagation of the electromagnetic wave



#### 13.1 Superconducting Materials

#### Applications:

- ➤ MRI body scanners;
- ➤ Particle accelerators;
- ➤ fusion energy tokamaks;
- ➤ voltage standards;
- ➤ in the future, power transmission

There is no simple model for zero resistivity in superconductivity. We can think about superconductors as the condensation of the normal electrons of a metal into a ground state. The ground state has an associated energy. The superelectrons are not scattered (i.e. zero resistivity). We can think of a superconductor as being like an enormous atom with a (macroscopic) wavefunction that can be kilometres long.

#### 14.1 The material properties and definitions for superconductors

The two London equations describe superconductors in low magnetic fields. They are motivated by the two fundamental properties:

1. Zero resistivity:

If we assume there is no scattering of the charge carriers, we have:

$$m\underline{a} = m\frac{d\underline{v}}{dt} \tag{14.1}$$

Using  $\underline{F} = q\underline{\mathcal{E}}$  amd  $J = Nq\underline{v}$ , we find the first London equation:

$$\underline{\mathcal{E}} = \mu_0 \lambda_L^2 \frac{\partial \underline{J}}{\partial t} \tag{14.2}$$

where the London penetration depth,  $\lambda_L = \sqrt{\frac{m_e}{\mu_0 N_s e^2}}$ ,  $N_s$  is the denisty of superelectrons

2. The Meissner state - exclusion of magnetic flux The second London equation is given by

$$\underline{\mathcal{B}} = -\mu_0 \lambda_L^2 \underline{\nabla} \times J \tag{14.3}$$

Substituting Maxwell IV for  $\underline{\underline{J}}$ , where  $\frac{\partial \underline{\mathcal{E}}}{\partial t} = 0$ , into the second London equation gives

$$\underline{\mathcal{B}} = -\lambda_L^2 \underline{\nabla} \times \underline{\nabla} \times \underline{\mathcal{B}} \tag{14.4}$$

$$\implies \underline{\nabla} \times \underline{\nabla} \times \underline{\mathcal{B}} = \underline{\nabla}(\underline{\nabla} \cdot \underline{\mathcal{B}}) - \underline{\nabla}^2 \underline{\mathcal{B}}$$
 (14.5)

$$\Longrightarrow \underline{\nabla}^2 \underline{\mathcal{B}} = \frac{1}{\lambda_I^2} \underline{\mathcal{B}} \tag{14.6}$$

$$\implies \mathcal{B}(x) = \mathcal{B}_0 \exp\left(\frac{-x}{\lambda_L}\right)$$
 (14.7)

for a semi-infinite slab.

Zero resistance implies that low energy EM waves cannot travel through the bulk of superconductors. Microscopically, superelectrons are paired, so very high energy photons can pass through the superconductor if the photon energy is high enough to destroy the superconductivity.

#### 14.2 Dielectrics

To describe how the bound charges in a dielectric behave as a function of time, we add a restoring force  $(-m\omega_0^2x)$  associated with simple harmonic vibrations to the equation of motion used for conductors. This gives:


$$m\frac{d\underline{v}}{dt} = q\underline{\mathcal{E}} - \frac{m\underline{v}}{\tau} - m\omega_0^2 x \tag{14.8}$$

In the standard description for dielectrics, the negative charges in the dielectric are fixed in space and the positive charges respond to any applied  $\underline{\mathcal{E}}$ -field. The variable x represents the displacement between the positive and negative charges and v represents the velocity of the positive charges. Using  $\tilde{x} = x_0 e^{-i\omega t}$ , which  $\tilde{v} = \frac{d\tilde{x}}{dt} = -i\omega\tilde{x}$ , and  $\frac{d\tilde{v}}{dt} = -\omega^2\tilde{x}$  (the tilde denotes complex variables). The complex equation of motion for the bound but moving charges is the linearised:

$$-\omega^2 \tilde{x} m = q \tilde{\mathcal{E}} + \frac{i\omega \tilde{x}}{\tau} - m\omega_0^2 \tilde{x}$$
 (14.9)

$$\implies m\left(\omega_0^2 - \omega^2 - \frac{i\omega}{\tau}\right)\tilde{x} = q\tilde{\mathcal{E}} \tag{14.10}$$

Using Euler's equation, we can rearrange this complex equation to give:



$$\frac{\tilde{x}}{\tilde{\mathcal{E}}} = \frac{qe^{i\theta}}{m\sqrt{(\omega_0^2 - \omega^2) + \left(\frac{\omega}{\tau}\right)^2}}$$
(14.11)

$$\tan \theta = \frac{\omega}{\tau(\omega_0^2 - \omega^2)} \tag{14.12}$$

$$\tan \theta = \frac{\omega}{\tau(\omega_0^2 - \omega^2)}$$

$$\cos \theta = \frac{\omega^2 - \omega_0^2}{\sqrt{(\omega^2 - \omega_0^2)^2 + (\frac{\omega}{\tau})^2}}$$

$$\sin \theta = \frac{\omega}{\tau\sqrt{(\omega^2 - \omega_0^2) + (\frac{\omega}{\tau})^2}}$$
(14.12)
$$(14.13)$$

$$\sin \theta = \frac{\omega}{\tau \sqrt{(\omega^2 - \omega_0^2) + \left(\frac{\omega}{\tau}\right)^2}}$$
(14.14)


Writing the definition of  $\underline{P}$  (polarisation), and  $\epsilon_r$  (permittivity) in complex form:

$$\underline{\tilde{P}} = (\epsilon_r - 1)\epsilon_0 \underline{\tilde{\mathcal{E}}} = Nq\tilde{x}$$
(14.15)

Using  $e^{i\theta} = \cos \theta + i \sin \theta$ , the real and imaginary parts of the relative permittivity are:

$$\epsilon_{real} = 1 + \frac{Nq^2}{m\epsilon_0} \left( \frac{\omega_0^2 - \omega^2}{(\omega_0^2 - \omega^2)^2 + \left(\frac{\omega}{\tau}\right)^2} \right)$$
(14.16)

$$\epsilon_{im} = -\frac{Nq^2}{m\epsilon_0 \tau} \frac{\omega}{(\omega_0^2 - \omega^2) + \left(\frac{\omega}{\tau}\right)^2}$$
 (14.17)



#### 15.1 Auxiliary Fields and the Poynting vector

#### 15.1.1 Electric Displacement Field

$$\underline{D} = \epsilon_0 \mathcal{E} + \underline{P} \tag{15.1}$$

Rewriting this in differential form:

$$\underline{\nabla} \cdot \underline{D} = \underline{\nabla} \cdot (\epsilon_0 \underline{\mathcal{E}} + \underline{P}) = \rho_{total} - \rho_{dielectric} = \rho_{free}$$
(15.2)

So we can rewrite Maxwell I in terms of  $\underline{D}$  and  $\rho_{free}$ :

$$\underline{\nabla} \cdot \underline{D} = \rho_{free} \tag{15.3}$$

In general, we tend to use the relative permittivity to characterise a dielectric. However, we can use  $\underline{P}$  or  $\underline{D} = \epsilon_0 \underline{\mathcal{E}} + \underline{P} = \epsilon_r \epsilon_0 \underline{\mathcal{E}}$  if it simplifies calculations.

#### 15.1.2 Magnetic Field Strength

$$\underline{\mathcal{B}} = \mu_0(\underline{H} + \underline{M}) \tag{15.4}$$

Maxwell IV is

$$\underline{\nabla} \times \underline{\mathcal{B}} = \mu_0 \underline{J} + \mu_0 \epsilon_0 \frac{\partial \underline{\mathcal{E}}}{\partial t}$$
 (15.5)

The current density produced by conducting, magnetic, and dielectric materials is given by

$$\underline{J} = \underline{J}_{free} + \frac{\partial \underline{P}}{\partial t} + \underline{\nabla} \times \underline{M}$$
 (15.6)

which can be rearranged as

$$\underline{\nabla} \times (\underline{\mathcal{B}} - \mu_0 \underline{M}) = \mu_0 \underline{J}_{free} + \mu_0 \frac{\partial}{\partial t} (\underline{P} + \epsilon_0 \underline{\mathcal{E}})$$
(15.7)

So we can rewrite Maxwell IV as:

$$\underline{\nabla} \times \underline{H} = \underline{J}_{free} + \frac{\partial \underline{D}}{\partial t}$$
 (15.8)

Again, we tend to use  $\mu_{\tau}$  to characterise a magnetic material, however we can use  $\underline{H}$  or  $\underline{M}$  if it simplifies calculations.

$$\underline{\nabla} \cdot \underline{D} = \rho_{free} \tag{MI}$$

$$\underline{\nabla} \cdot \underline{\mathcal{B}} = 0 \tag{MII}$$

$$\underline{\nabla} \times \underline{\mathcal{E}} = -\frac{\partial \underline{\mathcal{B}}}{\partial t} \tag{MIII}$$

$$\underline{\nabla} \times \underline{H} = \underline{J}_{free} + \frac{\partial \underline{D}}{\partial t}$$
 (MIV)

#### 15.2 The Poynting Vector

The direction of propagation for an electromagnetic waves is  $\underline{\mathcal{E}} \times \underline{H}$ . Poynting suggested that the instantaneous power per unit area for electromagnetic waves is given by  $\underline{N}$  where:

$$N = \mathcal{E} \times H \tag{15.9}$$

#### 15.2.1 General Proof

If  $\underline{N}$  is the instantaneous power per unit area associated with electromagnetic fields, then the total energy per unit time radiating out of an arbitrary volume ( $P_{rad}$ ) is

$$P_{rad} = \int \underline{N} \cdot d\underline{S} = \int (\underline{\mathcal{E}} \times \underline{H}) \cdot d\underline{S}$$
 (15.10)

Using the divergence theorem:

$$P_{rad} = \int \underline{\nabla} \cdot \underline{N} \, dV = \int \underline{\nabla} \cdot (\underline{\mathcal{E}} \times \underline{H}) \, dV \tag{15.11}$$

Use the vector identity

$$\nabla \cdot (\mathcal{E} \times H) = H \cdot (\nabla \times \mathcal{E}) - \mathcal{E} \cdot (\nabla \times H) \tag{15.12}$$

Hence, we have

$$P_{rad} = \int \underline{H} \cdot (\underline{\nabla} \times \underline{\mathcal{E}}) \, dV - \int \underline{\mathcal{E}} \cdot (\underline{\nabla} \times \underline{H}) \, dV \tag{15.13}$$

From Maxwell's equations

$$\underline{\nabla} \times \underline{\mathcal{E}} = -\frac{\partial \underline{\mathcal{B}}}{\partial t} = -\mu_0 \mu_r \frac{\partial \underline{H}}{\partial t} \tag{15.14}$$

$$\underline{\nabla} \times \underline{H} = \underline{J}_{free} + \frac{\partial \underline{D}}{\partial t} = \underline{J}_{free} + \epsilon_r \epsilon_0 \frac{\partial \mathcal{E}}{\partial t}$$
(15.15)

$$P_{rad} = \int \underline{H} \cdot \mu_r \mu_0 \frac{\partial \underline{H}}{\partial t} dV - \int \underline{\mathcal{E}} \cdot \left( \underline{I}_{free} + \epsilon_0 \epsilon_r \frac{\partial \underline{\mathcal{E}}}{\partial t} \right) dV$$
 (15.16)

$$= -\frac{\partial}{\partial t} \int \left( \frac{1}{2} \mu_r \mu_0 H^2(t) + \frac{1}{2} \epsilon_0 \epsilon_r E^2(t) \right) dV - \int \underline{\mathcal{E}} \cdot \underline{I} dV$$
 (15.17)

$$\Rightarrow P_{rad} + \int \underbrace{\mathcal{E} \cdot \underline{I} dV}_{\text{Power dissipated as Joule heat}} = -\frac{\partial}{\partial t} \int \underbrace{\left(\frac{1}{2}\mu_r \mu_0 H^2(t) + \frac{1}{2}\epsilon_0 \epsilon_r E^2(t)\right) dV}_{\text{Energy stored per unit volume in the magnetic and electric fields}}$$
 (15.18)

The interpretation of the equation for  $P_{rad}$  is:

- ➤ The reduction in the potential energy stored in the electric and magnetic fields per unit time is equal to the net flow of power out through the surface plus the power dissipated as heat within the volume.
- The deivation is a self-consistent statement of the conservation of energy, so  $\underline{N}$  correctly represents the instantaneous power per unit area.

#### 16.1 Radiation and Communication

#### 16.1.1 Maxwell's equations rewritten using potentials

For time-independent problems, we use

$$\mathcal{E} = -\nabla V \tag{16.1}$$

where V is the electrostatic potential.

In general, the potential, V, is defined by:

$$\underline{\mathcal{E}} = -\underline{\nabla}V - \frac{\partial \underline{A}}{\partial t} \tag{16.2}$$

Similarly, the magnetic vector potential is defined by:

$$\underline{\mathcal{B}} = \underline{\nabla} \times \underline{A} \tag{16.3}$$

Consider Maxwell II:

$$\underline{\nabla} \cdot \underline{\mathcal{B}} = 0 : \underline{\nabla} \cdot (\underline{\nabla} \times \underline{A}) = 0 \tag{16.4}$$

Now consider Maxwell III:

$$\underline{\nabla} \times \underline{\mathcal{E}} = \underline{\nabla} \times \left( -\underline{\nabla} V - \frac{\partial \underline{A}}{\partial t} \right) = -\underline{\nabla} \times \underline{\nabla} V - \frac{\partial}{\partial t} \underline{\nabla} \times \underline{A} = -\frac{\partial \underline{\mathcal{B}}}{\partial t}$$
(16.5)

Hence, if we rewrite  $\underline{\mathcal{B}}$  and  $\underline{\mathcal{E}}$  in terms of  $\underline{A}$  and V, Maxwell II and III are automatically solved. Maxwell's four equations are thus reduced to just two equations:

$$-\underline{\nabla} \cdot \underline{\nabla} V - \frac{\partial}{\partial t} \underline{\nabla} \cdot \underline{A} = \frac{\rho}{\epsilon_0} \tag{MI}$$

$$\underline{\nabla} \times \underline{\nabla} \times \underline{A} = \mu_0 \underline{I} + \mu_0 \epsilon_0 \frac{\partial}{\partial t} \left( -\underline{\nabla} V - \frac{\partial \underline{A}}{\partial t} \right)$$
(MIV)

The potentials  $\underline{A}$  and V are not uniquely specified. We can add to the vector field  $\underline{A}$  any function whose curl is zero, and add to V any function whose gradient is zero. Hence it is often useful to impose the Lorentz condition,

$$\underline{\nabla} \cdot \underline{A} = -\mu_0 \epsilon_0 \frac{\partial V}{\partial t} \tag{16.6}$$

Maxwell I becomes the wave equation for V:

$$-\nabla^2 V + \mu_0 \epsilon_0 \frac{\partial^2 V}{\partial t^2} = \frac{\rho}{\epsilon_0} \tag{16.7}$$

and Maxwell IV becomes the wave equation for A:

$$-\nabla^2 \underline{A} + \mu_0 \epsilon_0 \frac{\partial^2 \underline{A}}{\partial t} = \mu_0 \underline{J}$$
 (16.8)

#### 16.1.2 Hertzian dipoles/oscillating electric dipoles

#### A Hertzian dipole:

➤ A length of wire in which a time-dependent alternating current is flowing (equivalent to an alternating electric dipole)

We can start to solve the wave equation for A by considering (static) solutions for

$$-\nabla^2 \underline{A} = \mu_0 \underline{J} \tag{16.9}$$

From electrostatics, using  $\underline{\mathcal{E}} = -\nabla V$ , we know the solution for  $\underline{\nabla} \cdot \underline{\mathcal{E}} = -\nabla \cdot \nabla V = -\nabla^2 V = \frac{\rho}{\epsilon_0}$  is  $V = \frac{Q}{4\pi\epsilon_0 r}$ , where  $Q = \int \rho \, dV$ .

By inspection, the static solution for  $\underline{A}$  is:

$$\underline{A} = \frac{\mu_0 I \, d\underline{l}}{4\pi}, \, I \, d\underline{l} = \int \underline{I} \cdot dV \tag{16.10}$$

Recognising that if we set  $\underline{J}$  to be zero, we find oscillating solutions. The general solution to the wave equation for  $\underline{A}$  is:

$$\underline{A} = \frac{\mu_0 I \, d\underline{l}}{4\pi} e^{i(kr - \omega t)} \tag{16.11}$$

In spherical polar coordinates,  $d\underline{l} = \cos\theta \hat{r} - \sin\theta \hat{\theta}$ . Using  $\underline{\mathcal{B}} - \underline{\nabla} \times \underline{A}$ , we have:

$$\underline{\mathcal{B}} = \frac{\mu_0 I}{4\pi} (1 - ikr) \sin \theta e^{i(kr - \omega t)} \hat{\phi}$$
(16.12)

We find physical solutions by taking the real parts of  $\underline{\mathcal{B}}$ . There is a 'near-field' term that dominates close to the dipole and a 'far-field' term that describes the radiation distant from the dipole:

$$\underline{\mathcal{B}}_{near} = \frac{\mu_0 I}{4\pi r^2} \sin\theta \cos(kr - \omega t)\hat{\phi}$$
 (16.13)

$$\underline{\mathcal{B}}_{far} = \frac{\mu_0 I}{4\pi r} k \sin \theta \sin(kr - \omega t) \hat{\phi}$$
 (16.14)

- ➤ The near-field part originates from the quasi-static field produced by the moving charges.
- ➤ The far-field comes from changing current, associated with the acceleration of the charges, and cause the radiation

Writing down Maxwell IV for the regions where there is no charge or current, we have  $\nabla \times \underline{\mathcal{B}} = \mu_0 \underline{J} + \mu_0 \varepsilon_0 \frac{\partial \mathcal{E}}{\partial t}$  which leads to:

$$\underline{\mathcal{E}} = \frac{i}{\mu_0 \epsilon_0 \omega} \underline{\nabla} \times \underline{\mathcal{B}} \tag{16.15}$$

$$= \frac{\mu_0 I}{2\pi} \frac{(i+kr)\cos\theta}{k^2 r^3} e^{i(kr-\omega t)} \hat{r} + \frac{\mu_0 I}{4\pi} \frac{(i+kriik^2 r^2)\sin\theta}{k^2 r^3} e^{i(kr-\omega t)} \hat{\theta}$$
 (16.16)


$$\underline{\mathcal{E}}_{near} = -\frac{\mu_0 I}{2\pi r^2} \frac{\omega}{k^2} \cos\theta \sin(kr - \omega t)\hat{r} - \frac{\mu_0 I}{4\pi r^3} \frac{v}{k^2} \sin\theta \sin(kr - \omega t)\hat{\theta}$$
(16.17)

$$\underline{\mathcal{E}}_{far} = -\frac{\mu_0 I}{4\pi r} \omega \sin \theta \sin(kr - \omega t) \hat{\theta}$$
 (16.18)

### Some notes:


- $\triangleright$   $\underline{\mathcal{B}}_{near}$  and  $\underline{\mathcal{E}}_{near}$  are  $\frac{\pi}{2}$  out of phase with each other because the current reaches a maximum as the charges cross each other at maximum velocity.
- ➤ The electric field reaches a maximum when the electric dipole is at a maximum and the charges have a maximum separation.
- ► In constrast,  $\underline{\mathcal{B}}_{far}$  and  $\underline{\mathcal{E}}_{far}$  are in phase with each other distant from the Hertzian dipole, we have plane waves.  $\underline{\mathcal{E}}$  is vertically polarised when  $\theta = \frac{\pi}{2}$ , and  $\underline{\mathcal{B}}$  is horizontally polarised.

### 17.1 Production of a wave



The production of the first half of a wave in snapshots:

- 1. The charges separate and there are  $\mathcal{E}$ -fields close to the charges.
- 2. V-shaped chevrons and the dotted lines show the electric field lines. For any snapshot in time, the charges behave like an extended dipole with both near- and far-field terms contributing to the  $\mathcal{E}$ -field.
- 3. The first half wave separates and radiates from the dipole. The solid lines are contours. The  $\underline{\mathcal{E}}$ -field points in the positive  $\theta$  direction through the first half wave.



- ➤ The solid lines are contours.
- ➤ Each magnetic field line is a circle with a dipole along the axis.
- ► The cross product  $\underline{\mathcal{E}} \times \underline{\mathcal{B}}$  gives the direction of propagation.

## 17.2 The angular dependence of the power radiated by a Hertzian dipole

We know that the instantaneous power radiated per unit area in any direction is

$$\underline{N} = \underline{\mathcal{E}} \times \underline{H} \tag{17.1}$$

The angular dependence of the time-averaged power unit area is:

$$\underline{N}_{t-av} = |\underline{\mathcal{E}} \times \underline{H}|_{t-av} = \frac{1}{2} \frac{\mu_0 c I_0^2 (\delta l)^2 \sin^2 \theta}{4r^2 \lambda^2} \hat{r}$$
(17.2)

This is from the far-field limit for  $\underline{\mathcal{B}}_{far}$  and  $\underline{\mathcal{E}}_{far}$ .  $\sin^2 > 0$  so the time average is  $\frac{1}{2}$  from  $1 = \cos^2 x + \sin^2 x$  when time-averaged.

The power peaks in the equitorial plane  $(\theta = \frac{\pi}{2})$ . No power is radiated along the axis of the dipole  $(\theta = 0, \pi)$ .

### 18.1 The total time-averaged power radiated by a Hertzian dipole

$$P_{total} = \frac{1}{2} \int \int \frac{1}{2} \frac{\mu_0 c I_0^2 (\delta l)^2 \sin^2 \theta}{4r^2 \lambda^2} r^2 \sin \theta \, d\theta \, d\phi \tag{18.1}$$


$$= \frac{\mu_0 c I_0^2 (\delta l)^2}{8\lambda^2} \int_0^{\pi} \sin^3 \theta \, d\theta \int_0^{2\pi} d\phi$$
 (18.2)

$$=\frac{\mu_0 c \pi}{3} \left(\frac{\delta l}{\lambda}\right) I_0^2 \tag{18.3}$$

#### 18.2 Electromagnetic fields and wave crossing interfaces

Pauli: "God made the bulk, but the devil has the surfaces."

#### 18.2.1 Boundary conditions across the interfacial plane between two dielectrics



Two charged capacitor plates immersed in two dielectrics. The magnitude and direction of the dc electric field changes as it passes from one dielectric to another. (N.b. This is not a ray dispersion.)

1. From an insulating material, consider the cylinder and Maxwell I:

$$\nabla \cdot \underline{D} = \rho_{free} = 0 \tag{18.4}$$

$$\underline{\nabla} \cdot \underline{D} = \rho_{free} = 0$$

$$\lim_{h \to 0} \int \underline{D}_1 \cdot d\underline{S} = \int \underline{D}_2 \cdot d\underline{S}$$
(18.4)

$$\implies D_{1\perp} = D_{2\perp} \tag{18.6}$$

$$\implies \epsilon_1 \mathcal{E}_{1\perp} = \epsilon_2 \mathcal{E}_{2\perp} \tag{18.7}$$

2. Using Maxwell III (consider the path drawn):

$$\underline{\nabla} \times \underline{\mathcal{E}} = -\frac{\partial \underline{\mathcal{B}}}{\partial t} \tag{18.8}$$

$$\int \underline{\mathcal{E}} \cdot d\underline{l} = -\frac{\partial}{\partial t} \int \underline{\mathcal{B}} \cdot d\underline{S}$$
 (18.9)

$$\underline{\nabla} \times \underline{\mathcal{E}} = -\frac{\partial \underline{\mathcal{B}}}{\partial t} \qquad (18.8)$$


$$\int \underline{\mathcal{E}} \cdot d\underline{l} = -\frac{\partial}{\partial t} \int \underline{\mathcal{B}} \cdot d\underline{S} \qquad (18.9)$$

$$\lim_{h \to 0} (\mathcal{E}_{1||} \int -\mathcal{E}_{2||} \int) = -\frac{\partial \phi}{\partial t} = 0 \qquad (18.10)$$

$$\Longrightarrow \mathcal{E}_{1||} = \mathcal{E}_{2||} \qquad (18.11)$$

$$\Longrightarrow \mathcal{E}_{1\parallel} = \mathcal{E}_{2\parallel} \tag{18.11}$$

## Boundary conditions across the interfacial plane between two magnetic materials



Maxwell II:

$$\int \underline{\mathcal{B}} \cdot d\underline{S} = 0 \implies \mathcal{B}_{1\perp} = \mathcal{B}_{2\perp}$$
 (19.1)

Maxwell IV:

$$\underline{\nabla} \times \underline{\mathcal{B}} = \mu_0 \underline{J} + \mu_0 \varepsilon_0 \frac{\partial \mathcal{E}}{\partial t}$$
 (19.2)

$$\underline{\nabla} \times \underline{H} = \underline{J}_{free} + \frac{\partial \underline{D}}{\partial t}$$
(19.3)

$$\underline{\nabla} \times \underline{H} = \underline{J}_{free} + \frac{\partial \underline{D}}{\partial t}$$


$$\int \underline{H} \cdot d\underline{l} = \int \underline{J}_{free} \cdot d\underline{S} + \frac{p}{\partial t} \int \underline{\nabla} \cdot \underline{D} \, dV$$
(19.3)

RHS equal to zero:

- > no free current density
- > no free charge density

$$\implies H_{1\parallel} = H_{2\parallel} \tag{19.5}$$

## 19.2 The laws of geometrical optics




An electromagnetic wave incident on an interface - it is partially reflected and partially transmitted. Let's make no assumptions about the polarisation of the reflected and transmitted wave:

$$\underline{\mathcal{E}}_{i}(\underline{r},t) = \underline{\mathcal{E}}_{0i} \exp[i(\underline{k}_{i} \cdot \underline{r} - \omega_{i}t)]$$
(19.6)

$$\underline{\mathcal{E}}_r(\underline{r},t) = \underline{\mathcal{E}}_{0r} \exp[i(\underline{k}_r \cdot \underline{r} - \omega_r t)] \tag{19.7}$$

$$\underline{\mathcal{E}}_{t}(\underline{r},t) = \underline{\mathcal{E}}_{0t} \exp[i(\underline{k}_{t} \cdot \underline{r} - \omega_{t}t)]$$
(19.8)

The  $\underline{\mathcal{E}}_0$  and  $\underline{k}$  terms are constants, not variables.  $\underline{k}$  can in principle be complex, to incorporate phase information and decay.



Across the interfacial plane, the geneal condition for the continuity of  $\mathcal{E}_{\parallel}$  (i.e.  $\mathcal{E}$  parallel to the interfacial plane) requires:

$$\mathcal{E}_{i\parallel}(\underline{r},t) + \mathcal{E}_{r\parallel} = \mathcal{E}_{t\parallel}(\underline{r},t) \tag{19.9}$$

for all  $\underline{r}$  in the interfacial plane at all t.

For simplicity, we assume the origin of the coordinate system is in the interfacial plane and consider special cases:

1. r = 0:

$$\mathcal{E}_{0i\parallel}e^{-i\omega_i t} + \mathcal{E}_{0r\parallel}e^{-i\omega_r t} = \mathcal{E}_{0t\parallel}e^{-\omega_t t}$$
(19.10)

$$\mathcal{E}_{0i\parallel}\cos(\omega_i t) + \mathcal{E}_{0r\parallel}\cos(\omega_r t) = \mathcal{E}_{0t\parallel}\cos(\omega_t t)$$
(19.11)

where  $\mathcal{E}_{0i\parallel}$ ,  $\mathcal{E}_{0r\parallel}$ ,  $\mathcal{E}_{0t\parallel}$  are all constants


An argand diagram showing these arbitrary complex vectors where at t = 1,  $r_1 e^{i\theta_1 t} + r_2 e^{i\theta_2 t} = r_3 e^{i\theta_3 t}$ . Also shown are the three complex vectors at a later time where the magnitude of the vectors has remained constant but the phase of each complex vector has doubled (i.e. t = 2).

► LHS - At the later time the vector addition identity is still valid because  $\theta_1 = \theta_2 = \theta + 3$  and remains true at all times.

RHS - At the later t=2, the vector addition identity is no longer true. Hence, given the vector equality must be true at all times, the phases of each complex wave must be the same, so:

$$\omega_i = \omega_r = \omega_t \tag{19.12}$$

(i.e. the indicent, transmitted, and reflected waves all have the same angular frequency)



2. 
$$t = 0$$
:

$$\mathcal{E}_{0i\parallel}e^{i(\underline{k}_i\cdot\underline{r})} + \mathcal{E}_{0r\parallel}e^{i(\underline{k}_r\cdot\underline{r})} = \mathcal{E}_{0t\parallel}e^{i(\underline{k}_t\cdot\underline{r})}$$
(19.13)

The condition is true for all  $\underline{r}$  in the plane.

$$\implies \underline{k}_i \cdot \underline{r} = \underline{k}_r \cdot \underline{r} = \underline{k}_t \cdot \underline{r} \tag{19.14}$$

Consider reflection (i.e.  $(\underline{k}_i - \underline{k}_r) \cdot \underline{r} = 0$ )  $\Longrightarrow \underline{k}_i - \underline{k}_r$  is normal to the interface. Then:

$$\underline{k}_{i||} = \underline{k}_{r||} \tag{19.15}$$

Since the phase velocities are the same for the incident and reflected waves:

$$|\underline{k}_r| = |\underline{k}_r| \tag{19.16}$$

$$\implies \theta_i = \theta_r$$
 (19.17)

The first law of geometrical optics: the angle of reflection = the angle of incidence.

Consider transmission (i.e.  $\underline{k}_r \cdot \underline{r} = \underline{k}_t \cdot \underline{r}$ ):

$$(\underline{k}_i - \underline{k}_t) \cdot \underline{r} = 0 \tag{19.18}$$

$$\underline{k}_{i\parallel} = \underline{k}_{t\parallel} \tag{19.19}$$

$$k_t \sin \theta_t = k_t \sin \theta_t \tag{19.20}$$

Using the definition of the refractive index,  $n_i = \frac{c}{v_{phase}} = \frac{ck_i}{\omega}$ ,  $n_t = \frac{ck_t}{\omega}$ :

$$\frac{n_i}{n_t} = \frac{k_i}{k_t} = \frac{\sin \theta_t}{\sin \theta_i}$$
 (Snell's Law)

Snell's Law is the second law of geometrical optics.

Snells Law is valid for all polarisations. Since we can also write down

$$\underline{k}_r \cdot \underline{r} = \underline{k}_t \cdot \underline{r} \tag{20.1}$$

$$\underline{k}_r \cdot \underline{r} = \underline{k}_t \cdot \underline{r}$$

$$(\underline{k}_r - \underline{k}_t) \cdot \underline{r} = 0$$
(20.1)

$$\underline{k}_r \sin \theta_r = \underline{k}_t \sin \theta_t \tag{20.3}$$


The constraints on the components of the incident, reflected, and transmitted wavevectors parallel to the interfacial plane and the constraints on the magnitude of the wavevectors in both media lead to the third law of geometrical optics:

"The incident, reflected, and transmitted waves are all in the plane of incidence."

#### 20.1 Fresnel's Equations

## **20.1.1** Perpendicular Equations

 $\mathcal{E}$ -field normal to the plane of incidence.



Assume  $\mathcal{E}$  doesn't change direction broadly in transmission and relection - use  $\underline{\mathcal{E}} \times \underline{H} \Longrightarrow \underline{k}$ 

An electromagnetic wave close to the interfacial plane incident to an interfacial plane where  ${\mathcal E}$  is normal to the plane of incidence. The incident and reflective waves superimpose in medium 1, only the transmitted wave is in medium 2.

We use the convention that the direction of the  $\mathcal{E}$ -field of the reflected and transmitted waves are broadly similar to the incident wave. The continuity of  $\mathcal{E}$  parallel to the interfacial plane requires

$$\mathcal{E}_{0i} + \mathcal{E}_{0r} = \mathcal{E}_{0t} \tag{20.4}$$

The continuity of  $\underline{H}$  parallel to the interfacial:

$$H_{0i}\cos\theta_i - H_{0r}\cos\theta_r = H_{0t}\cos\theta_t \tag{20.5}$$

We know that  $\theta_i = \theta_r$  and  $\omega$  is constant. Using  $\underline{\nabla} \times \underline{\mathcal{E}} = -\frac{\partial \underline{\mathcal{B}}}{\partial t} \implies \underline{k} \times \underline{\mathcal{E}} = \omega \underline{\mathcal{B}}$ :

$$\underline{\mathcal{B}} = \frac{\underline{\mathcal{E}}}{v_{phase}} \tag{20.6}$$

The refractive index, n, by definition is:

$$n = \frac{c}{v_{phase}} = \sqrt{\epsilon_r \mu_r} \tag{20.7}$$

Using  $\underline{\mathcal{B}} = \mu_0 \mu_r \underline{H} = \mu \underline{H}$ 

$$\underline{H} = \frac{n\underline{\mathcal{E}}}{c\mu} \tag{20.8}$$

Substituting Eq. 20.7 into Ep. 20.5, and assuming the media are non-magnetic (i.e.  $\mu = \mu_0$ ):

$$(n_i \mathcal{E}_{0i} - n_r \mathcal{E}_{0r}) \cos \theta_i = n_t \mathcal{E}_{0t} \cos \theta_t \tag{20.9}$$

Then combining Eq. 20.4 and Eq. 20.8 to eliminate  $\mathcal{E}_{0t}$  and  $\mathcal{E}_{0r}$  in turn, we obtain:


$$\frac{\mathcal{E}_{0r}}{\mathcal{E}_{0i}} = \frac{n_i \cos \theta_i - n_t \cos \theta_t}{n_i \cos \theta_i + n_t \cos \theta_t} \tag{20.10}$$

$$\frac{\mathcal{E}_{0r}}{\mathcal{E}_{0i}} = \frac{n_i \cos \theta_i - n_t \cos \theta_t}{n_i \cos \theta_i + n_t \cos \theta_t}$$

$$\frac{\mathcal{E}_{0t}}{\mathcal{E}_{0i}} = \frac{2n_i \cos \theta_i}{n_i \cos \theta_i + n_t \cos \theta_t}$$
(20.10)

These are Fresnel's two equations for  $\underline{\mathcal{E}}$  normal to the plane of incidence.

## 20.1.2 Parallel Equations



The continuity equations for  $H_{\parallel}$  and  $\mathcal{E}_{\parallel}$  are now:

$$(\mathcal{E}_{0i} + \mathcal{E}_{0r})\cos\theta_i = \mathcal{E}_{0t}\cos\theta_t \tag{20.12}$$

H is parallel to interfacial plane so,

$$H_{0i} - H_{0r} = H_{0t} (20.13)$$

$$n_i(\mathcal{E}_{0i} + \mathcal{E}_{0r}) = n_t \mathcal{E}_{0t} \tag{20.14}$$


So we find:

$$\frac{\mathcal{E}_{0r}}{\mathcal{E}_{0i}} = \frac{n_i \cos \theta_t - n_t \cos \theta_i}{n_i \cos \theta_t + n_t \cos \theta_i} \tag{20.15}$$

$$\frac{\mathcal{E}_{0r}}{\mathcal{E}_{0i}} = \frac{n_i \cos \theta_t - n_t \cos \theta_i}{n_i \cos \theta_t + n_t \cos \theta_i}$$

$$\frac{\mathcal{E}_{0t}}{\mathcal{E}_{0i}} = \frac{2n_i \cos \theta_i}{n_i \cos \theta_t + n_t \cos \theta_t}$$
(20.15)

These are Fresnel's equations for  $\underline{\mathcal{E}}$  parallel to the plane of incidence.



## 20.2 Coefficient of reflection and transmission

We can also consider reflection and transmission coefficients that are consistent with conservation of energy using the Poynting vector,  $\underline{N} = \underline{\mathcal{E}} \times \underline{H}$  (instantaneous power per unit area).

For dielectrics (non-magnetic, non-conducting):

$$\underline{\mathcal{B}} = \frac{\mathcal{E}}{v_{phase}} \implies v_{phase} = \sqrt{\frac{1}{\epsilon_r \epsilon_0 \mu_0}}$$
 (20.17)

The average power per unit time per unit area incident on the interface (perpendicular to the direction of travel),  $N_i$ :

$$N_i = \frac{1}{2} \left( \frac{\epsilon_r}{\mu_0} \right)^{\frac{1}{2}} \mathcal{E}_{0i}^2 \cos \theta_i \tag{20.18}$$

## 21.1 Coefficients of relection and transmission

Incident:

$$\underline{N} = \underline{\mathcal{E}} \times \underline{H} \tag{21.1}$$

$$N_i = \frac{1}{2} \left( \frac{\epsilon_r}{\mu_0} \right)^{\frac{1}{2}} \mathcal{E}_{0r}^2 \cos \theta_i \tag{21.2}$$

This is for the reflected wave, where  $\cos \theta$  is using the angle between  $\underline{k}$  and  $\hat{n}$  to the interfacial plane:

$$N_r = \frac{1}{2} \left( \frac{\epsilon_1}{\mu_0} \right)^{\frac{1}{2}} \mathcal{E}_{0r}^2 \cos \theta_r \tag{21.3}$$

For the transmitted wave:

$$N_t = \frac{1}{2} \left( \frac{\epsilon_2}{\mu_0} \right)^{\frac{1}{2}} \mathcal{E}_{0t}^2 \cos \theta_t \tag{21.4}$$

$$R = \frac{N_r}{N_i} = \left(\frac{\mathcal{E}_{0r}}{\mathcal{E}_{0i}}\right)^2 \tag{21.5}$$

and the transmission coefficient is defined as:


$$T = \frac{N_t}{N_i} = \left(\frac{\epsilon_2}{\epsilon_1}\right)^{\frac{1}{2}} \frac{\mathcal{E}_{0t}^2}{\mathcal{E}_{0i}^2} \frac{\cos \theta_t}{\cos \theta_i} = \frac{n_2}{n_1} \frac{\mathcal{E}_{0t}^2}{\mathcal{E}_{0i}^2} \frac{\cos \theta_t}{\cos \theta_i}$$
(21.6)

Using Fresnel's equations in either polarisation gives:

$$R + T = 1 \tag{21.7}$$

## 21.2 Wave guides

## 21.2.1 Waves propagating in a hollow rectangular waveguide



A hollow waveguide carrying a transverse electric wave. Transverse electromagnetic waves cannot exist inside a hollow waveguide.

Maxwell's equations give:

$$\nabla^2 \underline{\mathcal{E}} = \mu_0 \epsilon_0 \frac{\partial^2 \underline{\mathcal{E}}}{\partial t^2} \tag{21.8}$$

for propagation in the z-direction, we can first consider transverse  $\mathcal{E}$ -field (i.e. the  $\mathcal{E}$ -field perpendicular of propagation) and for simplicity take the  $\mathcal{E}$ -field to be in the y-direction only.

$$\underline{\mathcal{E}}(\underline{r},t) = \hat{j}E_{0v}\exp[i(kz - \omega t)]\sin(k_x x) \tag{21.9}$$

The solution meets the requirement that the component on  $\mathcal{E}$  parallel to the internal boundaries of the waveguide must be zero, else it generate currents which decays the  $\mathcal{E}$ -field so we need  $\mathcal{E}=0$  at boundaries for steady state.

For steady state solutions, the constraint on the component of  $\mathcal{E}$ -field parallel to the internal surface being zero requires

$$k_x a = m\pi, \ m \in \mathcal{Z} \tag{21.10}$$

The solution must satisfy the wave equation:

$$k^2 + k_x^2 = \frac{\omega^2}{c^2} \tag{21.11}$$

$$\implies k^2 = \frac{\omega^2}{c^2} - \frac{m^2 \pi^2}{a^2} \tag{21.12}$$

This is the dispersion relation for EM waves in a waveguide.

 $k^2 > 0$  for steady state, if k is complex, leads to decay.

Similar tp a plasma, we have a cut off for angular frequency (where k = 0) given by

$$\omega_c = \frac{\pi c}{a} \tag{21.13}$$


We can identify two regions:

- 1.  $\omega > \omega_c$  k is real, wave can propagate without attentuation
- 2.  $\omega < \omega_c$  k is imaginary, there is an attenuated solution

### 21.2.2 Phase velocity

$$v_{phase} = \frac{\omega}{k} = \frac{c}{\sqrt{1 - \left(\frac{\omega_c}{\omega}\right)^2}} > c, \text{ for } \omega > \omega_c$$
 (21.14)

$$v_{group} = \frac{\partial \omega}{\partial k} = c\sqrt{1 - \left(\frac{\omega_c}{\omega}\right)^2} < c \text{ for } \omega > \omega_c$$
 (21.15)



For the propagating wave, Maxwell III:

$$\underline{\nabla} \times \underline{\mathcal{E}} = -\frac{\partial \underline{\mathcal{B}}}{\partial t} \tag{21.16}$$

$$\underline{\nabla} \times \underline{\mathcal{E}} = \begin{vmatrix} \hat{i} & \hat{j} & \hat{k} \\ \frac{\partial}{\partial x} & \frac{\partial}{\partial y} & \frac{\partial}{\partial z} \\ \mathcal{E}_{x} \to 0 & \mathcal{E}_{y} & \mathcal{E}_{z} \to 0 \end{vmatrix} = -\hat{i} \frac{\partial \mathcal{E}_{y}}{\partial z} + \hat{k} \frac{\partial E_{y}}{\partial x} \tag{21.17}$$

$$= -ik\mathcal{E}_{0y}\exp[i(kz - \omega t)]\sin(k_x x)\hat{i} + k_x\mathcal{E}_{0y}\exp[i(kz - \omega t)]\cos(k_x x)\hat{k}$$
 (21.18)

Maxwell III gives

$$\underline{\mathcal{B}} = \frac{1}{i\omega} \underline{\nabla} \times \underline{\mathcal{E}} \tag{21.19}$$

$$\underline{\mathcal{B}} = -\frac{\mathcal{E}_{0y}}{c} \sqrt{1 - \left(\frac{\omega_c}{\omega}\right)^2} \exp[i(kz - \omega t)] \sin(k_x x) \hat{i} - \frac{i\omega_c}{c\omega} \mathcal{E}_{0y} \exp[i(kz - \omega t)] \cos(k_x x) \hat{k}$$
(21.20)

 $\mathcal{B}$ -field has components parallel and perpendicular to k.

The first component is a transverse one, the second is longitudinal.

A transverse electric wave (TE) has an  $\mathcal{E}$ -field that is only transverse, but it has a  $\mathcal{B}$ -field that has components that are both transverse and parallel (longitudinal) to the direction of propagation.

A transverse magnetic wave has a  $\mathcal{B}$ -field that is transverse to the direction of propagation but an  $\mathcal{E}$ -field that has both transverse and longitudinal components.