Nevatch Server 1.5.3 on Docker

Runs the same server as the Windows launcher: Xray (VLESS + Reality), the web console, and the update service that hands out new versions of Nevatch.exe. Works on any Linux machine or NAS with Docker (x64 or arm64).

Start

1. Unzip this package on the Docker machine and open a terminal in the folder.
2. `cp .env.example .env` and fill it in:
   - `VPN_PORT`: the port your friends connect to (443 unless it's taken).
   - `PUBLIC_HOST`: your public IP, or better a dynamic DNS name (e.g. `myname.duckdns.org`), since home IPs change.
   - `ADMIN_PASSWORD`: the console password.
3. `docker compose up -d --build`
4. **Router:** forward TCP `VPN_PORT` to this machine's local IP. Do **not** forward the console port (8088).
5. Open the console at `http://<this-machine>:8088`, log in, and add people.

Adding a friend

In the console, *People* → type a name → **Add**. Then click **Copy key**. It gives a `vless://…` link (it holds your address, the port and their personal ID). Send them that key and `Nevatch-<version>.exe` from the Releases page. They paste the key in Nevatch with **Add key**, or in a phone app such as Hiddify, v2rayNG or Streisand.

Each person gets their own key, so you can disable or remove one person without affecting the others.

Things to mind on Docker

- **The port is fixed by `VPN_PORT`.** It's published with the same number on both sides because it also goes into every key; the console's port field is locked. Changing it means every key changes: send fresh downloads, or have people paste their new key with *Add key*.
- **Moving from the Windows server?** Copy its `server/data/state.json` into `./data/` here *before* the first start. It holds the server keys and people; without it everyone needs a new key.
- **Back up `./data`.** Same reason.
- **Speed limit per person** counts per internet address. On Linux, Docker keeps your friends' real addresses. Docker Desktop (Windows/Mac) shows them all as one address, so they'd share one limit there.
- **The lag card's "router" ping** measures Docker's internal gateway, not your real router, so it stays low even when your Wi-Fi is busy. The internet ping and each person's numbers are accurate.
- **The server log** is capped at 3 files of 10 MB (see `logging` in `docker-compose.yml`).
- **Console from outside your home:** don't. Use a VPN into your home network, or set `CONSOLE_BIND=127.0.0.1` and an SSH tunnel.

Updating

Unzip the new package over this folder (`.env` and `data/` stay), then `docker compose up -d --build`. Everyone's Nevatch updates itself to the Nevatch.exe inside the package the next time it connects, or within 6 hours while it stays connected.

Useful commands: `docker compose logs -f` (server log), `docker compose restart`, `docker compose down`.