



**ORDER
7110.2B**

Effective Date:
March 19, 2026

SUBJ: BOI ATCT/TRACON Standard Operating Procedures

This document establishes the Boise Airport Traffic Control Tower (BOI ATCT) and Big Sky Terminal Radar Approach Control (BOI TRACON) Standard Operating Procedures within the Salt Lake City ARTCC on VATSIM (vZLC). Controllers are required to be familiar with the provisions of this document and to exercise their best judgment if they encounter situations not covered by it. The provisions and procedures described herein are supplemental to vZLC Facility Policies and FAA Order JO 7110.65.

The information contained herein is to be used for flight simulation purposes only on the VATSIM network. It is not intended, nor should it be used for real-world navigation. The Virtual Salt Lake City ARTCC is not affiliated with the FAA, the actual Salt Lake City ARTCC, or any governing aviation body.

Cameron Negrete
Air Traffic Manager
Salt Lake City ARTCC

Adam Earl
Facilities Engineer
Salt Lake City ARTCC

Record of Changes

[illegible]

Table of Contents

Chapter 1. General Control	1
Section 1. Introduction	1
1-1-1. Purpose	1
1-1-2. Audience	1
1-1-3. Distribution	1
1-1-4. Cancellation	1
Section 2. Operational Positions	2
Section 3. Coordination and Intrafacility Procedures	3
1-3-1. BOI Runway Configurations	3
1-3-2. BOI Automatic Departure Releases	3
1-3-3. BOI Departure Instructions	3
1-3-4. Vectoring IFR Departures (DVA)	3
1-3-5. Vectors Below the MVA	4
1-3-6. BOI Missed Approach/Go-Around Procedures	4
1-3-7. BOI Visual Separation	5
1-3-8. BOI Practice Approaches (Planned Missed Approaches)	5
1-3-9. BOI Automated Point-Outs	5
Section 4. Pre-Arranged Coordination Procedures (PACP)	6
1-4-1. General	6
1-4-2. Application	6
Section 5. Opposite Direction Operations (ODO)	7
1-5-1. General	7
1-5-2. Responsibilities	7
1-5-3. IFR Aircraft Procedures	7
1-5-4. VFR Aircraft Procedures	8
Chapter 2. Tower Operational Positions	9
Section 1. Clearance Delivery (CD)	9
2-1-1. Position Responsibilities	9
2-1-2. IFR Departure Routing	9
2-1-3. IFR Departure Altitudes	10
2-1-4. Use of Pre-Departure Clearances (PDCs)	10
2-1-5. Reroute Procedures	10
2-1-6. Compliance with TMIs	10
2-1-7. VFR Departure Instructions	11
Section 2. Ground Control (GC)	12
2-2-1. Position Responsibilities	12
2-2-2. Area of Jurisdiction	12
2-2-3. Traffic Flow	12
2-2-4. ATIS	12
2-2-5. Multiple Runway Crossings	12

2-2-6. Pushback Clearances	12
2-2-7. Use Of SAID System	12
Section 3. Local Control (LC)	13
2-3-1. Position Responsibilities	13
2-3-2. Area of Jurisdiction	13
2-3-3. Use of Radar	13
2-3-4. Departure Procedures	13
2-3-5. Arrival Procedures	14
2-3-6. Landing Clearance	14
2-3-7. Multiple Runway Crossings	14
Chapter 3. TRACON Operational Positions	15
Section 1. General Control	15
3-1-1. Facility Identification	15
3-1-2. Scratchpad Use	15
3-1-3. Altitude Filter Limits	15
Section 2. Alpine Radar	16
3-2-1. Position Responsibilities	16
3-2-2. LC Coordination	16
3-2-3. Procedures	16
Section 3. Sage Radar	17
3-3-1. Position Responsibilities	17
3-3-2. Procedures	17
Section 4. Bozeman Radar	19
3-4-1. Position Responsibilities	19
3-4-2. Procedures	19
Appendix 1. Airspace	20
Appendix 1A. BOI Local Control Airspace	20
Appendix 1B. Sage/Alpine Radar (East Flow)	21
Appendix 1C. Sage/Alpine Radar (West Flow)	22
Appendix 1D. Bozeman Radar	23
Appendix 2. Pre-Arranged Coordination Areas	24
Appendix 2A. East Flow	24
Appendix 2B. West Flow	25
Appendix 3. Arrival Zones	26
Appendix 3A. East Flow	26
Appendix 3B. West Flow	27

Chapter 1. General Control

Section 1. Introduction

1-1-1. Purpose

This document establishes the Boise Airport Traffic Control Tower (BOI ATCT) and Big Sky Terminal Radar Approach Control (BOI TRACON) Standard Operating Procedures within the Salt Lake City ARTCC on VATSIM (vZLC).

1-1-2. Audience

All vZLC controllers and visitors contained within the vZLC and VATUSA roster.

1-1-3. Distribution

This document is authorized for unrestricted use and release and is available in the Resources Section of the vZLC Website.

1-1-4. Cancellation

This document cancels 7110.2A, dated November 1, 2024.

Section 2. Operational Positions

Table 1-2-1. BOI ATCT Operational Positions Table

Sector/Position	STARS ID	VATSIM Callsign	Frequency
Clearance Delivery (CD)	H	BOI_DEL	125.900
Ground Control (GC)	R	BOI_GND	121.700
Local Control (LC)	T	BOI_TWR	118.100
Sage Radar (SAG)	G	BOI_G_APP	119.600
Alpine Radar (ALP)	A	BOI_A_APP	126.900
Bozeman Radar (APB)	B	BZN_APP	118.975

Bold designates a primary position.

Section 3. Coordination and Intrafacility Procedures

1-3-1. BOI Runway Configurations

- a. The active runway configuration refers to the general cardinal direction of departures and arrivals currently in use. Authorized runway configurations are listed in subparagraphs e. and f.
- b. When selecting a Runway Flow, the following factors must be considered:
 - (1) Wind direction.
 - (2) Wind speed. The gust factor takes precedence over the constant wind speed.
- c. When changing runway flows, the following items must be accomplished:
 - (1) The radar position(s) must coordinate with ZLC ARTCC, in accordance with the BOI-ZLC LOA.
 - (2) All operational positions must be verbally advised of:
 - (a) Impending runway configuration changes.
 - (b) The callsign of the last departure and arrival in the old configuration.
 - (3) Ensure the ATIS broadcast is updated.
- d. East Flow is designated as the “calm wind” runway configuration.
- e. East Flow: Landing and departing Runway 10L and Runway 10R.
- f. West Flow: Landing and departing Runway 28L and Runway 28R.

1-3-2. BOI Automatic Departure Releases

- a. BOI Local Control has automatic release for all departures.
- b. Sage/Alpine has control on contact for all departures.

1-3-3. BOI Departure Instructions

- a. IFR departures must be issued the following:
 - (1) Runway heading.
 - (2) An initial altitude of 16,000 feet, or lower filed altitude.

NOTE-

IFR departures must be assigned a minimum of 8,000 feet.

- b. Departures requesting VFR-on-top must not be restricted above 16,000 feet.

1-3-4. Vectoring IFR Departures (DVA)

- a. DVAs are only authorized for IFR departures.
- b. DVAs must not be utilized when a SID or ODP has been assigned, or when issuing missed approach/go-around instructions.
- c. The following DVAs, listed in Table 1-3-1 and 1-3-2, are authorized:

Table 1-3-1. BOI Diverse Vector Area

Runway(s)	Headings	Distance from BOI
10L and 10R	089° clockwise to 270°	20nm
28L and 28R	150° clockwise to 330°	20nm

Table 1-3-2. BZN Diverse Vector Area

Runway(s)	Headings	Distance from BZN
12	245° clockwise to 302°	18nm
30	215° clockwise to 298°	18nm

1-3-5. Vectors Below the MVA

Air traffic is responsible for terrain and obstruction avoidance when vectoring an aircraft that is not on a published procedure below the MVA/MIA. This is primarily performed for aircraft conducting a go-around/missed approach. The following provisions must be complied with when vectoring aircraft below the MVA:

- a. BOI:
 - (1) Runway 10L/10R: Vectors below the MVA are not authorized.
 - (2) Runway 28L/28R: Headings between 200° clockwise to 330° are authorized in accordance with FAA JO 7110.65 paragraph 5-6-3. STARS Map 13 must be depicted when vectoring below the MVA.
- b. BZN:
 - (1) Runway 12: Headings between 245° clockwise to 302° are authorized.
 - (2) Runway 30: Headings between 215° clockwise to 298° are authorized.

1-3-6. BOI Missed Approach/Go-Around Procedures

IFR aircraft executing an unplanned missed approach/go-around must comply with the following procedures:

- a. IFR aircraft that are not on a visual approach must be instructed to fly the published missed approach procedure and to maintain 8,000 feet.
- b. IFR aircraft that are on a visual approach can be issued either of the following:
 - (1) Instruct the pilot to fly runway heading and maintain 8,000 feet.

NOTE-

A heading between 200° clockwise to 330° may be given to aircraft on a visual approach to Runway 28L/R. This heading must only be assigned after the aircraft has crossed the runway threshold.

- (2) Instruct the pilot to join the local traffic pattern, in accordance with FAA JO 7110.65, paragraph 7-4-1.

1-3-7. BOI Visual Separation

- a. When Sage or Alpine is using pilot-applied visual separation on arrival traffic, "VS" must be placed in Scratchpad 2 of the aircraft's full data block, unless otherwise coordinated.
- b. When Local Control is using pilot-applied visual separation on successive departures, verbal coordination must be accomplished.

1-3-8. BOI Practice Approaches (Planned Missed Approaches)

- a. The following climb out instructions must be issued to aircraft requesting multiple approaches in Sage or Alpine airspace:
 - (1) IFR: Alpine is responsible for issuing the following climb out instruction:

PHRASEOLOGY-

"Climb out instructions: fly the published missed approach, maintain eight thousand."

- (2) VFR: Local Control is responsible for issuing instructions. Local Control may issue any heading in accordance with Table 2-3-1 or Table 2-3-2, depending on the runway flow.
- b. Alpine must ensure the appropriate practice approach information is entered into the data block, in accordance with the ZLC Scratchpad Directive (7210.4).
- c. Alpine must handoff the aircraft to Local Control, regardless of the aircraft's flight rules.
- d. Local Control must handoff the aircraft to the appropriate sector following the missed approach.

1-3-9. BOI Automated Point-Outs

The STARS automated point-out function may be used to point-out traffic between Local Control and/or Sage/Alpine under the following conditions:

- a. The transferring controller must enter the destination or direction of flight in the scratchpad area of the STARS data block prior to initiating the automated point-out.
- b. The receiving controller must accept the point-out using automation to indicate no altitude or speed restrictions are imposed, or verbally coordinate altitude/speed/route restrictions prior to accepting the point-out.

Section 4. Pre-Arranged Coordination Procedures (PACP)

1-4-1. General

Pre-arranged coordination refers to the procedure where one controller may penetrate another controller's airspace without coordination, on the basis that the penetrating aircraft is operating on a pre-determined track/route, which enables the controller applying PACP to determine whether or not appropriate separation can be applied between the penetrating aircraft and other traffic. When applying PACP, the following procedures must be complied with:

- a. Two positions of operation cannot be authorized to penetrate each other's airspace simultaneously.
- b. Any penetration of another controller's airspace that is not designated as a pre-arranged coordination area (see Appendix 2) is prohibited, unless otherwise coordinated.
- c. The following must be considered prior to applying PACP. If any of the following situations exist, PACP should not be used:
 - (1) Complexity and volume of traffic in the pre-arranged airspace.
 - (2) Weather or other conditions that may disrupt the normal flow of traffic.
 - (3) Whether or not the use of PACP will disrupt or adversely affect the normal flow of traffic for the other sector.
- d. PACP may be terminated at any time by the controller responsible for the pre-arranged airspace and must not be resumed until additional coordination has been accomplished.
- e. The controller using PACP in another controller's airspace must:
 - (1) Continuously display data block information for all traffic in that sector's airspace, which must contain, at a minimum, the position symbol and altitude information.
 - (2) Assume separation responsibility for, and avoid, all traffic under the jurisdiction of the controller responsible for the pre-arranged airspace.

1-4-2. Application

- a. Sage departure aircraft may depart Local Control airspace through the areas depicted in Appendix 2.
- b. Alpine has control to turn VFR departures to the north. Any deviation from the Local Control assigned heading to the south must be coordinated with Sage.
- c. Arrival aircraft sequenced by Sage/Alpine to BOI airport must be routed through the arrival zones, as depicted in Appendix 3.

Section 5. Opposite Direction Operations (ODO)

1-5-1. General

Opposite Direction Operations consists of IFR/VFR operations conducted to the same or parallel runway where an aircraft is operating in a reciprocal direction of another aircraft arriving, departing, or conducting an approach.

1-5-2. Responsibilities

- a. Local Control and Sage/Alpine share the responsibility to coordinate ODO and issue traffic advisories (see below).
- b. Local Control is responsible for cutoff point compliance for opposite direction arriving and departing aircraft. STARS Map 710 (ODO Cutoff Points) must be displayed.
- c. Sage/Alpine is responsible for cutoff point compliance for opposite direction arrival/arrival aircraft. STARS Map 710 (ODO Cutoff Points) must be displayed.

1-5-3. IFR Aircraft Procedures

a. General:

- (1) Traffic advisories must be issued to both aircraft conducting ODO.

PHRASEOLOGY-

OPPOSITE DIRECTION TRAFFIC (distance) MILE FINAL, (type aircraft).

OPPOSITE DIRECTION TRAFFIC DEPARTING RUNWAY (number), (type aircraft).

OPPOSITE DIRECTION TRAFFIC (position), (type aircraft).

- (2) Opposite direction, same or parallel runway, operations with opposing traffic inside the cutoff point are prohibited.
- (3) Visual separation is not authorized during ODO.
- (4) Aircraft conducting RNAV Z approaches must be cleared from OFTER or JIMMI for ODO to be authorized.

b. Coordination:

- (1) Local Control must verbally request opposite direction departures with Sage/Alpine and include aircraft callsign, aircraft type, runway, and the phrase "opposite direction."
- (2) Sage/Alpine must verbally request opposite direction arrivals with Local Control and include aircraft callsign, aircraft type, runway, and the phrase "opposite direction."

c. Cutoff procedures for aircraft conducting ODO:

- (1) A departing aircraft, including an aircraft performing a touch-and-go, stop-and-go, go-around, low approach, or missed approach, must be airborne and have commenced a turn to avoid conflict prior to an aircraft reaching:
 - (a) A point 10 flying miles from the threshold of the runway of intended landing, or;
 - (b) The base leg turn for an aircraft established in the traffic pattern.

- (2) An arriving aircraft must cross the runway threshold prior to an aircraft reaching:
 - (a) A point 15 flying miles from the threshold of the runway of intended landing, or;
 - (b) The base leg turn for an aircraft established in the traffic pattern.
- (3) If the above conditions are not met, action must be taken to ensure control instructions are issued to protect the integrity of the cutoff points.

NOTE-

Flying miles are defined as the distance an aircraft is expected to fly (via pilot navigation) or required to fly (via control instructions) to reach the landing threshold of the runway of intended landing.

1-5-4. VFR Aircraft Procedures

- a. Ensure VFR aircraft are issued a turn to avoid conflict with the opposing IFR/VFR traffic.
- b. During coordination, the phrase “opposite direction” must be used.
- c. Traffic information must be issued to both aircraft, including the direction that the departure will turn (as appropriate) and/or the location of the opposing aircraft on final (as appropriate).

Chapter 2. Tower Operational Positions

Section 1. Clearance Delivery (CD)

2-1-1. Position Responsibilities

- Monitor the CD frequency (125.900 MHz).
- Prepare and update flight progress strips in accordance with the ZLC Flight Strip Handling Directive (7210.3).
- Issue departure clearances to IFR aircraft, complying with posted traffic management initiatives (TMIs), letters of agreement (LOAs), and published preferred routes.
- Issue departure clearances to VFR aircraft in accordance with paragraph 2-1-7.
- Create VFR flight plans for departing VFR aircraft.
- Assume other clearance delivery or other cab responsibilities, as assigned.

2-1-2. IFR Departure Routing

- All aircraft must be instructed to fly runway heading and expect radar vectors to their first fix. For aircraft that will leave the Big Sky TRACON, the first fix must be in accordance with subparagraph b. Write "RH" into Box 9 of the aircraft's flight progress strip when given.
- All aircraft that will leave the Big Sky TRACON must be routed via one of the departure fixes listed in Table 2-1-1. Aircraft that are unable to be routed via a departure fix must be routed through a departure corridor or coordinated with ZLC ARTCC. Departure corridors are depicted and described in the BOI-ZLC LOA.

Table 2-1-1. BOI Departure Fixes

Departure Fix	FRD	Minimum Altitude (MSL)
HYVAL	BOI215041	10,000'
SAILL	BOI268041	8,000'
OLAAB	BOI309040	10,000'
VALYY	BOI350040	11,000'
FETHR	BOI071039	13,000'
ROARR	BOI096039	10,000'
BARNR	BOI030039	13,000'

- Aircraft requesting IFR practice approaches at BOI must be routed KBOI.RENOL.KBOI.
- Aircraft requesting IFR practice approaches at a satellite airport must be routed direct.

2-1-3. IFR Departure Altitudes

- a. All aircraft must be issued an initial departure altitude of 16,000 feet, or lower filed altitude.
- b. Aircraft with a filed altitude below 16,000 feet that will exit Big Sky TRACON airspace must be assigned an altitude at or above the minimum altitude for their departure fix, in accordance with Table 2-1-1.

2-1-4. Use of Pre-Departure Clearances (PDCs)

- a. Unless an operational necessity exists, a route amendment is required, or the aircraft is impacted by a posted TMI (except as outlined in paragraph 2-1-6), all PDC capable aircraft must be sent a PDC via vTDLS in lieu of a voice clearance.
- b. Fill out the boxes in vTDLS as follows:
 - (1) "Expect" box: Always select "10 MIN AFT DP" unless the aircraft's initial climb instruction is equal to their requested/assigned altitude. In this instance, leave the selection in this box blank.
 - (2) "SID" box: Always select "NO SID".
 - (3) "Transition" box: Must always be left blank.
 - (4) "Climb out" box: Always select "FLY RUNWAY HEADING".
 - (5) "Climb via" box: Must always be left blank.
 - (6) "Maintain" box: Select the initial altitude assignment in accordance with paragraph 2-1-3.
 - (7) "Contact info" box: This box should be left blank unless the aircraft will push back into the movement area.
 - (8) "Departure frequency" box: Select the appropriate departure frequency for the aircraft's route of flight and/or current staffing. Temporary non-standard departure frequencies can be added in the vTDLS Facility Menu.
 - (9) "Local info" box: Must always be left blank.

2-1-5. Reroute Procedures

When a reroute is required, CD must proceed with the following steps in order:

- a. Dump the aircraft from vTDLS.
- b. Amend the flight plan as necessary in the flight plan window, complying with paragraph 2-1-2.
- c. Print the amended flight progress strip, ensuring the revision number is correct, and delete the original strip.
- d. Verbally issue the departure clearance to the aircraft.
- e. Mark the amended flight progress strip in accordance with the ZLC Flight Strip Handling Directive (7210.3).

2-1-6. Compliance with TMIs

- a. Aircraft affected by posted TMIs must be advised of any delays verbally.
- b. Aircraft affected by posted TMIs must have pertinent TMI information placed in their flight progress strip, in accordance with the ZLC Flight Strip Handling Directive (7210.3).
- c. Aircraft affected by posted TMIs must not be issued a PDC.

NOTE-

Aircraft affected by an ESP or CFR program that are not expected to be assigned an EDCT are exempt from this clause.

2-1-7. VFR Departure Instructions

- a. Turbojet departures must be assigned runway heading without an altitude restriction. Write "RH" following a check mark into Box F of the aircraft's flight progress strip when given. An example FPS is listed below in Figure 2-1-1.

Figure 2-1-1. Example VFR Turbojet FPS

NIPU H25B FF North	10R W/0722 ✓ RH	
--------------------------	-----------------------	--

- b. All other aircraft:
 - (1) Runway 10L/10R:
 - (a) Aircraft departing south of the runway centerline must be assigned at or below 5,000 feet. Mark the altitude restriction on the FPS.
 - (b) Aircraft departing north of the runway centerline must not be assigned an altitude restriction.
 - (2) Runway 28L/28R departures must be assigned at or below 5,000 feet. Mark the altitude restriction on the FPS.

Section 2. Ground Control (GC)

2-2-1. Position Responsibilities

- a. Monitor the GC frequency (121.700 MHz).
- b. Ensure all taxiing aircraft have the current ATIS.
- c. Determine/finalize aircraft departure runway assignments.
- d. Marks FPSs in accordance with the ZLC Flight Strip Handling Directive (7210.3).
- e. Assume other ground control responsibilities, as assigned.
- f. Assume CD responsibilities when combined.

2-2-2. Area of Jurisdiction

GC has jurisdiction of all taxiways in the movement area, except for all taxiways located between Runway 10L and Runway 10R.

NOTE-

Taxiway J between Runway 10R and Taxiway W must be considered located between the runways, and therefore is not the jurisdiction of GC.

2-2-3. Traffic Flow

GC must ensure all aircraft yield to aircraft exiting a runway, unless otherwise coordinated with Local Control.

2-2-4. ATIS

Ensure all departure aircraft have the current ATIS.

2-2-5. Multiple Runway Crossings

A waiver has been granted to BOI ATCT for FAA JO 7110.65, paragraph 3-7-2, which requires an aircraft to have crossed a previous runway before another runway crossing clearance can be issued. Thus, aircraft may be cleared to cross both runways at BOI with a single clearance.

2-2-6. Pushback Clearances

To the maximum extent possible, aircraft parked at the terminal ramp should push back within the non-movement area.

2-2-7. Use Of SAID System

- a. SAID only displays ADS-B-equipped and transmitting aircraft/vehicles within the site-specific adapted area (the airport itself, not the surrounding area).
- b. SAID systems may rely solely on ADS-B transponder information to display aircraft identification if NAS flight plan information is not available to the system. This may result in a discrepancy between SAID depicted aircraft identification and NAS flight plan identification. This means that aircraft must have their ADS-B on with Altitude Reporting Enabled in order to move on the airport movement areas.
- c. SAID-derived information may only be used for reference and requires confirmation via visual observation and/or pilot/operator reporting.

- d. The SAID system does not use search patterns in a scratchpad box like ASDE-X.

Section 3. Local Control (LC)

2-3-1. Position Responsibilities

- Monitor the LC frequency (118.100 MHz).
- Provide control instructions to aircraft within the LC area of jurisdiction.
- Operate TDW/STARS equipment, as necessary.
- Marks FPSs in accordance with the ZLC Flight Strip Handling Directive (7210.3).
- Assume other local control or other cab responsibilities, as assigned.

2-3-2. Area of Jurisdiction

LC has jurisdiction of the following:

- LC airspace, as depicted in Appendix 1A.
- Runway 10L/28R.
- Runway 10R/28L.
- All taxiways between Runway 10L/28R and Runway 10R/28L.

2-3-3. Use of Radar

When using TDW/STARS, LC must:

- Comply with the provisions contained within FAA JO 7110.65 Chapter 5.
- Adjust the range of the radar to display a minimum of 10 NM.
- Display the BOI Tower List.

2-3-4. Departure Procedures

For all departing aircraft, LC must:

- Provide initial separation between all departures.
- Assign all non-turbojet VFR departures a heading and altitude restriction in accordance with Table 2-3-1 in East Flow or Table 2-3-2 in West Flow. LC may assign any heading within the heading ranges described in the applicable table.

Table 2-3-1. VFR Departure Procedures (East Flow)

Heading(s)	Altitude
010° clockwise to 069° (See Note)	Unrestricted
070° clockwise to 100°	
140° clockwise to 180°	At or below 5,000

NOTE-

LC assumes responsibility for separation from all known traffic within 8 NM of the center of BOI airport when assigning a heading between 010° clockwise to 069°.

Table 2-3-2. VFR Departure Procedures (West Flow)

Heading(s)	Altitude
250° clockwise to 310°	At or below 5,000

- c. Assign all turbojet VFR departures runway heading without an altitude restriction.
- d. Coordinate with Sage/Alpine if a departure aircraft does not auto-acquire within 3 NM of the departure end of the runway.
- e. Advise Sage/Alpine of aircraft executing an unplanned missed approach/go-around and comply with paragraph 1-3-6.

2-3-5. Arrival Procedures

For all arriving aircraft, LC must:

- a. Quick-look the Alpine sector.

NOTE-

When Alpine is combined to Sage, LC must quick-look the Sage sector.

- b. Sequence and separate VFR downwind traffic from all other traffic after accepting the handoff from Sage/Alpine.
- c. Have control of arrivals on initial contact. If LC issues control instructions that affect the sequence, LC assumes responsibility for separation and must coordinate with Sage/Alpine.

NOTE-

Coordination may be verbal or via STARS scratchpad.

- d. Issue traffic advisories to aircraft when:
 - (1) Two aircraft are on opposing bases.
 - (2) One aircraft is established on final and another aircraft will turn base to final beside the aircraft established on final.

2-3-6. Landing Clearance

The use of a memory aid upon issuance of a landing clearance is mandatory. The preferred method for utilizing a landing clearance memory aid is by highlighting the aircraft's STARS Full Data Block (FDB).

2-3-7. Multiple Runway Crossings

A waiver has been granted to BOI ATCT for FAA JO 7110.65, paragraph 3-7-2, which requires an aircraft to have crossed a previous runway before another runway crossing clearance can be issued. Thus, aircraft may be cleared to cross both runways at BOI with a single clearance.

Chapter 3. TRACON Operational Positions

Section 1. General Control

3-1-1. Facility Identification

When working TRACON sectors listed in sections 3-2 through 3-4, controllers must identify themselves as “Big Sky Approach” or “Big Sky Departure.”

3-1-2. Scratchpad Use

All scratchpad entries must be made in accordance with the ZLC Scratchpad Directive (7210.4). At a minimum, all arrival aircraft must have the approach type and runway placed in Scratchpad #1.

3-1-3. Altitude Filter Limits

Each position is required to set the filter limits at a minimum of 1,000 feet below the surface to 1,000 feet above the vertical limits assigned to that position. Other altitudes may be viewed at the controller’s discretion.

Section 2. Alpine Radar

3-2-1. Position Responsibilities

- a. Monitor the Alpine frequency (126.900 MHz).
- b. Provide air traffic control services within the Alpine delegated airspace (see Appendix 2B and 2C).

3-2-2. LC Coordination

Alpine must:

- a. Sequence all arrivals to BOI airport except for VFR aircraft handed off to LC.
- b. Ensure separation of arrivals to the LC airspace lateral boundary, except when wake turbulence separation minima applies. In this instance, ensure separation to the runway threshold.
- c. Transfer communications of arrival traffic to LC prior to the LC airspace boundary, but no further than 10 NM from the airport.
- d. Hand off all VFR arrivals to LC prior to the LC airspace boundary.

3-2-3. Procedures

- a. Alpine must adjust the range of their radar to display a minimum of 11 NM outside delegated airspace.
- b. Aircraft handed off from Sage are released for turns and descent, except for arrivals in the southernmost downwind during East Flow.

Section 3. Sage Radar

3-3-1. Position Responsibilities

- Monitor the Sage frequency (119.600 MHz).
- Provide air traffic control services within the Sage delegated airspace (see Appendix 2B and 2C).
- Assume Alpine responsibilities when combined.

3-3-2. Procedures

- Sage must adjust the range of their radar to display a minimum of 11 NM outside delegated airspace.
- Sequence BOI IFR arrival traffic to Alpine in accordance with Table 3-2-1 in East Flow or Table 3-2-2 in West Flow.

Table 3-2-1. BOI IFR Arrival Sequencing (East Flow)

STAR/Route/Direction	Altitude
KOURT# / SPUUD#	Descending to 8,000
Downwind (Heading 280°)	
SADYL#, Direct JIMMI or heading west of JIMMI (See Note)	Descending to 7,000
SADYL# (Vectored to a downwind only)	Descending to 8,000

NOTE-

Sage arrival traffic inbound via the Ellis Corridor or a “right base” leg to final (from the Southwest) must be routed via the SADYL#, direct to JIMMI, or assigned a heading that will direct the aircraft west of JIMMI.

Table 3-2-2. BOI IFR Arrival Sequencing (West Flow)

STAR/Route/Direction	Altitude
KYANN# / BEWTE#	Descending to 8,000
Downwind (Heading 100°)	
SADYL# (See Note 1)	
Direct TOILS or heading east of TOILS (See Note 2)	Descending to 11,000 or MVA (whichever is higher)

NOTE-

1. Aircraft assigned the SADYL# may be vectored into a downwind or may be kept on the West Flow transition.

2. Sage arrival traffic inbound via the Euugg Corridor that has been routed direct to BOI by ZLC must be routed direct to TOILS or assigned a heading that will direct the aircraft east of TOILS.

- c. When vectoring BOI IFR arrival traffic into a downwind for Alpine, headings may be assigned $\pm 15^\circ$ from the heading specified in Table 3-2-1 or Table 3-2-2 without additional coordination.

Section 4. Bozeman Radar

3-4-1. Position Responsibilities

- a. Monitor the Bozeman frequency (118.975 MHz).
- b. Provide air traffic control services within the Bozeman delegated airspace (see Appendix 2D).


3-4-2. Procedures

Bozeman must:


- a. Adjust the range of the radar to display a minimum of 10 NM outside of delegated airspace.
- b. Coordinate with Bozeman Federal Contract Tower (FCT) to determine the approach in use to be broadcast on the ATIS.
- c. Coordinate with BZN FCT for aircraft that are cleared for any type of approach other than advertised.
- d. Provide applicable separation for VFR aircraft conducting practice instrument approaches.

Appendix 1. Airspace


Appendix 1A. BOI Local Control Airspace




Appendix 1B. Sage/Alpine Radar (East Flow)



Appendix 1C. Sage/Alpine Radar (West Flow)




Appendix 1D. Bozeman Radar




Appendix 2. Pre-Arranged Coordination Areas

Appendix 2A. East Flow




Appendix 2B. West Flow



Appendix 3. Arrival Zones

Appendix 3A. East Flow



Appendix 3B. West Flow

