# Deploying MobileFirst Server on IBM PureApplication System

#### **Overview**

IBM MobileFirst Foundation provides the capability to deploy and manage IBM MobileFirst Server and MobileFirst applications on IBM PureApplication System and IBM PureApplication Service on SoftLayer.

IBM MobileFirst Platform Foundation in combination with IBM PureApplication System and IBM PureApplication Service on SoftLayer provides a simple and intuitive environment for developers and administrators, to develop mobile applications, test them, and deploy them to the cloud. This version of IBM MobileFirst Foundation System Pattern provides MobileFirst runtime and artifacts support for the PureApplication Virtual System Pattern technologies that are included in the most recent versions of IBM PureApplication System and IBM PureApplication Service on SoftLayer. Classic Virtual System Pattern was supported in earlier versions of IBM PureApplication System.

#### Jump to

- Installing IBM MobileFirst Foundation System Pattern
- Token licensing requirements for IBM MobileFirst Foundation System Pattern
- Deploying MobileFirst Server on a single-node WebSphere Application Server Liberty profile server
- Deploying MobileFirst Server on a multiple-node WebSphere Application Server Liberty profile server
- Deploying MobileFirst Server on a single-node WebSphere Application Server full profile server
- Deploying MobileFirst Server on a multiple-node WebSphere Application Server full profile server
- Deploying MobileFirst Server on clusters of WebSphere Application Server Network Deployment servers
- Deploying MobileFirst Application Center on a single-node WebSphere Application Server Liberty profile server
- Deploying MobileFirst Application Center on a single-node WebSphere Application Server full profile server
- Configuring MobileFirst administration security with an external LDAP repository
  - o Configuring an external database with a IBM MobileFirst Platform Foundation System Pattern
- Deploying and configuring MobileFirst Analytics
- Predefined templates for MobileFirst Platform Pattern
- Script packages for MobileFirst Server
- Upgrading IBM MobileFirst Platform Foundation System Pattern

#### Key benefits

IBM MobileFirst Foundation System Pattern provides the following benefits:

- Predefined templates enable you to build patterns in a simple way for the most typical MobileFirst Server deployment topologies. Examples of the topologies are:
  - IBM WebSphere Application Server Liberty profile single node
  - IBM WebSphere Application Server Liberty profile multiple nodes
  - IBM WebSphere Application Server full profile single node
  - IBM WebSphere Application Server full profile multiple nodes
  - o Clusters of WebSphere Application Server Network Deployment servers

In V8.0.0 MobileFirst Application Center, deployment topologies such as: \* IBM WebSphere Application Server Liberty profile single node \* IBM WebSphere Application Server full profile single node

- Script packages act as building blocks to compose extended deployment topologies such as automating the
  inclusion of an analytics server in a pattern and flexible DB VM deployment options. WebSphere Application
  Server and DB2 script packages are available through the inclusion of WebSphere Application Server and DB2
  pattern types.
- Optional JNDI properties in the runtime deployment script package allow fine-grained tuning for the deployment

topology. In addition, deployment topologies that are built with IBM WebSphere Application Server full profile now support accessing the WebSphere Application Server Administration Console, which gives you full control over the configuration of the application server.

#### Important restrictions

Depending on the pattern template you use, do not change some of the component attributes. If you change any of these component attributes, the deployment of patterns that are based on these templates fails.

#### MobileFirst Platform (Application Center Liberty single node)

Do not change the values for the following attributes in the Liberty profile server:

- WebSphere product Installation directory
- Configuration data location
- Liberty profile server name
- Under Install an IBM Java SDK, select only Java SDK V7.0 or Java SDK V7.1
- Select the Install additional features and clear the selection of IBM WebSphere eXtreme Scale.

#### MobileFirst Platform (Application Center WebSphere Application Server single node)

Do not change the values for the following attributes in the Liberty profile server:

- WebSphere product Installation directory
- Configuration data location
- Cell name
- Node name
- Profile name
- Under Install an IBM Java SDK, select only Java SDK V7.0 or Java SDK V7.1
- Select the Install additional features and clear the selection of IBM WebSphere eXtreme Scale.

#### MobileFirst Platform (Liberty single node)

Do not change the values for the following attributes in the Liberty profile server:

- WebSphere product Installation directory
- Configuration data location
- Liberty profile server name
- Under Install an IBM Java SDK, select only Java SDK V7.0 or Java SDK V7.1
- Select the Install additional features and clear the selection of IBM WebSphere eXtreme Scale.

#### MobileFirst Platform (Liberty server farm)

Do not change the values for the following attributes in the Liberty profile server:

- WebSphere product Installation directory
- Configuration data location
- Liberty profile server name
- Under Install an IBM Java SDK, select only Java SDK V7.0 or Java SDK V7.1
- Select the Install additional features and clear the selection of IBM WebSphere eXtreme Scale.

#### MobileFirst Platform (WebSphere Application Server single node) template

In the **Standalone server component** of the MobileFirst Server node, do not unlock or change the values for any of the following attributes:

- Cell name
- Node name
- Profile name
- If you change any of these attributes, your pattern deployment fails.

MobileFirst Platform (WebSphere Application Server server farm) template

In the **Standalone server component** of the MobileFirst Server node, do not unlock or change the values for any of the following attributes:

- Cell name
- Node name
- Profile name
- If you change any of these attributes, your pattern deployment fails.

MobileFirst Platform (WebSphere Application Server Network Deployment) template

In the **Deployment manager component** of the **DmgrNode node** or the **Custom nodes component** of the **CustomNode node**, do not unlock or change the values for any of the following attributes:

- Cell name
- Node name
- Profile name

If you change any of these attributes, your pattern deployment fails.

#### Limitations

The following limitations apply:

- Dynamic scaling for WebSphere Application Server Liberty profile server farms and WebSphere Application Server full profile server farms is not supported. The number of server farm nodes can be specified in the pattern by setting the scaling policy but cannot be changed during run time.
- The IBM MobileFirst Foundation System Pattern Extension for MobileFirst Studio and Ant command-line interface that is supported in versions earlier than V7.0 are not available in this version of IBM MobileFirst Foundation System Pattern.
- IBM MobileFirst Foundation System Pattern depends on WebSphere Application Server Patterns, which has its own restrictions. For more information, see Restrictions for WebSphere Application Server Patterns (http://ibm.biz/knowctr#SSAJ7T\_1.0.0/com.ibm.websphere.waspatt20base.doc/ae/rins\_patternsB\_restrictions.html).
- Due to restrictions in the uninstallation of Virtual System Patterns, you must delete the script packages manually
  after you delete the pattern type. In IBM PureApplication System, go to Catalog → Script Packages to delete the
  script packages that are listed in the Components section.
- The MobileFirst (WebSphere Application Server Network Deployment) pattern template does not support token licensing. If you want to use this pattern, you must use perpetual licensing. All other patterns support token licensing.

#### Composition

IBM MobileFirst Platform Foundation System Pattern is composed of the following patterns:

- IBM WebSphere Application Server Network Deployment Patterns 2.2.0.0.
- [PureApplication Service] WebSphere 8558 for Mobile IM repository to allow the WebSphere Application Server Network Deployment Patterns to work. Contact the administrator for IBM PureApplication System to confirm that the WebSphere 8558 IM repository is installed.
- IBM DB2 with BLU Acceleration Pattern 1.2.4.0.
- IBM MobileFirst Platform Foundation System Pattern.

#### Components

In addition to all components provided by IBM WebSphere Application Server Pattern and IBM DB2 with BLU Acceleration Pattern, IBM MobileFirst Platform Foundation System Pattern provides the following Script Packages:

MFP Administration DB

- MFP Runtime DB
- MFP Server Prerequisite
- MFP Server Administration
- MFP Server Runtime Deployment
- MFP Server Application Adapter Deployment
- MFP IHS Configuration
- MFP Analytics
- MFP Open Firewall Ports for WAS
- MFP WAS SDK Level
- MFP Server Application Center

### Compatibility between pattern types and artifacts created with different product versions

If you use MobileFirst Studio V6.3.0 or earlier to develop your applications, you can upload the associated runtime, application, and adapter artifacts into patterns associated with IBM MobileFirst Platform Foundation V7.0.0 and later.

Pattern types that are associated with IBM MobileFirst Platform Foundation V6.3.0 or earlier are not compatible with runtime, application, and adapter artifacts created by using MobileFirst Studio V7.0.0 and later.

For versions V6.0.0 and earlier, only the same versions of server, .war file, application (.wlapp file), and adapters are compatible.

### Installing IBM MobileFirst Foundation System Pattern

You can find the vsys.mobilefirst-8.0.0.0.tgz file in the mobilefirst\_patterns\_8.0.0.zip file. Make sure you extract it before you start this procedure.

- 1. Log in to IBM PureApplication System with an account that has permission to create new pattern types.
- Go to Catalog → Pattern Types.
- 3. Upload the IBM MobileFirst Platform Foundation System Pattern .tgz file:
  - On the toolbar, click +. The "Install a pattern type" window opens.
  - the Local tab, click **Browse**, select the IBM MobileFirst Platform Foundation System Pattern .tgz file, and then wait for the upload process to complete. The pattern type is displayed in the list and is marked as not enabled.
- 4. In the list of pattern types, click the uploaded pattern type. Details of the pattern type are displayed.
- 5. In the License Agreement row, click **License**. The License window is displayed stating the terms of the license agreement.
- 6. To accept the license, click Accept. Details of the pattern type now show that the license is accepted.
- 7. In the Status row, click **Enable**. The pattern type is now listed as being enabled.
- 8. Mandatory for PureApplication Service: After the pattern type is enabled successfully, go to Catalog → Script Packages and select script packages with names similar to "MFP \*\*\*". On the details page to the right, accept the license in the License agreement field. Repeat for all eleven script packages listed in the Components section.

### Token licensing requirements for IBM MobileFirst Foundation System Pattern

If you use token licensing to license IBM MobileFirst Foundation, you must install IBM Rational License Key Server and configure with your licenses before you deploy the MobileFirst Platform Pattern.

**Important:** The **MobileFirst Platform (WAS ND)** pattern template does not support token licensing. You must be using perpetual licensing when you deploy patterns based on the MobileFirst Platform (WAS ND) pattern template. All other pattern templates support token licensing.

Your IBM Rational License Key Server must be external to your PureApplication System. MobileFirst Pattern do not support the PureApplication System shared service for IBM Rational License Key Server.

In addition, you must know the following information about your Rational License Key Server to add the license key server information to your pattern attributes:

- Fully qualified host name or IP address of your Rational License Key Server
- License manager daemon (Imgrd) port
- Vendor daemon (ibmratl) port

If you have a firewall between your Rational License Key Server and your PureApplication System, ensure that both daemon ports are open in your firewall. The deployment of MobileFirst Pattern fails if the license key server cannot be contacted or if insufficient license tokens are available.

For details about installing and configuring Rational License Key Server, see IBM Support - Rational licensing start page (http://www.ibm.com/software/rational/support/licensing/).

# Deploying MobileFirst Server on a single-node WebSphere Application Server Liberty profile server

You use a predefined template to deploy MobileFirst Server on a single-node WebSphere Application Server Liberty profile server.

This procedure involves uploading certain artifacts to IBM PureApplication System such as the required application and adapter. Before you begin, ensure that the artifacts are available for upload.

**Token licensing requirements:** If you use token licensing to license IBM MobileFirst Foundation, review the requirements outlined in Token licensing requirements for IBM MobileFirst Foundation System Pattern before you continue. The deployment of this pattern fails if the license key server cannot be contacted or if insufficient license tokens are available.

Some parameters of script packages in the template have been configured with the recommended values and are not mentioned in this section. For fine-tuning purposes, see more information about all the parameters of script packages in Script packages for MobileFirst Server.

For more information about the composition and configuration options of the predefined template that is used in this procedure, see MobileFirst Platform (Liberty single node) template.

- 1. Create a pattern from the predefined template:
  - In the IBM PureApplication System dashboard, click Patterns → Virtual System Patterns. The Virtual System Patterns page opens.
  - On the Virtual System Patterns page, click Create New, and then in the pop-up window, select
    MobileFirst Platform (Liberty single node) from the list of predefined templates. If the name is only
    partially visible due to its length, you can confirm that the correct template is selected by viewing its
    description on the More information tab.
  - o In the Name field, provide a name for the pattern.
  - In the **Version** field, specify the version number of the pattern.
  - Click Start Building.
- 2. Mandatory for AIX: In IBM PureApplication System running on Power, the MobileFirst Platform DB node needs to use the AIX-specific add-on component "Default AIX add disk" to replace the "Default add disk" component in the template to support the jfs2 file system:
  - In the Pattern Builder, select the **MobileFirst Platform DB** node.
  - Click the Add a Component Add-on button (the button is visible above the component box when you
    hover the cursor over the MobileFirst Platform DB node).
  - From the Add Add-ons list, select Default AIX add disk. The component is added as the lowest component of the MobileFirst Platform DB node.
  - Select the **Default AIX add disk** component and specify the following attributes:
    - DISK\_SIZE\_GB: Storage size (measured in GB) to be extended to the DB server. Example value:

- FILESYSTEM TYPE: Supported file system in AIX. Default value: jfs2.
- MOUNT\_POINT: Align with the attribute Mount point for instance owner in the Database Server component in the MobileFirst Platform DB node. Example value: /dbinst.
- **VOLUME\_GROUP:** Example value: **group1**. Contact your IBM PureApplication System administrator for the correct value.
- In the MobileFirst Platform DB node, select the **Default add disk** component, and then click the bin icon to delete it.
- o Save the pattern.
- 3. Optional: Configure MobileFirst Server administration. You can skip this step if you want to specify the user credential with MobileFirst Server administration privilege later during the pattern deployment configuration phase in step 9. To specify it now, complete these steps:

**Note:** If you want to configure administration security with an LDAP server, you need to supply additional LDAP information. For more information, see Configuring MobileFirst administration security with an external LDAP repository.

- In the MobileFirst Platform Server node, click the **MFP Server Administration** component. The properties of the selected component are displayed next to the canvas.
- Next to the admin\_user and admin\_password fields, click the Delete button to clear their pattern level parameter settings.
- In the admin\_user and admin\_password fields, specify the administration user name and password.
- If you use token licensing to license IBM MobileFirst Platform Foundation, complete the following fields. If you do not use token licensing, leave these fields blank.

**ACTIVATE\_TOKEN\_LICENSE**: Select this field to license your pattern with token licensing.

**LICENSE\_SERVER\_HOSTNAME**: Enter the fully qualified host name or IP address of your Rational License Key Server.

**LMGRD\_PORT**: Enter the port number that the license manager daemon (**Imrgd**) listens for connections on. The default license manager daemon port is 27000.

**IBMRATL\_PORT**:Enter the port number that the vendor daemon (**ibmratl**) listens for connections on. The default vendor daemon port is typically 27001.

A default administration account for MobileFirst Server is created during pattern deployment.

- 4. Optional: Configure MobileFirst Server runtime deployment. You can skip this step if you want to specify the context root name for the runtime later during the pattern deployment configuration phase in step 9. To specify the context root name now, complete these steps:
  - In the MobileFirst Platform Server node, click the **MFP Server Runtime Deployment** component. The properties of the selected component are displayed next to the canvas.
  - Next to the runtime\_contextRoot field, click the Delete button to clear the pattern level parameter setting.
  - In the **runtime\_contextRoot** field, specify the runtime context root name. Note that the context root name must start with a forward slash, /; for example, /HelloWorld.
- 5. Upload application and adapter artifacts:

**Important:** When specifying the Target path for applications and adapters, make sure all the applications and adapters are placed in the same directory. For example, if one target path is /opt/tmp/deploy/HelloWorld-common.json, all the other target paths should be /opt/tmp/deploy/\*.

- In the MobileFirst Platform Server node, click the MFP Server Application or MFP Server Adapter component. The properties of the selected component are displayed next to the canvas.
- In the Additional file field, click the Browse button to locate and upload the application or adapter artifact.
- In the **Target path** field, specify the full path for storing the artifact including its file name; for example, /opt/tmp/deploy/HelloWorld-common.json.
- If no application or adapter is to be deployed in the pattern, remove the relevant component by clicking the X button inside it. To get an empty MobileFirst Operations Console deployed without any app or adapter installed, remove the MFP Server Application Adapter Deployment component by clicking the X button inside it.
- 6. Optional: Add more application or adapter artifacts for deployment:
  - From the Assets toolbar, expand Software Components, and then drag and drop an Additional file component onto the MobileFirst Paltform Server node in the canvas. Rename it MobileFirst App\_X or MobileFirst Adatper\_X (where X stands for a unique number for differentiation).
  - Hover the cursor over the newly added App or Adapter component, and then click the Move Up and Move
     Down buttons to adjust its sequence in the node. Make sure it is placed after the MFP Runtime
     Deployment component but before the MFP Server Application Adapter Deployment component.
  - Click the newly added application or adapter component. The properties of the selected component are displayed next to the canvas. Upload the application or adapter artifact and specify its target path by referring to the steps in step 6.
  - Repeat step 7 to add more applications and adapters for deployment.
- 7. Optional: Configure application and adapter deployment to MobileFirst Server. You can skip this step if you want to specify the user credential with deployment privilege later during the pattern deployment configuration phase in step 9. If you have specified the default admin user credential in step 3, you can now specify the deployer user, which must align with the admin user credential:
  - In the MobileFirst Platform Server node, select the **MFP Server Application Adapter Deployment** component. The properties of the selected component are displayed next to the canvas.
  - Find the parameters named **deployer\_user** and **deployer\_password**, and then click the adjacent Delete buttons to clear the pattern level parameter settings.
  - In the deployer\_user and deployer\_password fields, specify the user name and password.
- 8. Configure and launch the pattern deployment:
  - o In the IBM PureApplication System dashboard, click Patterns → Virtual System Patterns.
  - o On the Virtual System Patterns page, use the **Search** field to find the pattern you created, and then select the pattern.
  - o In the toolbar above the panel displaying detailed information about the pattern, click the Deploy button.
  - In the Deploy Pattern window, in the Configure panel, select the correct environment profile from the
     Environment Profile list, and provide other IBM PureApplication System environment parameters. To
     obtain the correct information, consult your IBM PureApplication System administrator.
  - In the middle column, click **Pattern attributes** to display attributes such as user names and passwords.
     Supply the following information in the fields provided:

**Note:** Make appropriate changes to the default values of the pattern-level parameters even if an external LDAP server is configured. If you configure administration security by using an LDAP server, you need to supply additional LDAP information. For more information, see Configuring MobileFirst administration security with an external LDAP repository.

#### admin\_user

Not visible if configured in step 3. Create a default MobileFirst Server administrator account. Default value: demo.

#### admin\_password

Not visible if configured in step 3. Default admin account password. Default value: demo.

#### ACTIVATE\_TOKEN\_LICENSE

Not visible if configured in step 3. Select this field to license your pattern with token licensing. Leave this field clear if you use perpetual licenses.

#### LICENSE SERVER HOSTNAME

Not visible if configured in step 3. If you use token licensing to license IBM MobileFirst Platform Foundation, enter the fully-qualified hostname or IP address of your Rational License Key Server IP address. Otherwise, leave this field blank.

#### LMGRD PORT

Not visible if configured in step 3. If you use token licensing to license IBM MobileFirst Platform Foundation, enter the port number that the license manager daemon (Imrgd) listens for connections on. Otherwise, leave this field blank. The default license manager daemon port is 27000.

#### **IBMRATL PORT**

Not visible if configured in step 3. If you use token licensing to license IBM MobileFirst Platform Foundation, enter the port number that the vendor daemon (ibmratl) listens for connections on. Otherwise, leave this field blank. The default vendor daemon port is typically 27001.

#### runtime contextRoot

Not visible if configured in step 5. Context root name for the MobileFirst Server runtime. The name must start with "/".

#### deployer\_user

Not visible if configured in step 8. User name for the account with deployment privilege. If an external LDAP server is not configured, you must enter the same value as was specified when creating the default admin user for the administration service, because in this case, the only authorized user for app and adapter deployment is the default admin user.

#### deployer\_password

Not visible if configured in step 8. User password for the user with deployment privilege.

#### MFP Vms Password(root)

Root password for the MobileFirst Platform Server and MobileFirst Platform DB nodes. Default value: passw0rd.

#### MFP DB Password(Instance owner)

Instance owner password for the MobileFirst Platform DB node. Default value: passw0rd.

Click Quick Deploy to launch your pattern deployment. After a few seconds, a message is displayed to
indicate that the pattern has started to launch. You can click the URL provided in the message to track
your pattern deployment status or go to Patterns → Virtual System Instances to open the Virtual System
Instances page and search for your pattern there.

If you use token licensing to licenseIBM MobileFirst Platform Foundation, your pattern will fail to deploy if insufficient license tokens are available or if the license key server IP address and port were entered incorrectly.

- 9. Access the MobileFirst Operations Console:
  - Click Patterns → Virtual System Instances to open the Virtual System Instances page and search for

- your pattern there. Make sure it is in Running state.
- Select the pattern name and expand the Virtual machine perspective option in the panel displaying details of the selected instance.
- Find the MobileFirst Server VM that has a name similar to **MobileFirst\_Platform\_Server.** and make a note of its Public IP address: you need this information in the following step.
- In the browser, open the MobileFirst Operations Console by composing its URL with one of the following formats:
  - http://{MFP Server VM Public IP}:9080/mfpconsole
  - https://{MFP Server VM Public IP}:9443/mfpconsole
- Log in to the Console with admin user and password specified in step 3 or step 9.

### Deploying MobileFirst Server on a multiple-node WebSphere Application Server Liberty profile server

You use a predefined template to deploy MobileFirst Server on a multiple-node WebSphere Application Server Liberty profile server.

This procedure involves uploading certain artifacts to IBM PureApplication System such as the required application and adapter. Before you begin, ensure that the artifacts are available for upload.

**Token licensing requirements:** If you use token licensing to license IBM MobileFirst Foundation, review the requirements outlined in Token licensing requirements for IBM MobileFirst Foundation System Pattern before you continue. The deployment of this pattern fails if the license key server cannot be contacted or if insufficient license tokens are available.

Some parameters of script packages in the template have been configured with the recommended values and are not mentioned in this section. For fine-tuning purposes, see more information about all the parameters of script packages in Script packages for MobileFirst Server.

For more information about the composition and configuration options of the predefined template that is used in this procedure, see MobileFirst Platform (Liberty server farm) template.

- 1. Create a pattern from the predefined template:
  - In the IBM PureApplication System dashboard, click Patterns → Virtual System Patterns. The Virtual System Patterns page opens.
  - On the Virtual System Patterns page, click Create New, and then in the pop-up window, select
     MobileFirst Platform (Liberty server farm) from the list of predefined templates. If the name is only
     partially visible due to its length, you can confirm that the correct template is selected by viewing its
     description on the More information tab.
  - o In the Name field, provide a name for the pattern.
  - In the **Version** field, specify the version number of the pattern.
  - · Click Start Building.
- 2. Mandatory for AIX: In IBM PureApplication System running on Power, the MobileFirst Platform DB node needs to use the AIX-specific add-on component "Default AIX add disk" to replace the "Default add disk" component in the template to support the jfs2 file system:
  - In the Pattern Builder, select the MobileFirst Platform DB node.
  - Click the Add a Component Add-on button (the button is visible above the component box when you
    hover the cursor over the MobileFirst Platform DB node).
  - From the Add Add-ons list, select Default AIX add disk. The component is added as the lowest component of the MobileFirst Platform DB node.
  - Select the **Default AIX add disk** component and specify the following attributes:
    - **DISK\_SIZE\_GB:** Storage size (measured in GB) to be extended to the DB server. Example value:
    - FILESYSTEM\_TYPE: Supported file system in AIX. Default value: jfs2.

- MOUNT\_POINT: Align with the attribute Mount point for instance owner in the Database Server component in the MobileFirst Platform DB node. Example value: /dbinst.
- **VOLUME\_GROUP:** Example value: **group1**. Contact your IBM PureApplication System administrator for the correct value.
- In the MobileFirst Platform DB node, select the **Default add disk** component, and then click the bin icon to delete it.
- · Save the pattern.
- 3. Optional: Configure MobileFirst Server administration. You can skip this step if you want to specify the user credential with MobileFirst Server administration privilege later during the pattern deployment configuration phase in step 9. To specify it now, complete these steps:

**Note:** If you want to configure administration security with an LDAP server, you need to supply additional LDAP information. For more information, see Configuring MobileFirst administration security with an external LDAP repository.

- In the MobileFirst Platform Server node, click the MFP Server Administration component.
   The properties of the selected component are displayed next to the canvas.
- Next to the admin\_user and admin\_password fields, click the Delete button to clear their pattern level parameter settings.
- In the admin\_user and admin\_password fields, specify the administration user name and password.
- If you use token licensing to license IBM MobileFirst Platform Foundation, complete the following fields. If you do not use token licensing, leave these fields blank.

ACTIVATE TOKEN LICENSE: Select this field to license your pattern with token licensing.

**LICENSE\_SERVER\_HOSTNAME**: Enter the fully qualified host name or IP address of your Rational License Key Server.

**LMGRD\_PORT**: Enter the port number that the license manager daemon (**Imrgd**) listens for connections on. The default license manager daemon port is 27000.

**IBMRATL\_PORT**:Enter the port number that the vendor daemon (**ibmratl**) listens for connections on. The default vendor daemon port is typically 27001.

A default administration account for MobileFirst Server is created during pattern deployment.

- 4. Optional: Configure MobileFirst Server runtime deployment. You can skip this step if you want to specify the context root name for the runtime later during the pattern deployment configuration phase in step 10. To specify the context root name now, complete these steps:
  - In the MobileFirst Platform Server node, click the **MFP Server Runtime Deployment** component. The properties of the selected component are displayed next to the canvas.
  - Next to the runtime\_contextRoot field, click the Delete button to clear the pattern level parameter setting.
  - In the **runtime\_contextRoot** field, specify the runtime context root name. Note that the context root name must start with a forward slash, /; for example, /HelloWorld.
- 5. Upload application and adapter artifacts:

**Important:** When specifying the Target path for applications and adapters, make sure all the applications and adapters are placed in the same directory. For example, if one target path is /opt/tmp/deploy/HelloWorld-common.json, all the other target paths should be /opt/tmp/deploy/\*.

- In the MobileFirst Platform Server node, click the MFP Server Application or MFP Server Adapter component. The properties of the selected component are displayed next to the canvas.
- In the Additional file field, click the Browse button to locate and upload the application or adapter artifact.
- In the **Target path** field, specify the full path for storing the artifact including its file name; for example, /opt/tmp/deploy/HelloWorld-common.json.
- If no application or adapter is to be deployed in the pattern, remove the relevant component by clicking the X button inside it. To get an empty MobileFirst Operations Console deployed without any app or adapter installed, remove the MFP Server Application Adapter Deployment component by clicking the X button inside it.
- 6. Optional: Add more application or adapter artifacts for deployment:
  - From the Assets toolbar, expand Software Components, and then drag and drop an Additional file component onto the MobileFirst Paltform Server node in the canvas. Rename it MobileFirst App\_X or MobileFirst Adatper\_X (where X stands for a unique number for differentiation).
  - Hover the cursor over the newly added App or Adapter component, and then click the Move Up and Move
     Down buttons to adjust its sequence in the node. Make sure it is placed after the MFP Runtime
     Deployment component but before the MFP Server Application Adapter Deployment component.
  - Click the newly added application or adapter component. The properties of the selected component are displayed next to the canvas. Upload the application or adapter artifact and specify its target path by referring to the steps in step 6.
  - Repeat step 7 to add more applications and adapters for deployment.
- 7. Optional: Configure application and adapter deployment to MobileFirst Server. You can skip this step if you want to specify the user credential with deployment privilege later during the pattern deployment configuration phase in step 9. If you have specified the default admin user credential in step 3, you can now specify the deployer user, which must align with the admin user credential:
  - In the MobileFirst Platform Server node, select the **MFP Server Application Adapter Deployment** component. The properties of the selected component are displayed next to the canvas.
  - Find the parameters named **deployer\_user** and **deployer\_password**, and then click the adjacent Delete buttons to clear the pattern level parameter settings.
  - In the deployer\_user and deployer\_password fields, specify the user name and password.
- 8. Configure base scaling policy:
  - In the **MobileFirst Platform Server** node, select the **Base Scaling Policy** component. The properties of the selected component are displayed next to the canvas.
  - In the Number of Instances field, specify the number of server nodes to be instantiated during pattern
    deployment. The default value is 2 in the predefined template. Because dynamic scaling is not supported
    in this release, do not specify values in the remaining attribute fields.
- 9. Configure and launch the pattern deployment:
  - In the IBM PureApplication System dashboard, click Patterns → Virtual System Patterns.
  - o On the Virtual System Patterns page, use the **Search** field to find the pattern you created, and then select the pattern.
  - In the toolbar above the panel displaying detailed information about the pattern, click the Deploy button.

- In the Deploy Pattern window, in the Configure panel, select the correct environment profile from the
   Environment Profile list, and provide other IBM PureApplication System environment parameters. To
   obtain the correct information, consult your IBM PureApplication System administrator.
- In the middle column, click **Pattern attributes** to display attributes such as user names and passwords.
   Supply the following information in the fields provided:

**Note:** Make appropriate changes to the default values of the pattern-level parameters even if an external LDAP server is configured. If you configure administration security by using an LDAP server, you need to supply additional LDAP information. For more information, see Configuring MobileFirst administration security with an external LDAP repository.

#### admin\_user

Not visible if configured in step 3. Create a default MobileFirst Server administrator account. Default value: demo.

#### admin\_password

Not visible if configured in step 3. Default admin account password. Default value: demo.

#### **ACTIVATE TOKEN LICENSE**

Not visible if configured in step 3. Select this field to license your pattern with token licensing. Leave this field clear if you use perpetual licenses.

#### LICENSE\_SERVER\_HOSTNAME

Not visible if configured in step 3. If you use token licensing to license IBM MobileFirst Platform Foundation, enter the fully-qualified hostname or IP address of your Rational License Key Server IP address. Otherwise, leave this field blank.

#### LMGRD\_PORT

Not visible if configured in step 3. If you use token licensing to license IBM MobileFirst Platform Foundation, enter the port number that the license manager daemon (Imrgd) listens for connections on. Otherwise, leave this field blank. The default license manager daemon port is 27000.

#### **IBMRATL PORT**

Not visible if configured in step 3. If you use token licensing to license IBM MobileFirst Platform Foundation, enter the port number that the vendor daemon (ibmratl) listens for connections on. Otherwise, leave this field blank. The default vendor daemon port is typically 27001.

#### runtime contextRoot

Not visible if configured in step 5. Context root name for the MobileFirst Server runtime. The name must start with "/".

#### deployer\_user

Not visible if configured in step 8. User name for the account with deployment privilege. If an external LDAP server is not configured, you must enter the same value as was specified when creating the default admin user for the administration service, because in this case, the only authorized user for app and adapter deployment is the default admin user.

#### deployer\_password

Not visible if configured in step 8. User password for the user with deployment privilege.

#### MFP Vms Password(root)

Root password for the MobileFirst Platform Server and MobileFirst Platform DB nodes. Default value: passw0rd.

#### MFP DB Password(Instance owner)

Instance owner password for the MobileFirst Platform DB node. Default value: passw0rd.

Click Quick Deploy to launch your pattern deployment. After a few seconds, a message is displayed to
indicate that the pattern has started to launch. You can click the URL provided in the message to track
your pattern deployment status or go to Patterns → Virtual System Instances to open the Virtual System

Instances page and search for your pattern there.

If you use token licensing to licenseIBM MobileFirst Platform Foundation, your pattern will fail to deploy if insufficient license tokens are available or if the license key server IP address and port were entered incorrectly.

- 10. Access the MobileFirst Operations Console:
  - Click Patterns → Virtual System Instances to open the Virtual System Instances page and search for your pattern there. Make sure it is in Running state.
  - Select the pattern name and expand the Virtual machine perspective option in the panel displaying details of the selected instance.
  - Find the IHS Server VM that has a name similar to **IHS\_Server.**\* and make a note of its Public IP address: you need this information in the following step.
  - In the browser, open the MobileFirst Operations Console by composing its URL with one of the following formats:
    - http://{IHS Server VM Public IP}/mfpconsole
    - https://{IHS Server VM Public IP}/mfpconsole
  - Log in to the Console with the admin user ID and password specified in step 3 or step 10.

### Deploying MobileFirst Server on a single-node WebSphere Application Server full profile server

You use a predefined template to deploy a single-node MobileFirst Server to a WebSphere Application Server full profile server.

This procedure involves uploading certain artifacts to IBM PureApplication System such as the required application and adapter. Before you begin, ensure that the artifacts are available for upload.

**Token licensing requirements:** If you use token licensing to license IBM MobileFirst Foundation, review the requirements outlined in Token licensing requirements for IBM MobileFirst Foundation System Pattern before you continue. The deployment of this pattern fails if the license key server cannot be contacted or if insufficient license tokens are available.

Some parameters of script packages in the template have been configured with the recommended values and are not mentioned in this section. For fine-tuning purposes, see more information about all the parameters of script packages in Script packages for MobileFirst Server.

For more information about the composition and configuration options of the predefined template that is used in this procedure, see MobileFirst Platform (WAS single node) template.

- 1. Create a pattern from the predefined template:
  - In the IBM PureApplication System dashboard, click Patterns → Virtual System Patterns. The Virtual System Patterns page opens.
  - On the Virtual System Patterns page, click Create New, and then in the pop-up window, select
     MobileFirst Platform (WAS single node) from the list of predefined templates. If the name is only
     partially visible due to its length, you can confirm that the correct template is selected by viewing its
     description on the More information tab.
  - In the **Name** field, provide a name for the pattern.
  - In the **Version** field, specify the version number of the pattern.
  - · Click Start Building.
- 2. Mandatory for AIX: In IBM PureApplication System running on Power, the MobileFirst Platform DB node needs to use the AIX-specific add-on component "Default AIX add disk" to replace the "Default add disk" component in the template to support the jfs2 file system:
  - In the Pattern Builder, select the **MobileFirst Platform DB** node.
  - Click the Add a Component Add-on button (the button is visible above the component box when you
    hover the cursor over the MobileFirst Platform DB node).
  - From the Add Add-ons list, select Default AIX add disk. The component is added as the lowest

component of the MobileFirst Platform DB node.

- Select the Default AIX add disk component and specify the following attributes:
  - **DISK\_SIZE\_GB:** Storage size (measured in GB) to be extended to the DB server. Example value: **10**.
  - FILESYSTEM TYPE: Supported file system in AIX. Default value: ifs2.
  - MOUNT\_POINT: Align with the attribute Mount point for instance owner in the Database Server component in the MobileFirst Platform DB node. Example value: /dbinst.
  - **VOLUME\_GROUP:** Example value: **group1**. Contact your IBM PureApplication System administrator for the correct value.
- In the MobileFirst Platform DB node, select the **Default add disk** component, and then click the bin icon to delete it.
- · Save the pattern.
- 3. Optional: Configure MobileFirst Server administration. You can skip this step if you want to specify the user credential with MobileFirst Server administration privilege later during the pattern deployment configuration phase in step 9. To specify it now, complete these steps:

**Note:** If you want to configure administration security with an LDAP server, you need to supply additional LDAP information. For more information, see Configuring MobileFirst administration security with an external LDAP repository.

- In the MobileFirst Platform Server node, click the MFP Server Administration component.
   The properties of the selected component are displayed next to the canvas.
- Next to the admin\_user and admin\_password fields, click the Delete button to clear their pattern level parameter settings.
- In the admin\_user and admin\_password fields, specify the administration user name and password.
- If you use token licensing to license IBM MobileFirst Platform Foundation, complete the following fields. If you do not use token licensing, leave these fields blank.

**ACTIVATE TOKEN LICENSE**: Select this field to license your pattern with token licensing.

**LICENSE\_SERVER\_HOSTNAME**: Enter the fully qualified host name or IP address of your Rational License Key Server.

**LMGRD\_PORT**: Enter the port number that the license manager daemon (**Imrgd**) listens for connections on. The default license manager daemon port is 27000.

**IBMRATL\_PORT**:Enter the port number that the vendor daemon (**ibmratl**) listens for connections on. The default vendor daemon port is typically 27001.

A default administration account for MobileFirst Server is created during pattern deployment.

- 4. Optional: Configure MobileFirst Server runtime deployment. You can skip this step if you want to specify the context root name for the runtime later during the pattern deployment configuration phase in step 9. To specify the context root name now, complete these steps:
  - In the MobileFirst Platform Server node, click the MFP Server Runtime Deployment component. The
    properties of the selected component are displayed next to the canvas.
  - Next to the runtime\_contextRoot field, click the Delete button to clear the pattern level parameter setting.
  - In the **runtime\_contextRoot** field, specify the runtime context root name. Note that the context root name must start with a forward slash, /; for example, /HelloWorld.
- 5. Upload application and adapter artifacts:

**Important:** When specifying the Target path for applications and adapters, make sure all the applications and adapters are placed in the same directory. For example, if one target path is /opt/tmp/deploy/HelloWorld-common.json, all the other target paths should be /opt/tmp/deploy/\*.

- In the MobileFirst Platform Server node, click the MFP Server Application or MFP Server Adapter component. The properties of the selected component are displayed next to the canvas.
- In the Additional file field, click the Browse button to locate and upload the application or adapter artifact.
- In the **Target path** field, specify the full path for storing the artifact including its file name; for example, /opt/tmp/deploy/HelloWorld-common.json.
- If no application or adapter is to be deployed in the pattern, remove the relevant component by clicking the X button inside it. To get an empty MobileFirst Operations Console deployed without any app or adapter installed, remove the MFP Server Application Adapter Deployment component by clicking the X button inside it.
- 6. Optional: Add more application or adapter artifacts for deployment:
  - From the Assets toolbar, expand Software Components, and then drag and drop an Additional file component onto the MobileFirst Paltform Server node in the canvas. Rename it MobileFirst App\_X or MobileFirst Adatper\_X (where X stands for a unique number for differentiation).
  - Hover the cursor over the newly added App or Adapter component, and then click the Move Up and Move
     Down buttons to adjust its sequence in the node. Make sure it is placed after the MFP Runtime
     Deployment component but before the MFP Server Application Adapter Deployment component.
  - Click the newly added application or adapter component. The properties of the selected component are displayed next to the canvas. Upload the application or adapter artifact and specify its target path by referring to the steps in step 6.
  - Repeat step 7 to add more applications and adapters for deployment.
- 7. Optional: Configure application and adapter deployment to MobileFirst Server. You can skip this step if you want to specify the user credential with deployment privilege later during the pattern deployment configuration phase in step 9. If you have specified the default admin user credential in step 3, you can now specify the deployer user, which must align with the admin user credential:
  - In the MobileFirst Platform Server node, select the **MFP Server Application Adapter Deployment** component. The properties of the selected component are displayed next to the canvas.
  - Find the parameters named **deployer\_user** and **deployer\_password**, and then click the adjacent Delete buttons to clear the pattern level parameter settings.
  - In the deployer\_user and deployer\_password fields, specify the user name and password.
- 8. Configure base scaling policy:
  - o In the IBM PureApplication System dashboard, click Patterns → Virtual System Patterns.
  - On the **Virtual System Patterns** page, use the Search field to find the pattern you created, and then select the pattern.
  - In the toolbar above the panel displaying detailed information about the pattern, click the **Deploy** button.
  - In the **Deploy Pattern** window, in the **Configure** panel, select the correct **Environment Profile** and other IBM PureApplication System environment parameters by consulting your IBM PureApplication System administrator.
  - In the middle column, click Pattern attributes to set attributes such as user name and passwords.
     Supply the following information in the fields provided:

**Note:** Make appropriate changes to the default values of the pattern-level parameters even if an external LDAP server is configured. If you configure administration security by using an LDAP server, you need to supply additional LDAP information. For more information, see Configuring MobileFirst administration security with an external LDAP repository.

#### WebSphere administrative user name

Admin user ID for WebSphere administration console login. Default value: virtuser.

#### WebSphere administrative password

Admin user password for WebSphere administration console login. Default value: passw0rd.

#### admin user

Not visible if configured in step 3. Create a default MobileFirst Server administrator account. Default value: demo.

#### admin\_password

Not visible if configured in step 3. Default admin account password. Default value: demo.

#### **ACTIVATE TOKEN LICENSE**

Not visible if configured in step 3. Select this field to license your pattern with token licensing. Leave this field clear if you use perpetual licenses.

#### LICENSE SERVER HOSTNAME

Not visible if configured in step 3. If you use token licensing to license IBM MobileFirst Platform Foundation, enter the fully-qualified hostname or IP address of your Rational License Key Server IP address. Otherwise, leave this field blank.

#### LMGRD PORT

Not visible if configured in step 3. If you use token licensing to license IBM MobileFirst Platform Foundation, enter the port number that the license manager daemon (Imrgd) listens for connections on. Otherwise, leave this field blank. The default license manager daemon port is 27000.

#### **IBMRATL PORT**

Not visible if configured in step 3. If you use token licensing to license IBM MobileFirst Platform Foundation, enter the port number that the vendor daemon (ibmratl) listens for connections on. Otherwise, leave this field blank. The default vendor daemon port is typically 27001.

#### runtime contextRoot

Not visible if configured in step 5. Context root name for the MobileFirst Server runtime. The name must start with "/".

#### deployer\_user

Not visible if configured in step 8. User name for the account with deployment privilege. If an external LDAP server is not configured, you must enter the same value as was specified when creating the default admin user for the administration service, because in this case, the only authorized user for app and adapter deployment is the default admin user.

#### deployer password

Not visible if configured in step 8. User password for the user with deployment privilege.

#### MFP Vms Password(root)

Root password for the MobileFirst Platform Server and MobileFirst Platform DB nodes. Default value: passw0rd.

#### MFP DB Password(Instance owner)

Instance owner password for the MobileFirst Platform DB node. Default value: passw0rd.

#### Important restriction:

When you set these attrbutes, do not change the following attributes in the MobileFirst Platform Server section:

■ Cell name

- Node name
- Profile name

If you change any of these attributes, your pattern deployment will fail.

- Click Quick Deploy to launch your pattern deployment. After a few seconds, a message is displayed to indicate that the pattern has started to launch. You can click the URL provided in the message to track your pattern deployment status or go to Patterns → Virtual System Instances to open the Virtual System Instances page and search for your pattern there.
- 9. Access the MobileFirst Operations Console:
  - Click Patterns → Virtual System Instances to open the Virtual System Instances page and search for your pattern there. Make sure it is in Running state.
  - Select the pattern name and expand the Virtual machine perspective option in the panel displaying details of the selected instance.
  - Find the MobileFirst Server VM that has a name similar to MobileFirst\_Platform\_Server. and make a
    note of its Public IP address: you need this information in the following step.
  - In the browser, open the MobileFirst Operations Console by composing its URL with one of the following formats:
    - http://{MFP Server VM Public IP}:9080/mfpconsole
    - https://{MFP Server VM Public IP}:9443/mfpconsole
  - Log in to the Console with admin user and password specified in step 3 or step 9.

# Deploying MobileFirst Server on a multiple-node WebSphere Application Server full profile server

You use a predefined template to deploy MobileFirst Server on a multiple-node WebSphere Application Server full profile server.

This procedure involves uploading certain artifacts to IBM PureApplication System such as the required application and adapter. Before you begin, ensure that the artifacts are available for upload.

**Token licensing requirements:** If you use token licensing to license IBM MobileFirst Foundation, review the requirements outlined in Token licensing requirements for IBM MobileFirst Foundation System Pattern before you continue. The deployment of this pattern fails if the license key server cannot be contacted or if insufficient license tokens are available.

Some parameters of script packages in the template have been configured with the recommended values and are not mentioned in this section. For fine-tuning purposes, see more information about all the parameters of script packages in Script packages for MobileFirst Server.

For more information about the composition and configuration options of the predefined template that is used in this procedure, see MobileFirst Platform (WAS server farm) template.

- 1. Create a pattern from the predefined template:
  - In the IBM PureApplication System dashboard, click Patterns → Virtual System Patterns. The Virtual System Patterns page opens.
  - On the Virtual System Patterns page, click Create New, and then in the pop-up window, select
     MobileFirst Platform (WAS server farm) from the list of predefined templates. If the name is only
     partially visible due to its length, you can confirm that the correct template is selected by viewing its
     description on the More information tab.
  - In the **Name** field, provide a name for the pattern.
  - In the **Version** field, specify the version number of the pattern.
  - Click Start Building.
- 2. Mandatory for AIX: In IBM PureApplication System running on Power, the MobileFirst Platform DB node needs to use the AIX-specific add-on component "Default AIX add disk" to replace the "Default add disk" component in the template to support the ifs2 file system:

- In the Pattern Builder, select the MobileFirst Platform DB node.
- Click the **Add a Component Add-on** button (the button is visible above the component box when you hover the cursor over the **MobileFirst Platform DB** node).
- From the Add Add-ons list, select Default AIX add disk. The component is added as the lowest component of the MobileFirst Platform DB node.
- Select the **Default AIX add disk** component and specify the following attributes:
  - DISK\_SIZE\_GB: Storage size (measured in GB) to be extended to the DB server. Example value:
    10.
  - FILESYSTEM\_TYPE: Supported file system in AIX. Default value: jfs2.
  - MOUNT\_POINT: Align with the attribute Mount point for instance owner in the Database Server component in the MobileFirst Platform DB node. Example value: /dbinst.
  - **VOLUME\_GROUP:** Example value: **group1**. Contact your IBM PureApplication System administrator for the correct value.
- In the MobileFirst Platform DB node, select the **Default add disk** component, and then click the bin icon to delete it.
- o Save the pattern.
- 3. Optional: Configure MobileFirst Server administration. You can skip this step if you want to specify the user credential with MobileFirst Server administration privilege later during the pattern deployment configuration phase in step 9. To specify it now, complete these steps:

**Note:** If you want to configure administration security with an LDAP server, you need to supply additional LDAP information. For more information, see Configuring MobileFirst administration security with an external LDAP repository.

- In the MobileFirst Platform Server node, click the MFP Server Administration component.
   The properties of the selected component are displayed next to the canvas.
- Next to the admin\_user and admin\_password fields, click the Delete button to clear their pattern level parameter settings.
- In the **admin\_user** and **admin\_password** fields, specify the administration user name and password.
- If you use token licensing to license IBM MobileFirst Platform Foundation, complete the following fields. If you do not use token licensing, leave these fields blank.

ACTIVATE TOKEN LICENSE: Select this field to license your pattern with token licensing.

**LICENSE\_SERVER\_HOSTNAME**: Enter the fully qualified host name or IP address of your Rational License Key Server.

**LMGRD\_PORT**: Enter the port number that the license manager daemon (**Imrgd**) listens for connections on. The default license manager daemon port is 27000.

**IBMRATL\_PORT**:Enter the port number that the vendor daemon (**ibmratl**) listens for connections on. The default vendor daemon port is typically 27001.

A default administration account for MobileFirst Server is created during pattern deployment.

- 4. Optional: Configure MobileFirst Server runtime deployment. You can skip this step if you want to specify the context root name for the runtime later during the pattern deployment configuration phase in step 10. To specify the context root name now, complete these steps:
  - In the MobileFirst Platform Server node, click the **MFP Server Runtime Deployment** component. The properties of the selected component are displayed next to the canvas.
  - Next to the runtime\_contextRoot field, click the Delete button to clear the pattern level parameter setting.
  - In the **runtime\_contextRoot** field, specify the runtime context root name. Note that the context root name must start with a forward slash, /; for example, /HelloWorld.

5. Upload application and adapter artifacts:

**Important:** When specifying the Target path for applications and adapters, make sure all the applications and adapters are placed in the same directory. For example, if one target path is /opt/tmp/deploy/HelloWorld-common.json, all the other target paths should be /opt/tmp/deploy/\*.

- In the MobileFirst Platform Server node, click the MFP Server Application or MFP Server Adapter component. The properties of the selected component are displayed next to the canvas.
- In the Additional file field, click the Browse button to locate and upload the application or adapter artifact.
- In the **Target path** field, specify the full path for storing the artifact including its file name; for example, /opt/tmp/deploy/HelloWorld-common.json.
- If no application or adapter is to be deployed in the pattern, remove the relevant component by clicking the X button inside it. To get an empty MobileFirst Operations Console deployed without any app or adapter installed, remove the MFP Server Application Adapter Deployment component by clicking the X button inside it.
- 6. Optional: Add more application or adapter artifacts for deployment:
  - From the Assets toolbar, expand Software Components, and then drag and drop an Additional file component onto the MobileFirst Paltform Server node in the canvas. Rename it MobileFirst App\_X or MobileFirst Adatper\_X (where X stands for a unique number for differentiation).
  - Hover the cursor over the newly added App or Adapter component, and then click the Move Up and Move
     Down buttons to adjust its sequence in the node. Make sure it is placed after the MFP Runtime
     Deployment component but before the MFP Server Application Adapter Deployment component.
  - Click the newly added application or adapter component. The properties of the selected component are displayed next to the canvas. Upload the application or adapter artifact and specify its target path by referring to the steps in step 6.
  - Repeat step 7 to add more applications and adapters for deployment.
- 7. Optional: Configure application and adapter deployment to MobileFirst Server. You can skip this step if you want to specify the user credential with deployment privilege later during the pattern deployment configuration phase in step 10. If you have specified the default admin user credential in step 3, you can now specify the deployer user, which must align with the admin user credential:
  - In the MobileFirst Platform Server node, select the **MFP Server Application Adapter Deployment** component. The properties of the selected component are displayed next to the canvas.
  - Find the parameters named deployer\_user and deployer\_password, and then click the adjacent Delete buttons to clear the pattern level parameter settings.
  - In the **deployer\_user** and **deployer\_password** fields, specify the user name and password.
- 8. Configure base scaling policy:
  - In the **MobileFirst Platform Server** node, select the **Base Scaling Policy** component. The properties of the selected component are displayed next to the canvas.
  - In the Number of Instances field, specify the number of server nodes to be instantiated during pattern deployment. The default value is 2 in the predefined template. Because dynamic scaling is not supported in this release, do not specify values in the remaining attribute fields.
- 9. Configure and launch the pattern deployment:
  - In the IBM PureApplication System dashboard, click Patterns → Virtual System Patterns.
  - On the Virtual System Patterns page, use the **Search** field to find the pattern you created, and then select the pattern.

- In the toolbar above the panel displaying detailed information about the pattern, click the Deploy button.
- In the Deploy Pattern window, in the Configure panel, select the correct environment profile from the
   Environment Profile list, and provide other IBM PureApplication System environment parameters. To
   obtain the correct information, consult your IBM PureApplication System administrator.
- In the middle column, click **Pattern attributes** to display attributes such as user names and passwords.
   Supply the following information in the fields provided:

**Note:** Make appropriate changes to the default values of the pattern-level parameters even if an external LDAP server is configured. If you configure administration security by using an LDAP server, you need to supply additional LDAP information. For more information, see Configuring MobileFirst administration security with an external LDAP repository.

#### runtime contextRoot list

Context root names of the MobileFirst Server runtimes in case multiple runtimes exist. Use a semicolon, ";" to separate each runtime context root; for example, **HelloMobileFirst;HelloWorld**.

**Important:** runtime\_contextRoot\_list must align with the context root specified in the MFP Server Runtime Deployment node; otherwise, IHS will not be able to correctly route requests that contain the runtime context root.

#### WebSphere administrative user name

Admin user ID for WebSphere administration console login. Default value: virtuser.

#### WebSphere administrative password

Admin user password for WebSphere administration console login. Default value: passw0rd.

#### admin user

Not visible if configured in step 3. Create a default MobileFirst Server administrator account. Default value: demo.

#### admin\_password

Not visible if configured in step 3. Default admin account password. Default value: demo.

#### ACTIVATE\_TOKEN\_LICENSE

Not visible if configured in step 3. Select this field to license your pattern with token licensing. Leave this field clear if you use perpetual licenses.

#### LICENSE SERVER HOSTNAME

Not visible if configured in step 3. If you use token licensing to license IBM MobileFirst Platform Foundation, enter the fully-qualified hostname or IP address of your Rational License Key Server IP address. Otherwise, leave this field blank.

#### LMGRD PORT

Not visible if configured in step 3. If you use token licensing to license IBM MobileFirst Platform Foundation, enter the port number that the license manager daemon (Imrgd) listens for connections on. Otherwise, leave this field blank. The default license manager daemon port is 27000.

#### **IBMRATL PORT**

Not visible if configured in step 3. If you use token licensing to license IBM MobileFirst Platform Foundation, enter the port number that the vendor daemon (ibmratl) listens for connections on. Otherwise, leave this field blank. The default vendor daemon port is typically 27001.

#### runtime\_contextRoot

Not visible if configured in step 5. Context root name for the MobileFirst Server runtime. The name must start with "/".

#### deployer user

Not visible if configured in step 8. User name for the account with deployment privilege. If an external LDAP server is not configured, you must enter the same value as was specified when creating the default

admin user for the administration service, because in this case, the only authorized user for app and adapter deployment is the default admin user.

#### deployer\_password

Not visible if configured in step 8. User password for the user with deployment privilege.

#### MFP Vms Password(root)

Root password for the MobileFirst Platform Server and MobileFirst Platform DB nodes. Default value: passw0rd.

#### MFP DB Password(Instance owner)

Instance owner password for the MobileFirst Platform DB node. Default value: passw0rd.

Click Quick Deploy to launch your pattern deployment. After a few seconds, a message is displayed to
indicate that the pattern has started to launch. You can click the URL provided in the message to track
your pattern deployment status or go to Patterns → Virtual System Instances to open the Virtual System
Instances page and search for your pattern there.

If you use token licensing to licenseIBM MobileFirst Platform Foundation, your pattern will fail to deploy if insufficient license tokens are available or if the license key server IP address and port were entered incorrectly.

- 10. Access the MobileFirst Operations Console:
  - Click Patterns → Virtual System Instances to open the Virtual System Instances page and search for your pattern there. Make sure it is in Running state.
  - Select the pattern name and expand the Virtual machine perspective option in the panel displaying details of the selected instance.
  - Find the IHS Server VM that has a name similar to **IHS\_Server.**\* and make a note of its Public IP address: you need this information in the following step.
  - In the browser, open the MobileFirst Operations Console by composing its URL with one of the following formats:
    - http://{IHS Server VM Public IP}/mfpconsole
    - https://{IHS Server VM Public IP}/mfpconsole
  - Log in to the Console with the admin user ID and password specified in step 3 or step 10.

### Deploying MobileFirst Server on clusters of WebSphere Application Server Network Deployment servers

You can use a predefined template to deploy MobileFirst Server on clusters of WebSphere Application Server Network Deployment servers. This application pattern template does not support token licensing.

This procedure involves uploading certain artifacts to IBM PureApplication System such as the required application and adapter. Before you begin, ensure that the artifacts are available for upload.

If you are running the System Monitoring for WebSphere Application Server shared service, the MobileFirst runtime environment might fail to start correctly when you deploy the pattern. If possible, stop the shared service before you continue with this procedure. If you cannot stop the shared service, you might need to restart the IBM MobileFirst Foundation runtime from the WebSphere Application Server administrative console to fix the problem. For more information, see MobileFirst runtime synchronization limitation with WebSphere Application Server Network Deployment

**Important token licensing restriction:** This pattern template does not support token licensing. You must be using perpetual licensing when you deploy patterns based on the MobileFirst Platform (WAS ND) pattern template.

Some parameters of script packages in the template are configured with recommended values and are not covered in this topic. For fine-tuning purposes, see more information about all the parameters of script packages in Script packages for MobileFirst Server.

For more information about the composition and configuration options of the predefined template that is used in this procedure, see MobileFirst Platform (WAS ND) template.

1. Create a pattern from the predefined template:

- In the IBM PureApplication System dashboard, click Patterns → Virtual System Patterns. The Virtual System Patterns page opens.
- On the Virtual System Patterns page, click Create New, and then in the pop-up window, select
   MobileFirst Platform (WAS ND) from the list of predefined templates. If the name is only partially visible
   due to its length, you can confirm that the correct template is selected by viewing its description on the
   More information tab.
- In the **Name** field, provide a name for the pattern.
- In the **Version** field, specify the version number of the pattern.
- Click Start Building.
- 2. Mandatory for AIX: In IBM PureApplication System running on Power, the MobileFirst Platform DB node needs to use the AIX-specific add-on component "Default AIX add disk" to replace the "Default add disk" component in the template to support the jfs2 file system:
  - In the Pattern Builder, select the MobileFirst Platform DB node.
  - Click the Add a Component Add-on button (the button is visible above the component box when you
    hover the cursor over the MobileFirst Platform DB node).
  - From the Add Add-ons list, select Default AIX add disk. The component is added as the lowest component of the MobileFirst Platform DB node.
  - Select the **Default AIX add disk** component and specify the following attributes:
    - DISK\_SIZE\_GB: Storage size (measured in GB) to be extended to the DB server. Example value:
      10.
    - FILESYSTEM\_TYPE: Supported file system in AIX. Default value: jfs2.
    - MOUNT\_POINT: Align with the attribute Mount point for instance owner in the Database Server component in the MobileFirst Platform DB node. Example value: /dbinst.
    - **VOLUME\_GROUP:** Example value: **group1**. Contact your IBM PureApplication System administrator for the correct value.
  - In the MobileFirst Platform DB node, select the **Default add disk** component, and then click the bin icon to delete it.
  - Save the pattern.
- 3. Optional: Configure MobileFirst Server administration. You can skip this step if you want to specify the user credential with MobileFirst Server administration privilege later during the pattern deployment configuration phase in step 9. To specify it now, complete these steps:

**Note:** If you want to configure administration security with an LDAP server, you need to supply additional LDAP information. For more information, see Configuring MobileFirst administration security with an external LDAP repository.

- In the MobileFirst Platform Server node, click the **MFP Server Administration** component. The properties of the selected component are displayed next to the canvas.
- Next to the admin\_user and admin\_password fields, click the Delete button to clear their pattern level parameter settings.
- In the admin\_user and admin\_password fields, specify the administration user name and password.
- If you use token licensing to license IBM MobileFirst Platform Foundation, complete the following fields. If you do not use token licensing, leave these fields blank.

**ACTIVATE\_TOKEN\_LICENSE**: Select this field to license your pattern with token licensing. **LICENSE\_SERVER\_HOSTNAME**: Enter the fully qualified host name or IP address of your Rational License Key Server.

LMGRD PORT: Enter the port number that the license manager daemon (Imrgd) listens for connections on. The

default license manager daemon port is 27000.

**IBMRATL\_PORT**:Enter the port number that the vendor daemon (**ibmratl**) listens for connections on. The default vendor daemon port is typically 27001.

A default administration account for MobileFirst Server is created during pattern deployment.

- 4. Optional: Configure MobileFirst Server runtime deployment. You can skip this step if you want to specify the context root name for the runtime later during the pattern deployment configuration phase in step 10. To specify the context root name now, complete these steps:
  - In the MobileFirst Platform Server node, click the **MFP Server Runtime Deployment** component. The properties of the selected component are displayed next to the canvas.
  - Next to the runtime\_contextRoot field, click the Delete button to clear the pattern level parameter setting.
  - In the **runtime\_contextRoot** field, specify the runtime context root name. Note that the context root name must start with a forward slash, /; for example, /HelloWorld.
- 5. Optional: Adjust the number of application server nodes in your WebSphere Application Server Network Deployment clusters for the MobileFirst Administration component and the MobileFirst runtime environment. By default, the Administration component and runtime environment each have two application server nodes in their respective clusters.
  - In the DmgrNode node, click the **MFP Server Administration** component. The properties of the component are displayed next to the canvas.
  - In the NUMBER\_OF\_CLUSTERMEMBERS field, specify the number of application server nodes that you
    want in your WebSphere Application Server Network Deployment cluster for the MobileFirst Administration
    component.
  - In the DmgrNode node, click the **MFP Server Runtime Deployment** component. The properties of the component are displayed next to the canvas.
  - In the NUMBER\_OF\_CLUSTERMEMBERS field, specify the number of application server nodes that you
    want in your WebSphere Application Server Network Deployment cluster for the MobileFirst runtime
    environment.
  - In the CustomNode node, click the **Base Scaling Policy** component.
  - Adjust the Number of Instances value to account for the total number of application server nodes that you
    entered in the NUMBER\_OF\_CLUSTERMEMBERS field for each component. The minimum value for
    Number of Instances is the total number of server nodes for the MobileFirst Administration component
    and the MobileFirst runtime environments.

For example, the default value for **Number of Instances** is 4 for the default topology with two nodes for the administration component and two nodes for the runtime environment. If you change **NUMBER\_OF\_CLUSTERMEMBERS** values for the administration component to 3 and for the runtime environment to 5, the minimum value for Number of Instances is 8.

6. Upload application and adapter artifacts:

**Important:** When specifying the Target path for applications and adapters, make sure all the applications and adapters are placed in the same directory. For example, if one target path is /opt/tmp/deploy/HelloWorld-common.json, all the other target paths should be /opt/tmp/deploy/\*.

- In the MobileFirst Platform Server node, click the MFP Server Application or MFP Server Adapter component. The properties of the selected component are displayed next to the canvas.
- In the Additional file field, click the Browse button to locate and upload the application or adapter artifact.
- In the **Target path** field, specify the full path for storing the artifact including its file name; for example, /opt/tmp/deploy/HelloWorld-common.json.
- If no application or adapter is to be deployed in the pattern, remove the relevant component by clicking the X button inside it. To get an empty MobileFirst Operations Console deployed without any app or adapter installed, remove the MFP Server Application Adapter Deployment component by clicking the X button inside it.
- 7. Optional: Add more application or adapter artifacts for deployment:
  - From the Components toolbar, expand Software Components, and then drag and drop an Additional
    file component onto the MobileFirst Paltform Server node in the canvas. Rename it MobileFirst App\_X or
    MobileFirst Adatper\_X (where X stands for a unique number for differentiation).
  - Hover the cursor over the newly added App or Adapter component, and then click the Move Up and Move
     Down buttons to adjust its sequence in the node. Make sure it is placed after the MFP Runtime
     Deployment component but before the MFP Server Application Adapter Deployment component.
  - Click the newly added application or adapter component. The properties of the selected component are displayed next to the canvas. Upload the application or adapter artifact and specify its target path by referring to the steps in step 6.
  - In the **Additional file \*\*field, click the \*\*Browse** button to locate and upload the application or adapter artifact.
  - In the **Target path** field, specify the full path for storing the artifact, including its file name. For example, /opt/tmp/deploy/HelloWorld-common.wlapp.

Repeat this step if you want to add more applications and adapters for deployment.

- 8. Optional: Configure application and adapter deployment to MobileFirst Server. You can skip this step if you want to specify the user credential with deployment privilege later during the pattern deployment configuration phase in step 10. If you have specified the default admin user credential in step 3, you can now specify the deployer user, which must align with the admin user credential:
  - In the MobileFirst Platform Server node, select the **MFP Server Application Adapter Deployment** component. The properties of the selected component are displayed next to the canvas.
  - Find the parameters named **deployer\_user** and **deployer\_password**, and then click the adjacent Delete buttons to clear the pattern level parameter settings.
  - o In the deployer user and deployer password fields, specify the user name and password.
- 9. Configure base scaling policy:
  - In the IBM PureApplication System dashboard, click Patterns → Virtual System Patterns.
  - On the **Virtual System Patterns** page, use the Search field to find the pattern you created, and then select the pattern.
  - In the toolbar above the panel displaying detailed information about the pattern, click the **Deploy** button.
  - In the Deploy Pattern window, in the Configure panel, select the correct Environment Profile and other IBM PureApplication System environment parameters by consulting your IBM PureApplication System

administrator.

In the middle column, click **Pattern attributes** to set attributes such as user name and passwords.
 Supply the following information in the fields provided:

**Note:** Make appropriate changes to the default values of the pattern-level parameters even if an external LDAP server is configured. If you configure administration security by using an LDAP server, you need to supply additional LDAP information. For more information, see Configuring MobileFirst administration security with an external LDAP repository.

#### WebSphere administrative user name

Admin user ID for WebSphere administration console login. Default value: virtuser.

#### WebSphere administrative password

Admin user password for WebSphere administration console login. Default value: passw0rd.

#### admin user

Not visible if configured in step 3. Create a default MobileFirst Server administrator account. Default value: demo.

#### admin password

Not visible if configured in step 3. Default admin account password. Default value: demo.

#### **ACTIVATE TOKEN LICENSE**

Not visible if configured in step 3. Select this field to license your pattern with token licensing. Leave this field clear if you use perpetual licenses.

#### LICENSE SERVER HOSTNAME

Not visible if configured in step 3. If you use token licensing to license IBM MobileFirst Platform Foundation, enter the fully-qualified hostname or IP address of your Rational License Key Server IP address. Otherwise, leave this field blank.

#### LMGRD PORT

Not visible if configured in step 3. If you use token licensing to license IBM MobileFirst Platform Foundation, enter the port number that the license manager daemon (Imrgd) listens for connections on. Otherwise, leave this field blank. The default license manager daemon port is 27000.

#### **IBMRATL PORT**

Not visible if configured in step 3. If you use token licensing to license IBM MobileFirst Platform Foundation, enter the port number that the vendor daemon (ibmratl) listens for connections on. Otherwise, leave this field blank. The default vendor daemon port is typically 27001.

#### runtime\_contextRoot

Not visible if configured in step 5. Context root name for the MobileFirst Server runtime. The name must start with "/".

#### deployer\_user

Not visible if configured in step 8. User name for the account with deployment privilege. If an external LDAP server is not configured, you must enter the same value as was specified when creating the default admin user for the administration service, because in this case, the only authorized user for app and adapter deployment is the default admin user.

#### deployer\_password

Not visible if configured in step 8. User password for the user with deployment privilege.

#### MFP Vms Password(root)

Root password for the MobileFirst Platform Server and MobileFirst Platform DB nodes. Default value: passw0rd.

#### MFP VMs Password(virtuser)

Password for the virtuser user of the DmgrNode, CustomNode, IHSNode and MobileFirst Platform DB nodes. Default value: passw0rd.

#### Open firewall ports for WAS

The WebSphere Application Server nodes that are deployed in the CustomNode VM nodes require open firewall ports to connect to the database server and the LDAP server (if configured for LDAP). If you need to specify multiple port numbers, separate the port numbers with a semicolon (;). For example, 50000;636The default value is 50000 (the default port for DB2 server).

#### Important restriction:

When you set these attrbutes, do not change the following attributes in the MobileFirst Platform Server section:

- Cell name
- Node name
- Profile name

If you change any of these attributes, your pattern deployment will fail.

- Click Quick Deploy to launch your pattern deployment. After a few seconds, a message is displayed to indicate that the pattern has started to launch. You can click the URL provided in the message to track your pattern deployment status or go to Patterns → Virtual System Instances to open the Virtual System Instances page and search for your pattern there.
- 10. Access the MobileFirst Operations Console:
  - Click Patterns → Virtual System Instances to open the Virtual System Instances page and search for your pattern there. Make sure it is in Running state.
  - Select the pattern name and expand the Virtual machine perspective option in the panel displaying details of the selected instance.
  - Find the MobileFirst Server VM that has a name similar to **MobileFirst\_Platform\_Server.** and make a note of its Public IP address: you need this information in the following step.
  - In the browser, open the MobileFirst Operations Console by composing its URL with one of the following formats:
    - http://{MFP Server VM Public IP}:9080/mfpconsole
    - https://{MFP Server VM Public IP}:9443/mfpconsole
  - Log in to the Console with admin user and password specified in step 3 or step 9.

If the console does not display the MobileFirst runtimes, restart the IBM MobileFirst Platform runtime node from the WebSphere Application Server administrative console. For instructions about restarting the runtime node from the administrative console, see Restarting the IBM MobileFirst Platform runtime from the WebSphere Application Server administrative console.

### MobileFirst runtime synchronization limitation with WebSphere Application Server Network Deployment

If you deploy a PureApplication pattern based on the **MobileFirst Platform (WAS ND)** template and run the System Monitoring for WebSphere Application Server shared service, the MobileFirst runtime environment might fail to start correctly, when you deploy the pattern.

A PureApplication virtual system pattern based on the **MobileFirst Platform (WAS ND)** template deploys the MobileFirst administration service and the IBM MobileFirst Foundation runtime into different WebSphere Application Server Network Deployment clusters. For the IBM MobileFirst Platform runtime to work correctly, it must be started after the MobileFirst administration service. If the IBM MobileFirst Platform runtime starts first, the runtime service fails to detect the MobileFirst administration service, which causes errors in the runtime service.

When the deployment of a PureApplication pattern is almost complete, the System Monitoring for WebSphere Application Server shared service restarts all of the WebSphere Application Server nodes that are deployed from the pattern. The nodes restart in a random order, so the nodes that contain the IBM MobileFirst Platform runtime might be restarted before the nodes that contain the MobileFirst administration service.

You must stop the System Monitoring for WebSphere Application Server shared service before you deploy the pattern. If you cannot stop the shared service, you might need to restart the IBM MobileFirst Platform runtime from the WebSphere Application Server administrative console to fix the problem.

### Restarting the IBM MobileFirst Platform runtime from the WebSphere Application Server administrative console

If your MobileFirst Operations Console is empty after you deploy a PureApplication System pattern based on the MobileFirst Platform (WAS ND) template, you might need to restart the IBM MobileFirst runtime from the WebSphere Application Server administrative console.

This procedure applies only when you are deploying PureApplication virtual system patterns based on the **MobileFirst Platform (WAS ND)** template when you are running the System Monitoring for WebSphere Application Server shared service. If you do not use this shared service or are deploying a pattern based on a different template, this procedure does not apply to you.

You must deploy your pattern before you do this procedure.

To work correctly, the MobileFirst administration service nodes must be started before the IBM MobileFirst Platform runtime nodes. If the System Monitoring for WebSphere Application Server shared service is running when you deploy a pattern, the shared service restarts all of the WebSphere Application Server nodes that are deployed from the pattern. The nodes restart in a random order, which means that the IBM MobileFirst Platform runtime nodes might be started before the MobileFirst administration service nodes.

- 1. Confirm that the System Monitoring for WebSphere Application Server shared service is deployed and running:
  - In the PureApplication System dashboard, click Patterns and then under Pattern Instances, click Shared Services.

**Important:** Shared Services appears twice in the **Patterns** menu, ensure that you click **Shared Services** under **Pattern Instances** and not under Patterns.

- On the Shared Service Instances page, look for a name that starts with System Monitoring for WebSphere Application Server. Click that name to expand its entry
  - If you do not see an entry for **System Monitoring for WebSphere Application Server**, the System Monitoring for WebSphere Application Server shared service is not deployed and you do not need to continue with this procedure.
- Check the Status column for the service.
  - If **Status** says Stopped, the System Monitoring for WebSphere Application Server shared service is stopped and you do not need to continue with this procedure.
  - If **Status** says Started, the System Monitoring for WebSphere Application Server shared service is running. Continue with the rest of this procedure.
- 2. Confirm that your pattern is running, and access the MobileFirst Operations Console from the PureApplication System dashboard.
  - For instructions about how access the MobileFirst Operations Console from the PureApplication System dashboard, see step 10 in Deploying MobileFirst Server on clusters of WebSphere Application Server Network Deployment servers.
- 3. If the console appears empty or is otherwise not displaying MobileFirst runtimes, restart the IBM MobileFirst Platform runtime node from the WebSphere Application Server administrative console:
  - In the PureApplication System dashboard, click Patterns → Virtual System Instances.
  - On the **Virtual System Instances** page, find your pattern instance and confirm that it is running. If it is not running, start the pattern instance.
  - Click the name of your pattern instance and in the details panel, find the Virtual machine perspective section.
  - In the Virtual machine perspective section, find the virtual machine whose name starts with DmgrNode and note its public IP address.

Open the WebSphere Application Server administrative console at the following URL:

https://{DmgrNode VM public IP address}:9043/ibm/console

Use the user ID and password that you specified for the WebSphere Application Server administrative console when you deployed the pattern.

- In the WebSphere Application Server administrative console, expand Applications and click All applications.
- Restart the IBM MobileFirst Platform runtime:
  - In the list of applications, select the application with name that begins with IBM\_Worklight\_project\_runtime\_MFP.
  - In the **Action** column, select **Stop**.
  - Click Submit Action.
  - Wait until the application status in the Status column shows the stopped icon.
  - In the Action column, select Start.
  - Click Submit Action.

Repeat this step for each IBM MobileFirst Platform runtime application in the list.

4. Access the MobileFirst Operations Console again and confirm that your IBM MobileFirst Platform runtimes are now visible.

# Deploying MobileFirst Application Center on a single-node WebSphere Application Server Liberty profile server

You use a predefined template to deploy MobileFirst Application Center on a single-node WebSphere Application Server Liberty profile server.

This procedure involves uploading certain artifacts to IBM PureApplication System such as the required application and adapter. Before you begin, ensure that the artifacts are available for upload.

**Token licensing requirements:** If you use token licensing to license IBM MobileFirst Foundation, review the requirements that are outlined in Token licensing requirements for IBM MobileFirst Foundation System Pattern before you continue. If the license key server cannot be contacted or if insufficient license tokens are available then the deployment of this pattern fails.

Some parameters of script packages in the template is configured with the recommended values and are not mentioned here. For fine-tuning purposes, see more information about all the parameters of script packages in Script packages for MobileFirst Server.

For more information about the composition and configuration options of the predefined template that is used in this procedure, see MobileFirst Platform Application Center (Liberty single node) template.

- 1. Create a pattern from the predefined template:
  - In the IBM PureApplication System dashboard, click Patterns → Virtual System Patterns. The Virtual System Patterns page opens.
  - On the Virtual System Patterns page, click Create New, and then in the pop-up window, select
     MobileFirst Platform (AppCenter Liberty single node) from the list of predefined templates. If the name
     is only partially visible due to its length, you can confirm that the correct template is selected by viewing its
     description on the More information tab.
  - In the Name field, provide a name for the pattern.
  - In the **Version** field, specify the version number of the pattern.
  - · Click Start Building.
- 2. Mandatory for AIX: In IBM PureApplication System running on Power, the MobileFirst Platform DB node needs to use the AIX-specific add-on component "Default AIX add disk" to replace the "Default add disk" component in the template to support the jfs2 file system:
  - In the Pattern Builder, select the MobileFirst Platform DB node.

- Click the **Add a Component Add-on** button (the button is visible above the component box when you hover the cursor over the **MobileFirst Platform DB** node).
- From the Add Add-ons list, select Default AIX add disk. The component is added as the lowest component of the MobileFirst Platform DB node.
- Select the **Default AIX add disk** component and specify the following attributes:
  - **DISK\_SIZE\_GB:** Storage size (measured in GB) to be extended to the DB server. Example value: 10.
  - FILESYSTEM TYPE: Supported file system in AIX. Default value: jfs2.
  - MOUNT\_POINT: Align with the attribute Mount point for instance owner in the Database Server component in the MobileFirst Platform DB node. Example value: /dbinst.
  - **VOLUME\_GROUP:** Example value: **group1**. Contact your IBM PureApplication System administrator for the correct value.
- In the MFP AppCenter DB node, select the **Default add disk** component, and then click the bin icon to delete it.
- o Save the pattern.
- 3. Optional: Configure MFP Server Application Center in the MFP AppCenter Server node.

**Note:** If you want to configure administration security with an LDAP server, you need to supply more LDAP information. For more information, see Configuring MobileFirst administration security with an external LDAP repository.

- In the MFP AppCenter Server node, click the MFP Server Application Center component.

  The properties of the selected component are displayed next to the canvas.
- Next to the admin\_user and admin\_password fields, click the Delete button to clear their pattern level parameter settings.
- In the admin\_user and admin\_password fields, specify the administration user name and password.
- Next to the db\_user and db\_password fields, click the Delete button to clear their pattern level parameter settings.
- In the db\_user and db\_password fields, specify the database user name and password.
- In the db\_name, db\_instance, db\_ip, and db\_port fields, specify the database user name, password, instance name, IP, and port number.

A default administration account for MobileFirst Server is created during pattern deployment.

- 4. Configure and launch the pattern deployment:
  - o In the IBM PureApplication System dashboard, click Patterns → Virtual System Patterns.
  - On the **Virtual System Patterns** page, use the **Search** field to find the pattern you created, and then select the pattern.
  - In the toolbar above the panel that displays the detailed information about the pattern, click the **Deploy** button.
  - In the Deploy Pattern window, in the Configure panel, select the correct environment profile from the Environment Profile list, and provide other IBM PureApplication System environment parameters. To obtain the correct information, consult your IBM PureApplication System administrator.
  - In the middle column, click Pattern attributes to display attributes such as user names and passwords.

Supply the following information in the fields provided:

**Note:** Make appropriate changes to the default values of the pattern-level parameters even if an external LDAP server is configured. If you configure administration security by using an LDAP server, you need to supply additional LDAP information. For more information, see Configuring MobileFirst administration security with an external LDAP repository.

#### admin\_user

Not visible if configured in step 3. Create a default MobileFirst Server administrator account. Default value: demo.

#### admin\_password

Not visible if configured in step 3. Default admin account password. Default value: demo.

#### ACTIVATE\_TOKEN\_LICENSE

Not visible if configured in step 3. Select this field to license your pattern with token licensing. Leave this field clear if you use perpetual licenses.

#### LICENSE SERVER HOSTNAME

Not visible if configured in step 3. If you use token licensing to license IBM MobileFirst Platform Foundation, enter the fully-qualified hostname or IP address of your Rational License Key Server IP address. Otherwise, leave this field blank.

#### LMGRD PORT

Not visible if configured in step 3. If you use token licensing to license IBM MobileFirst Platform Foundation, enter the port number that the license manager daemon (Imrgd) listens for connections on. Otherwise, leave this field blank. The default license manager daemon port is 27000.

#### **IBMRATL PORT**

Not visible if configured in step 3. If you use token licensing to license IBM MobileFirst Platform Foundation, enter the port number that the vendor daemon (ibmratl) listens for connections on. Otherwise, leave this field blank. The default vendor daemon port is typically 27001.

#### runtime contextRoot

Not visible if configured in step 5. Context root name for the MobileFirst Server runtime. The name must start with "/".

#### deployer\_user

Not visible if configured in step 8. User name for the account with deployment privilege. If an external LDAP server is not configured, you must enter the same value as was specified when creating the default admin user for the administration service, because in this case, the only authorized user for app and adapter deployment is the default admin user.

#### deployer password

Not visible if configured in step 8. User password for the user with deployment privilege.

#### MFP Vms Password(root)

Root password for the MobileFirst Platform Server and MobileFirst Platform DB nodes. Default value: passw0rd.

#### MFP DB Password(Instance owner)

Instance owner password for the MobileFirst Platform DB node. Default value: passw0rd.

- \* Click **Quick Deploy** to launch your pattern deployment. After a few seconds, a message is displayed to indicate that the pattern has started to launch. You can click the URL provided in the message to track your pattern deployment status or go to **Patterns → Virtual System Instances** to open the Virtual System Instances page and search for your pattern there.
- 5. To access the MobileFirst Operations Console perform the following steps:
  - Click Patterns → Virtual System Instances to open the Virtual System Instances page and search for your pattern there.
  - Select your pattern name and expand the Virtual machine perspective in the panel that displays the details
    of the selected instance.

- Find the MobileFirst Server VM that has a name similar to **MFP\_AppCenter\_Server.**, make a note of its public IP address.
- In the browser, open the MobileFirst Operations Console by composing its URL with one of the following formats:
  - http://{MFP Server VM Public IP}:9080/appcenterconsole
  - https://{MFP Server VM Public IP}:9443/appcenterconsole
- Log in to the Console with admin user and password specified in step 3.

# Deploying MobileFirst Application Center on a single-node WebSphere Application Server full profile server

You use a predefined template to deploy a single-node MobileFirst Application Center to a WebSphere Application Server full profile server.

This procedure involves uploading certain artifacts to IBM PureApplication System such as the required application and adapter. Before you begin, ensure that the artifacts are available for upload.

**Token licensing requirements:** If you use token licensing to license IBM MobileFirst Foundation, review the requirements outlined in Token licensing requirements for IBM MobileFirst Foundation System Pattern before you continue. The deployment of this pattern fails if the license key server cannot be contacted or if insufficient license tokens are available.

Some parameters of script packages in the template have been configured with the recommended values and are not mentioned in this section. For fine-tuning purposes, see more information about all the parameters of script packages in Script packages for MobileFirst Server.

For more information about the composition and configuration options of the predefined template that is used in this procedure, see MobileFirst Platform Application Center (WAS single node) template.

- 1. Create a pattern from the predefined template:
  - In the IBM PureApplication System dashboard, click Patterns → Virtual System Patterns. The Virtual System Patterns page opens.
  - On the Virtual System Patterns page, click Create New, and then in the pop-up window, select
     MobileFirst Platform (AppCenter Liberty single node) from the list of predefined templates. If the name
     is only partially visible due to its length, you can confirm that the correct template is selected by viewing its
     description on the More information tab.
  - o In the Name field, provide a name for the pattern.
  - In the **Version** field, specify the version number of the pattern.
  - Click Start Building.
- 2. Mandatory for AIX: In IBM PureApplication System running on Power, the MobileFirst Platform DB node needs to use the AIX-specific add-on component "Default AIX add disk" to replace the "Default add disk" component in the template to support the **jfs2** file system:
  - In the Pattern Builder, select the MFP AppCenter DB node.
  - Click the Add a Component Add-on button (the button is visible above the component box when you
    hover the cursor over the MFP AppCenter DB node).
  - From the Add Add-ons list, select **Default AIX** add disk. The component is added as the lowest component of the MobileFirst Platform DB node.
  - Select the **Default AIX** add disk component and specify the following attributes:

#### **DISK SIZE GB**

Storage size (measured in GB) to be extended to the DB server. Following is the example value: 10.

#### FILESYSTEM\_TYPE

Supported file system in AIX. Following is the default value: ifs2.

#### **MOUNT POINT**

Align with the attribute **Mount point for instance owner** in the Database Server component in the MobileFirst Platform DB node. Following is the example value: /dbinst.

#### **VOLUME GROUP**

Following is the example value: **group1**. Contact your IBM PureApplication System administrator for the correct value.

- In the MFP AppCenter DB node, select the Default add disk component, and then click the bin icon to delete it.
- · Save the pattern.
- 3. Optional: Configure MFP Server Application Center in the MFP AppCenter Server node.

**Note:** If you want to configure administration security with an LDAP server, you need to supply more LDAP information. For more information, see Configuring MobileFirst administration security with an external LDAP repository.

- In the **MFP AppCenter Server** node, click the **MFP Server Administration** component. The properties of the selected component are displayed next to the canvas.
- Next to the admin\_user and admin\_password fields, click the Delete button to clear their pattern level parameter settings.
- In the admin\_user and admin\_password fields, specify the administration user name and password.
- If you use token licensing to license IBM MobileFirst Platform Foundation, complete the following fields. If you do not use token licensing, leave these fields blank.

ACTIVATE\_TOKEN\_LICENSE: Select this field to license your pattern with token licensing.

**LICENSE\_SERVER\_HOSTNAME**: Enter the fully qualified host name or IP address of your Rational License Key Server.

**LMGRD\_PORT**: Enter the port number that the license manager daemon (**Imrgd**) listens for connections on. The default license manager daemon port is 27000.

**IBMRATL\_PORT**:Enter the port number that the vendor daemon (**ibmratl**) listens for connections on. The default vendor daemon port is typically 27001.

A default administration account for MobileFirst Server is created during pattern deployment.

- 4. Configure and launch the pattern deployment:
  - In the IBM PureApplication System dashboard, click Patterns → Virtual System Patterns.
  - o On the Virtual System Patterns page, use the **Search** field to find the pattern you created, and then select the pattern.
  - In the toolbar above the panel displaying detailed information about the pattern, click the Deploy button.
  - In the Deploy Pattern window, in the Configure panel, select the correct environment profile from the
     Environment Profile list, and provide other IBM PureApplication System environment parameters. To
     obtain the correct information, consult your IBM PureApplication System administrator.
  - In the middle column, click **Pattern attributes** to display attributes such as user names and passwords.
     Supply the following information in the fields provided:

**Note:** Make appropriate changes to the default values of the pattern-level parameters even if an external LDAP server is configured. If you configure administration security by using an LDAP server, you need to supply additional LDAP information. For more information, see Configuring MobileFirst administration security with an external LDAP repository.

#### admin user

Not visible if configured in step 3. Create a default MobileFirst Server administrator account. Default value: demo.

#### admin password

Not visible if configured in step 3. Default admin account password. Default value: demo.

#### **ACTIVATE TOKEN LICENSE**

Not visible if configured in step 3. Select this field to license your pattern with token licensing. Leave this field clear if you use perpetual licenses.

#### LICENSE\_SERVER\_HOSTNAME

Not visible if configured in step 3. If you use token licensing to license IBM MobileFirst Platform Foundation, enter the fully-qualified hostname or IP address of your Rational License Key Server IP address. Otherwise, leave this field blank.

#### LMGRD PORT

Not visible if configured in step 3. If you use token licensing to license IBM MobileFirst Platform Foundation, enter the port number that the license manager daemon (Imrgd) listens for connections on. Otherwise, leave this field blank. The default license manager daemon port is 27000.

#### **IBMRATL PORT**

Not visible if configured in step 3. If you use token licensing to license IBM MobileFirst Platform Foundation, enter the port number that the vendor daemon (ibmratl) listens for connections on. Otherwise, leave this field blank. The default vendor daemon port is typically 27001.

#### runtime\_contextRoot

Not visible if configured in step 5. Context root name for the MobileFirst Server runtime. The name must start with "/".

#### deployer\_user

Not visible if configured in step 8. User name for the account with deployment privilege. If an external LDAP server is not configured, you must enter the same value as was specified when creating the default admin user for the administration service, because in this case, the only authorized user for app and adapter deployment is the default admin user.

#### deployer password

Not visible if configured in step 8. User password for the user with deployment privilege.

#### MFP Vms Password(root)

Root password for the MobileFirst Platform Server and MobileFirst Platform DB nodes. Default value: passw0rd.

#### MFP DB Password(Instance owner)

Instance owner password for the MobileFirst Platform DB node. Default value: passw0rd.

- Click Quick Deploy to launch your pattern deployment. After a few seconds, a message is displayed to
  indicate that the pattern has started to launch. You can click the URL provided in the message to track
  your pattern deployment status or go to Patterns → Virtual System Instances to open the Virtual System
  Instances page and search for your pattern there.
- 5. To access the MobileFirst Operations Console perform the following steps:
  - Click Patterns → Virtual System Instances to open the Virtual System Instances page and search for your pattern there.
  - Select your pattern name and expand the Virtual machine perspective in the panel that displays the details
    of the selected instance.
  - Find the MobileFirst Server VM that has a name similar to MFP\_AppCenter\_Server., make a note of its public IP address.
  - In the browser, open the MobileFirst Operations Console by composing its URL with one of the following formats:

- http://{MFP Server VM Public IP}:9080/appcenterconsole
- https://{MFP Server VM Public IP}:9443/appcenterconsole
- Log in to the Console with admin user and password specified in step 3.

# Configuring MobileFirst administration security with an external LDAP repository

You can configure MobileFirst administration security to enable connecting out to an external LDAP repository. The configuration is common for both WebSphere Application Server Liberty profile and full profile.

This procedure involves configuring the LDAP parameters for connecting to the external user registry server. Before you begin, ensure the LDAP server is working and consult your LDAP administrator to obtain the required configuration information.

#### Important:

When the LDAP repository configuration is enabled, a default user for MobileFirst administration is not automatically created. Instead, you must specify the administration user name and password that are stored in the LDAP repository. This information is required by WebSphere Application Server Liberty profile and a server farm of WebSphere Application Server full profile.

If the runtime to be deployed in the pattern is configured to use LDAP for application authentication, make sure that the LDAP server configured in the runtime is the same as the LDAP server that is configured for the MobileFirst Administration; different LDAP servers are not supported. Also, the protocol and port for LDAP connection must be identical. For example, if connections from the runtime to the LDAP server are configured to use the SSL protocol and port is 636, connections from the MobileFirst Administration to the LDAP server must use the SSL protocol and port 636 as well.

- 1. Build a pattern with any topology you need. For more information, see the following topics:
  - Deploying MobileFirst Server on a single-node WebSphere Application Server Liberty profile server
  - Deploying MobileFirst Server on a multiple-node WebSphere Application Server Liberty profile server
  - Deploying MobileFirst Server on a single-node WebSphere Application Server full profile server
  - Deploying MobileFirst Server on a multiple-node WebSphere Application Server full profile server
  - Deploying MobileFirst Server on clusters of WebSphere Application Server Network Deployment servers
- 2. Mandatory for AIX: In IBM PureApplication System running on Power, the MobileFirst Platform DB node needs to use the AIX-specific add-on component "Default AIX add disk" to replace the "Default add disk" component in the template to support the jfs2 file system:
  - In the Pattern Builder, select the MobileFirst Platform DB node.
  - Click the Add a Component Add-on button (the button is visible above the component box when you
    hover the cursor over the MobileFirst Platform DB node).
  - From the Add Add-ons list, select Default AIX add disk. The component is added as the lowest component of the MobileFirst Platform DB node.
  - Select the Default AIX add disk component and specify the following attributes:

#### DISK SIZE GB

Storage size (measured in GB) to be extended to the DB server. Example value: 10.

#### FILESYSTEM\_TYPE

Supported file system in AIX. Default value: jfs2.

#### **MOUNT POINT**

Align with the attribute **Mount point for instance owner** in the **Database Server component** in the **MobileFirst Platform DB** node. Example value: /dbinst.

#### VOLUME\_GROUP

Example value: group1. Contact your IBM PureApplication System administrator for the correct value.

- In the MobileFirst Platform DB node, select the Default add disk component, and then click the bin icon to delete it.
- o Save the pattern.

- 3. Configure MobileFirst Server administration:
  - In IBM PureApplication System, in the dashboard, click Patterns → Virtual System Patterns. The Virtual System Patterns page opens.
  - On the **Virtual System Patterns** page, use the **Search** field to find and select the pattern you created, and then click **Open** to open the **Pattern Builder** page.
  - In the MobileFirst Platform Server node (or the DmgrNode node when using the MobileFirst Platform (WAS ND) template), select the MFP Server Administration component. The properties of the selected component are displayed next to the canvas.
  - Supply the following LDAP information in the fields provided:

#### admin user

User ID of the account that has MobileFirst Server administration privilege. This value is stored in the LDAP repository. Not required if the MobileFirst Server is to be deployed on a single node of WebSphere Application Server full profile.

#### admin\_password

Admin user password. This value is stored in the LDAP repository. Not required if the MobileFirst Server is to be deployed on a single node of WebSphere Application Server full profile.

#### LDAP TYPE

LDAP server type of your user registry. One of the following values:

#### - None

LDAP connection is disabled. When this is set, all the other LDAP parameters are treated as placeholders only.

#### — TivoliDirectoryServer

Select this if the LDAP repository is an IBM Tivoli Directory Server.

#### ActiveDirectory

Select this if the LDAP repository is a Microsoft Active Directory.

Default value: None.

#### LDAP IP

LDAP server IP address.

#### LDAP SSL PORT

LDAP port for secure connection.

#### LDAP PORT

LDAP port for non-secure connection.

#### BASE DN

Base DN.

#### BIND\_DN

Bind DN.

#### **BIND PASSWORD**

Bind DN password.

#### REQUIRE\_SSL

Select true for secure connection to the LDAP server. Default value: false.

#### **USER FILTER**

LDAP user filter that applies when searching the existing user registry for users.

#### **GROUP FILTER**

LDAP group filter that applies when searching the existing user registry for groups.

#### LDAP\_REPOSITORY\_NAME

LDAP server name.

#### CERT\_FILE\_PATH

Target path of the uploaded LDAP server certification.

#### mfpadmin

Admin role for MobileFirst Server. One of the following values: — None

No user.

#### - AllAuthenticatedUsers

Authenticated users

#### - Everyone

All users.

Default value: None. For more information about security roles, see Configuring user authentication for MobileFirst Server administration (../../installation-configuration/production/server-configuration/#configuring-user-authentication-for-mobilefirst-server-administration).

#### mfpdeployer

Deployer role for MobileFirst Server. One of the following values: — None

No user.

#### - AllAuthenticatedUsers

Authenticated users

#### - Everyone

All users.

Default value: None. For more information about security roles, see Configuring user authentication for MobileFirst Server administration (../../installation-configuration/production/server-configuration/#configuring-user-authentication-for-mobilefirst-server-administration).

#### mfpmonitor

Monitor role for MobileFirst Server. One of the following values:

- None

No user.

#### - AllAuthenticatedUsers

Authenticated users

#### - Everyone

All users.

Default value: None. For more information about security roles, see [Configuring user authentication for MobileFirst Server administration](../../installation-configuration/production/server-configuration/#configuring-user-authentication-for-mobilefirst-server-administration) (../../installation-configuration/production/server-configuration/#configuring-user-authentication-for-mobilefirst-server-administration).

#### mfpoperator

Operator role for MobileFirst Server. One of the following values: —  ${\bf None}$ 

No user.

#### - AllAuthenticatedUsers

Authenticated users

#### - Everyone

All users.

Default value: None. For more information about security roles, see Configuring user authentication for MobileFirst Server administration (../../../installation-configuration/production/server-configuration/#configuring-user-authentication-for-mobilefirst-server-administration).

- 4. Optional: Configure the LDAP SSL connection. This step is required only if you set **REQUIRE\_SSL** to true in the previous step to use secure connections to the LDAP server:
  - From the Assets toolbar, expand Software Components, and then drag and drop an Additional file component onto the MobileFirst Server node in the canvas. Rename the component "MobileFirst LDAP Cert", for example.
  - Hover the cursor over the newly added component, and then click the Move up and Move down buttons

to adjust the position of the component in the node. Make sure that it is placed between the **MFP Server Prerequisite** component and the **MFP Server Administration** component.

- Click the MobileFirst LDAP Cert component. The properties of the selected component are displayed next to the canvas. Upload the LDAP certification artifact in the Additional file field by clicking the Browse button to locate it
- In the **Target** path field, specify the full path for storing the artifact including its file name; for example, /opt/tmp/tdscert.der.
- o In the MobileFirst Server node (or the DmgrNode node when using the MobileFirst Platform (WebSphere Application Server Network Deployment), select the MFP Server Administration component, and then click the Add reference button next to the CERT\_FILE\_PATH field. In the pop-up window, click the component-level parameter tab. From the Component list, select MobileFirst LDAP Cert. In the Output attribute list, select target\_path. Click the Add button to refresh the Output value field, and then click OK.
- 5. Configure and launch the pattern deployment. On the Deploy Pattern page, in the Nodes list, you can adjust your LDAP configurations by clicking MobileFirst Server (or DmgrNode when using the MobileFirst Platform (WAS ND) template) and then expanding MFP Server Administration. For more information about pattern deployment, see the "Configure and launch the pattern deployment" step in one of the following topics depending on the topology you selected when creating the pattern:
  - Deploying MobileFirst Server on a single-node WebSphere Application Server Liberty profile server, step
  - Deploying MobileFirst Server on a multiple-node WebSphere Application Server Liberty profile server, step
     9.
  - o Deploying MobileFirst Server on a single-node WebSphere Application Server full profile server, step 8.
  - o Deploying MobileFirst Server on a multiple-node WebSphere Application Server full profile server, step 9.
  - Deploying MobileFirst Server on clusters of WebSphere Application Server Network Deployment servers, step 9 onwards.
- 6. Access the MobileFirst Operations Console. Use the administrator user name and password to log in to the MobileFirst Operations Console through your LDAP configuration. For more information, see the "Access the MobileFirst Operations Console:" step in one of the following topics depending on the topology you selected when creating the pattern;
  - Deploying MobileFirst Server on a single-node WebSphere Application Server Liberty profile server, step
  - Deploying MobileFirst Server on a multiple-node WebSphere Application Server Liberty profile server, step
     10
  - o Deploying MobileFirst Server on a single-node WebSphere Application Server full profile server, step 9.
  - o Deploying MobileFirst Server on a multiple-node WebSphere Application Server full profile server, step 10.
  - Deploying MobileFirst Server on clusters of WebSphere Application Server Network Deployment servers, step 10 onwards.

# Configuring an external database with a IBM MobileFirst Platform Foundation System Pattern

You can configure IBM MobileFirst Foundation System Patterns to enable connecting out to an external database. IBM DB2 is the only supported external database. The configuration is common for all the supported patterns.

#### Before you begin,

This procedure involves configuring the external database parameters for connecting to the external database. Before you begin, ensure the following:

- Configure the external database instance on your installed IBM DB2.
- Make a note of the database instance name, database user name, database password, database host name or IP and database instance port.

- 1. Build a pattern with any topology you need. For more information, see the following topics: Deploying MobileFirst Server on a single-node WebSphere Application Server Liberty profile server
  - o Deploying MobileFirst Server on a multiple-node WebSphere Application Server Liberty profile server
  - Deploying MobileFirst Server on a single-node WebSphere Application Server full profile server
  - Deploying MobileFirst Server on a multiple-node WebSphere Application Server full profile server
  - Deploying MobileFirst Server on clusters of WebSphere Application Server Network Deployment servers
- 2. Select the MobileFirst Platform DB and click Remove component.
- 3. Configure MobileFirst Server administration:
  - In IBM PureApplication System, in the dashboard, click Patterns → Virtual System Patterns. The Virtual System Patterns page opens.
  - o On the **Virtual System Patterns** page, use the **Search** field to find and select the pattern you created, and then click **Open** to open the **Pattern Builder** page.
  - In the MobileFirst Platform Server node (or the DmgrNode node when using the MobileFirst Platform (WAS ND) template), select the MFP Server Administration component. The properties of the selected component are displayed next to the canvas.
  - Check the option **USE\_EXTERNAL\_DATABASE** and configure the following parameters:

#### db instance

External database instance name.

#### db user

External database user name.

#### db name

External database name.

#### db password

External database password.

#### db\_ip

External database IP.

#### db\_port

External database port number.

**Note:** If you are using the MobileFirstPlatform (WAS ND) pattern template, you will need to additionally configure the attribute **Open firewall ports for WAS** to the external database port number.

- In the MobileFirst Server node (or the DmgrNode node when using the MobileFirst Platform (WAS ND) template), select the MFP Server Runtime Deployment component. The properties of the selected component are displayed next to the canvas.
- Under the **USE\_EXTERNAL\_DATABASE** configure the following parameters:

#### rtdb\_instance

External database instance name.

#### rtdb user

External runtime database user name.

#### rtdb name

External runtime database name, which will be created.

**rtdb\_password** External runtime database password.

# **Deploying and configuring MobileFirst Analytics**

You can deploy and configure the MobileFirst Analytics on both WebSphere Application Server Liberty profile and full profile to enable the Analytics features in the pattern.

Before you begin,

If you intend to use an LDAP repository to protect the Analytics Console, ensure that the LDAP server is working and consult your LDAP administrator to obtain the required configuration information.

**Important:** When the LDAP repository configuration is enabled in the Analytics component, a default administration user is not created for MobileFirst Analytics. Instead, you must specify the administration user name and password values that are stored in the LDAP repository. These values are required to protect the Analytics Console.

- 1. Build a pattern with the topology you need. For more information, see the following topics:
  - Deploying MobileFirst Server on a single-node WebSphere Application Server Liberty profile server
  - Deploying MobileFirst Server on a multiple-node WebSphere Application Server Liberty profile server
  - o Deploying MobileFirst Server on a single-node WebSphere Application Server full profile server
  - Deploying MobileFirst Server on a multiple-node WebSphere Application Server full profile server
  - Deploying MobileFirst Server on clusters of WebSphere Application Server Network Deployment servers
- 2. Add and configure MobileFirst Analytics:
  - In the IBM PureApplication System dashboard, click Patterns → Virtual System Patterns. The Virtual System Patterns page opens.
  - o On the **Virtual System Patterns** page, use the **Search** field to find and select the pattern you created, and then click **Open** to open the **Pattern Builder** page.
  - From the **Assets** list, expand **Software Components**, and then drag and drop one of the following components onto the canvas:

#### Liberty profile server

Select this component if you want to deploy MobileFirst Analytics on WebSphere Application Server Liberty profile.

#### Standalone server

Select this component if you want to deploy MobileFirst Analytics on WebSphere Application Server full profile.

A new node is created with the name "OS Node". Rename it "MobileFirst Foundation Analytics".

- Make the following configuration changes depending on the type of application server you want to deploy Analytics to:
  - If you are deploying MobileFirst Analytics to WebSphere Application Server Liberty profile, click Liberty profile server in the MobileFirst Platform Analytics node. The properties of the selected component are displayed next to the canvas. In the Configuration data location field, enter the path /opt/IBM/WebSphere/Liberty and specify the administrative user name and password. Use the default values for the other parameters.
  - If you are deploying MobileFirst Analytics to WebSphere Application Server full profile, click **Standalone server** in the MobileFirst Platform Analytics node. The properties of the selected component are displayed next to the canvas. In the **Configuration data location** field, enter the path /opt/IBM/WebSphere/AppServer/Profiles, change Profile name to AppSrv01, and specify the administrative user name and password. Use the default values for the other parameters.

**Important:** The WebSphere Application Server administrative user will be created in the WebSphere Application Server user repository. If LDAP will be configured for the Analytics server, avoid user name conflicts with the WebSphere Application Server administrative user. For example, if "user1" will be introduced by the LDAP server through its configuration, do not set "user1" as the WebSphere Application Server administrative user name.

From the Components list, expand Scripts, and then drag and drop an MFP Server Prerequisite
component and a MFP WAS SDK Level component onto the MobileFirst Foundation Analytics node on the

canvas.

- From the Components list, expand Scripts, and then drag and drop an MFP Analytics component onto the MobileFirst Foundation Analytics node on the canvas. Make sure the MFP Analytics component is positioned after the Liberty profile server component (or the Standalone server component).
- Supply the following MobileFirst Analytics information in the fields provided:
   The LDAP parameters are exactly the same as the MFP Server Administration parameters. For more information, see the "Configure MFP Server Administration" step in 3:

**Important:** For LDAP SSL connection configuration in MobileFirst Analytics, make sure that in step 4b in Configuring MobileFirst administration security with an external LDAP repository, the dragged-in MobileFirst LDAP Cert component in the MobileFirst Foundation Analytics node must be moved to between the Liberty profile server (or Stanalone server) and the MFP Analytics script package.

# WAS ROOT

- If MobileFirst Analytics is being installed on WebSphere Application Server Liberty profile, specify the installation directory of the Liberty profile for Analytics:
  - Click the Add reference button next to the WAS\_ROOT field and in the pop-up window, click the component-level parameter tab.
  - In the Component field, select Liberty profile server (it might be called Liberty profile server\_1 if the MobileFirst Server is also deployed on WebSphere Application Server Liberty profile).
  - In the **Output attribute** field, select **install\_directory**. Click the **Add** button to refresh the Output value field, and then click **OK**.
- If MobileFirst Analytics is being installed on WebSphere Application Server full profile, specify the installation directory of the WebSphere Application Server full profile for Analytics:
  - Click the Add reference button next to the WAS\_ROOT field and in the pop-up window, click the component-level parameter tab.
  - In the Component field, select Standalone server (it might be called Standalone server\_1 if the MobileFirst Server is also deployed on WebSphere Application Server full profile)
  - In the **Output attribute** field, select **install\_directory**. Click the **Add** button to refresh the Output value field, and then click **OK**.

#### HEAP MIN SIZE

Applicable to WebSphere Application Server full profile only.

The amount of Analytics data that is generated is directly proportional to the amount of memory required to handle it. Set this value to allow a larger minimum heap size for WebSphere Application Server full profile. Make sure that the **Memory size** value specified in the Core OS component of the MobileFirst Platform Analytics node is larger than **HEAP\_MIN\_SIZE**. Consider setting a value equal to **HEAP\_MAX\_SIZE**.

Default value: 4096 MB.

# HEAP\_MAX\_SIZE

Applicable to WebSphere Application Server full profile only.

The amount of Analytics data that is generated is directly proportional to the amount of memory required to handle it. Set this value to allow a larger maximum heap size for WebSphere Application Server full profile. Make sure that the **Memory size** value specified in the Core OS component of the MobileFirst Platform Analytics node is larger than **HEAP\_MAX\_SIZE**. Consider setting a value equal to **HEAP\_MIN\_SIZE**.

Default value: 4096 MB.

# WAS\_admin\_user

• Applicable to WebSphere Application Server full profile only.

WebSphere Application Server full profile admin user ID for the Analytics server.

- Click the Add reference button next to the WAS\_admin\_user field and in the pop-up window, click the component-level parameter tab.
- In the Component field, select Standalone server (it may be called Standalone server\_1 if the MobileFirst Server is also deployed on WebSphere Application Server full profile)
- In the **Output attribute** field, select **was\_admin**. Click the **Add** button to refresh the **Output** value field, and then click **OK**.

For Liberty profile, the default value can be used.

# WAS\_admin\_password

Applicable to WebSphere Application Server full profile only.

WebSphere Application Server full profile admin user ID for the Analytics server.

- Click the Add reference button next to the WAS\_admin\_password field and in the pop-up window, click the component-level parameter tab.
- In the Component field, select Standalone server (it may be called Standalone server\_1 if the MobileFirst Server is also deployed on WebSphere Application Server full profile)
- In the **Output** attribute field, select **was\_admin\_password**. Click the **Add** button to refresh the **Output** value field, and then click **OK**.

For Liberty profile, the default value can be used.

#### admin user

- If an LDAP repository is not enabled, create a default administration user for MobileFirst Analytics console protection.
- If an LDAP repository is enabled, specify the user name that has MobileFirst Analytics administration privilege. The value is stored in the LDAP repository.

#### admin password

- If an LDAP repository is not enabled, specify the password for the default administration user for MobileFirst Analytics console protection.
- If an LDAP repository is enabled, specify the administration user password. The value is stored in the LDAP repository.


Optional: Enable the LDAP repository for MobileFirst Analytics console protection. The LDAP parameters in MobileFirst Analytics are exactly the same as those for MobileFirst Server Administration. For more information, see "Configure MFP Server Administration" (step 3) in Configuring MobileFirst administration security with an external LDAP repository.

- 3. Configure MobileFirst Server runtime deployment for MobileFirst Analytics connection:
  - In the MobileFirst Platform Server node (or the DmgrNode node when using the MobileFirst Platform (WAS ND) template), select the MFP Server Runtime Deployment component.
  - Drag a link from the MFP Server Runtime Deployment component to the Liberty profile server component or to the Standalone server component in the MobileFirst Platform Analytics node, depending on the type of application server being used. The Configure Data Dependencies pop-up window opens.
  - o Configure the data dependencies:
    - In the Configure Data Dependencies window, clear any existing recommended data dependency entries by clicking the **X** button next to each entry.
    - Below MFP Server Runtime Deployment component, select analytics\_ip and below Liberty profile server or Standalone server, select IP.
    - Click the Add button to add the new data dependency.
    - Click **OK** to save your changes.




The link from the MFP Server Runtime Deployment component to the Liberty profile server component (or the Standalone server component) is built.

- Drag another link from the MFP Server Runtime Deployment component to the MFP Analytics component in the MobileFirst Platform Analytics node. The Configure Data Dependencies pop-up window opens.
- Configure the data dependencies:
  - In the Configure Data Dependencies window, clear all the recommended data dependencies entries by clicking the **X** button next to each entry.
  - Below MFP Server Runtime Deployment component, select analytics\_admin\_user and below MFP Analytics, select admin\_user.
  - Click the **Add** button to add the new data dependency.
  - Repeat the process to configure a data dependency from analytics\_admin\_password to admin\_password.
  - Click **OK** to save your changes.



The following figure shows an example of a MobileFirst Platform Analytics node added to a MobileFirst Platform WAS ND pattern:



4. Configure and launch the pattern deployment.

On the Deploy Pattern page, you can adjust your MobileFirst Analytics configuration settings by clicking the MobileFirst Platform Analytics component under the Nodes list in the middle column and then expanding MFP Analytics.

For more information about pattern deployment, see the "Configure and launch the pattern deployment" step in the following topics depending on the topology you selected when creating the pattern:

- Deploying MobileFirst Server on a single-node WebSphere Application Server Liberty profile server, step
   8.
- Deploying MobileFirst Server on a multiple-node WebSphere Application Server Liberty profile server, step
   9.
- Deploying MobileFirst Server on a single-node WebSphere Application Server full profile server, step 8.
- o Deploying MobileFirst Server on a multiple-node WebSphere Application Server full profile server, step 9.
- Deploying MobileFirst Server on clusters of WebSphere Application Server Network Deployment servers, step 9 onwards.
- 5. Access MobileFirst Analytics through the MobileFirst Operations Console.

For more information, see the "Access the MobileFirst Operations Console" step in one of the following topics depending on the topology you selected when creating the pattern:

- Deploying MobileFirst Server on a single-node WebSphere Application Server Liberty profile server, step
- Deploying MobileFirst Server on a multiple-node WebSphere Application Server Liberty profile server, step 10.
- o Deploying MobileFirst Server on a single-node WebSphere Application Server full profile server, step 9.
- Deploying MobileFirst Server on a multiple-node WebSphere Application Server full profile server, step 10.
- Deploying MobileFirst Server on clusters of WebSphere Application Server Network Deployment servers, step 10 onwards.

# **Predefined templates for MobileFirst Platform Pattern**

IBM MobileFirst Foundation System Pattern includes predefined templates that you can use to build patterns for the most typical deployment topologies.


The following templates are available:

#### Jump to

- MobileFirst Platform (Liberty single node) template
- MobileFirst Platform (Liberty server farm) template
- MobileFirst Platform (WAS single node) template
- MobileFirst Platform (WAS server farm) template
- MobileFirst Platform (WAS ND) template
- MobileFirst Platform Application Center (Liberty single node) template
- MobileFirst Platform Application Center (WAS single node) template

# MobileFirst Platform (Liberty single node) template

The below diagram shows the composition of the "MobileFirst Platform (Liberty single node)" template.



The "MobileFirst Platform (Liberty single node)" template is composed of the following nodes and components:

Node Components

#### Components

#### Liberty profile server

WebSphere Application Server Liberty profile server installation.

#### **MFP Server Prerequisite**

Prerequisites for MobileFirst Server installation including SSL and Ant.

#### **MFP Server Administration**

MobileFirst Server Administration web application including MobileFirst Operations Console.

#### **MFP Server Runtime Deployment**

MobileFirst Platform ServerRuntime context root configuration.

# **MFP Server Application**

MobileFirst application to be added to the deployment.

#### **MFP Server Adapter**

MobileFirst adapter to be added to the deployment.

#### MFP Server Application Adapter Deployment

Application and adapter deployment to the MobileFirst Server.

#### **Database Server**

DB2 database server installation.

#### **MFP Administration DB**

MobileFirst administration database schema installation.

#### MobileFirst Platform DB

#### MFP Runtime DB


MobileFirst runtime database schema installation.

### Default add disk

Disk size configuration.

# MobileFirst Platform (Liberty server farm) template

The diagram below shows the composition of the "MobileFirst Platform (Liberty server farm)" template.



The "MobileFirst Platform (Liberty server farm)" template is composed of the following nodes and components:

Node Components

**IBM HTTP servers** 

IBM HTTP Server installation.

**IHS Server** 

# **MFP IHS Configuration**

Automatic configuration of IBM HTTP Server.

#### Liberty profile server

WebSphere Application Server Liberty profile server installation.

# MFP Server Prerequisite

Prerequisites for MobileFirst Server installation including SSL and Ant.

#### **MFP Server Administration**

MobileFirst Server Administration web application including MobileFirst Operations Console.

#### **MFP Server Runtime Deployment**

# MobileFirst Platform Server

Runtime context root configuration.

#### **MFP Server Application**

MobileFirst application to be added to the deployment.

#### **MFP Server Adapter**

MobileFirst adapter to be added to the deployment.

#### MFP Server Application Adapter Deployment

Application and adapter deployment to the MobileFirst Server.

#### **Base Scaling Policy**

VM scaling policy: number of VMs.

Components

**Database Server** 

DB2 database server installation.

#### **MFP Administration DB**

MobileFirst administration database schema installation.

MobileFirst Platform DB

#### MFP Runtime DB


MobileFirst runtime database schema installation.

#### Default add disk

Disk size configuration.

# MobileFirst Platform (WAS single node) template

The diagram below shows the composition of the "MobileFirst Platform (WAS single node)" template.



The "MobileFirst Platform (WAS single node)" template is composed of the following nodes and components:

Node

Components

#### Components

#### Standalone server

WebSphere Application Server full profile server installation.

#### Restriction

Do not change the values for the following component attributes:

- Cell name
- Node name
- Profile name

If you change any of these attributes, the deployment of patterns that are based on this template fails.

#### **MFP Server Prerequisite**

MobileFirst Platform Server Prerequisites for MobileFirst Server installation including SSL and Ant.

#### **MFP Server Administration**

MobileFirst Server Administration web application including

#### **MFP Server Runtime Deployment**

Runtime context root configuration. MobileFirst Operations Console.

#### MobileFirst App

MobileFirst application to be added to the deployment.

### **MobileFirst Adapter**

MobileFirst adapter to be added to the deployment.

#### MFP Server Application Adapter Deployment

Application and adapter deployment to the MobileFirst Server.

# **Database Server**

DB2 database server installation.

#### **MFP Administration DB**

MobileFirst administration database schema installation.

#### MobileFirst Platform DB

#### **MFP Runtime DB**


MobileFirst runtime database schema installation.

#### Default add disk

Disk size configuration.

# MobileFirst Platform (WAS server farm) template

The diagram below shows the composition of the "MobileFirst Platform (WAS server farm)" template.



Components

**IBM HTTP servers** 

IBM HTTP Server installation.

**IHS Server** 

#### **MFP IHS Configuration**

Automatic configuration of IBM HTTP Server.

#### Components

#### Standalone server

WebSphere Application Server full profile server installation.

Restriction: Do not change the values for the following component attributes:

- Cell name
- Node name
- Profile name

If you change any of these attributes, the deployment of patterns that are based on this template fails.

#### **MFP Server Prerequisite**

Prerequisites for MobileFirst Server installation including SSL and Ant.

# MobileFirst Platform Server

#### MFP Server Administration

MobileFirst Server Administration web application including MobileFirst Operations Console.

#### **MFP Server Runtime Deployment**

Runtime context root configuration.

#### MobileFirst App

MobileFirst application to be added to the deployment.

MobileFirst AdapterMobileFirst adapter to be added to the deployment.

# **MFP Server Application Adapter Deployment**

Application and adapter deployment to the MobileFirst Server.

#### **Base Scaling Policy**

VM scaling policy: number of VMs.

#### **Database Server**

DB2 database server installation.

#### MFP Administration DB

MobileFirst administration database schema installation.

# MobileFirst Platform DB

# MFP Runtime DB


MobileFirst runtime database schema installation.

#### Default add disk

Disk size configuration.

# MobileFirst Platform (WAS ND) template

The diagram below shows the composition of the "MobileFirst Platform (WAS ND)" template.



The "MobileFirst Platform (WAS ND)" template is composed of the following nodes and components:

Node Components

**IBM HTTP servers** 

IBM HTTP Server installation.

**IHS Server** 

**MFP IHS Configuration** 

Automatic configuration of IBM HTTP Server.

#### Components

#### **Deployment manager**

WebSphere Application Server deployment manager installation.

Restriction: Do not change the values for the following component attributes:

- Cell name
- Node name
- Profile name

If you change any of these attributes, the deployment of patterns that are based on this template fails.

#### MFP Server Prerequisite

Prerequisites for MobileFirst Server installation including SSL and Ant.

#### **MFP Server Administration**

#### DmgrNode

MobileFirst Server Administration web application including MobileFirst Operations Console.

#### **MFP Runtime**

Runtime WAR file.

# **MFP Server Runtime Deployment**

Runtime context root configuration.

#### **MFP Application**

MobileFirst application to be added to the deployment.

#### **MFP Adapter**

MobileFirst adapter to be added to the deployment.

# MFP Server Application Adapter Deployment

Application and adapter deployment to the MobileFirst Server.

#### **Database Server**

DB2 database server installation.

#### MFP Administration DB

MobileFirst administration database schema installation.

# MobileFirst Platform DB

# MFP Runtime DB

MobileFirst runtime database schema installation.

#### Default add disk

Disk size configuration.

#### Node Components

#### **Custom nodes**

Details of the cells and nodes in the clusters of WebSphere Application Server Network Deployment servers.

Restriction: Do not change the values for the following component attributes:

- Cell name
- Node name

#### CustomNode

Profile name

If you change any of these attributes, the deployment of patterns that are based on this template fails.

### MFP Open Firewall Ports for WAS


Ports that must be open to enable connection to the database server and the LDAP server.

#### Base scaling policy

Number of virtual machine instances required for the chosen topology.

# MobileFirst Platform Application Center (Liberty single node) template

The diagram below shows the composition of the "MobileFirst Platform Application Center (Liberty single node)" template.



The "MobileFirst Platform Application Center (Liberty single node)" template is composed of the following nodes and components:

Node Components

**Database Server** 

MFP DB2 database server installation.

AppCenter

DB Default add disk

Disk size configuration. Liberty profile server

WebSphere Application Server Liberty profile server installation.

MFP MFP Server Prerequisite


AppCenter Prerequisites for MobileFirst Server installation including SSL and Ant. Server

#### **MFP Server Application Center**

This script package sets up the MobileFirst Application Center server in a WebSphere Application Server full profile or WebSphere Application Server Liberty profile server.

# MobileFirst Platform Application Center (WAS single node) template

The diagram shows the composition of the "MobileFirst Platform Application Center (WAS single node)" template.



The "MobileFirst Platform Application Center (WAS single node)" template is composed of the following nodes and components:

Node Components

**Database Server** 

MFP DB2 database server installation.

AppCenter

DB Default add disk

Disk size configuration.

#### Standalone server

WebSphere Application Server full profile server installation.

Restriction: Do not change the values for the following component attributes:

- Cell name
- Node name
- Profile name

MFP AppCenter

Server

If you change any of these attributes, the deployment of patterns that are based on this template fails.

### MFP WAS SDK Level

Purpose of this script is to set the required SDK level as the default SDK for the WAS Profile

# **MFP Server Prerequisite**

Prerequisites for MobileFirst Server installation including SSL and Ant.

#### **MFP Server Application Center**

This script package sets up the MobileFirst Application Center server in a WebSphere Application Server full profile or WebSphere Application Server Liberty profile server.

# Script packages for MobileFirst Server

IBM MobileFirst Foundation System Pattern provides script packages that are the building blocks to compose various pattern topologies.

The following sections list and describe the parameters for each script package.

#### Jump to

- MFP Administration DB
- MFP Analytics
- MFP IHS Configuration
- MFP Open Firewall Ports for WAS

- MFP WAS SDK Level
- MFP Runtime DB
- MFP Server Administration
- MFP Server Application Adapter Deployment
- MFP Server Application Center
- MFP Server Prerequisite
- MFP Server Runtime Deployment

### **MFP Administration DB**

This script package sets up the administration database schema in a DB2 database. It must be used with the Database Server (DB2) software component.

Parameter	Description
db_user	Mandatory. User name to create the Administration database. It can be mapped to the Instance name of
	the Database Server component. Default value: db2inst1.
db_name	Mandatory. Database name to create the Administration database. Default value: WLADM.
	Mandatory. User password to create the Administration database. It can be mapped to the Instance
db_password owner password of the Database Server component. Default value: passw0rd (as pattern level	
	parameter).
other db erg	Mandatory. Four parameters to create the Administration database:SQL type, Codeset,Territory and Collate. Default value: DB2 UTF-8 US SYSTEM.
other_ub_arg	SCollate. Default value: DB2 UTF-8 US SYSTEM.

# **MFP Analytics**

This script package sets up the MobileFirst Analytics server in a WebSphere Application Server full profile or WebSphere Application Server Liberty profile server, and sets up the connection and mapping of Analytics administration security roles to an external TDS or AD server. It must be used with the WebSphere Application Server Liberty profile server or WebSphere Application Server full profile (display name: Standalone server) software component. It must be installed after the Liberty profile or Standalone server software component.

Parameter	<ul> <li>Description</li> <li>Mandatory.</li> <li>If Analytics is installed on WebSphere Application Server Liberty profile, specify the</li> </ul>
WAS_ROOT	installation directory of the WebSphere Application Server Liberty profile for Analytics.
	<ul> <li>If Analytics is installed on WebSphere Application Server full profile, specify the installation directory of the WebSphere Application Server full profile for Analytics.</li> </ul>
	WebSphere Application Server full profile only.
HEAP_MIN_SIZE	Depending on the amount of Analytics data that is generated, more memory is required for more data handling. Set this to allow larger minimum heap size for WebSphere Application Server full profile. Make sure the memory size specified in the Core OS component of MobileFirst Analytics is larger than this. It is recommended to set the same value as HEAP_MAX_SIZE.
	Default value: 4096 (MB). WebSphere Application Server full profile only.
HEAP_MAX_SIZE	Depending on the amount of Analytics data that is generated, more memory is required for more data handling. Set this to allow larger maximum heap size for WebSphere Application Server full profile. Make sure the memory size specified in the Core OS component of MobileFirst Analytics is larger than this. It is recommended to set the same value asHEAP_MIN_SIZE.

Default value: 4096 (MB).

**Parameter** Description WebSphere Application Server full profile only. WAS admin user WebSphere Application Server full profile admin user for the Analytics server. For WebSphere Application Server Liberty profile, leave the default value unchanged. WebSphere Application Server full profile only. WAS admin password WebSphere Application Server full profile admin user password for the Analytics server. For WebSphere Application Server Liberty profile, leave the default value unchanged. Mandatory.{::nomarkdown}If LDAP repository not enabled, create a default administration user for MobileFirst Analytics console protection.If LDAP repository admin user is enabled, specify the user name that has MobileFirst Analytics administration privilege. The value is stored in the LDAP repository. Mandatory.If an LDAP repository is not enabled, specify the password for the default administration user for MobileFirst Analytics console protection. admin password repository is enabled, specify the admin user password. The value is stored in the LDAP repository.{:/} (LDAP parameter) Mandatory. LDAP server type of your user registry: None LDAP connection is disabled. When this is set, all the other LDAP parameters are treated as placeholders only. LDAP TYPE **TivoliDirectoryServer** Select this if the LDAP repository is an IBM Tivoli Directory Server. ActiveDirectory Select this if the LDAP repository is a Microsoft Active Directory. Default value: None. LDAP IP (LDAP parameter). LDAP server IP address. LDAP SSL PORT (LDAP parameter) LDAP port for secure connection. LDAP\_PORT (LDAP parameter) LDAP port for non-secure connection. BASE DN (LDAP parameter) Base DN. BIND DN (LDAP parameter) Bind DN. BIND\_PASSWORD (LDAP parameter) Bind DN password. (LDAP parameter) Set it to true for secure connection to LDAP server. • When it is true, LDAP SSL PORT is used and CERT FILE PATH is required to locate the certification file of the LDAP server. REQUIRE SSL • When it is false, LDAP\_PORT is used. Default value: false. USER FILTER (LDAP parameter) LDAP user filter that searches the existing user registry for users. GROUP\_FILTER (LDAP parameter) LDAP group filter that searches the existing user registry for groups. LDAP REPOSITORY NAME(LDAP parameter) LDAP server name. (LDAP parameter) Target path of the uploaded LDAP server certification. It is mandatory CERT\_FILE\_PATH when REQUIRE\_SSL is set to true. (LDAP parameter) Admin role for MobileFirst Server:

None No user.

mfpadmin AllAuthenticatedUsers
Authenticated users

Everyone All users.

Default value: None.

Parameter Description

(LDAP parameter) Deployer role for MobileFirst Server:

None No user.

mfpdeployer AllAuthenticatedUsers Authenticated users

Everyone All users.

Default value: None.

(LDAP parameter) Monitor role for MobileFirst Server:

None No user.

mfpmonitor

AllAuthenticatedUsers

Authenticated users

Everyone All users.

Default value: None.

(LDAP parameter) Operator role for MobileFirst Server:

None No user.

mfpoperator AllAuthenticatedUsers
Authenticated users

Everyone All users.

Default value: None.

# **MFP IHS Configuration**

This script package configures the IBM HTTP Server to work as a load balancer for multiple instances of MobileFirst Server. It must be used with the IBM HTTP servers software component. It must be installed after the IBM HTTP servers software component.

Parameter	Description  Mandatory. Installation directory of WebSphere Application Server Liberty profile or
	WebSphere Application Server full profile in the MobileFirst Platform Server node, or
WAS_ROOT	installation directory of Deployment manager in the DmgrNode node. In the pattern templates,
	it is mapped to output attributeinstall_directory of Liberty profile server, Standalone server, or
	Deployment manager.
	Optional. The profile name that contains the files for the WebSphere Application Server runtime environment.
profile_name	
	In the pattern templates, it is mapped to output attribute <code>dmgr_profile_name</code> of Deployment

manager or sa\_profile\_name of Standalone server.

Parameter runtime_contextRoot_lis	Description  Mandatory. Runtime context root list that allows IHS to route requests that have matching context roots. Use semicolons (;) to separate the runtime context roots. For example, HelloMobileFirst;HelloWorld
	Important: It must align with the context root specified in the MFP Server Runtime Deployment. Otherwise, IHS cannot correctly route requests that contain the Runtime context root.
http_port	Mandatory. Open the firewall port in the IHS Server node to allow the HTTP transport from IHS Server to MobileFirst Server. Must be 9080.
https_port	Mandatory. Open the firewall port in the IHS Server node to allow the HTTPS transport from IHS Server to MobileFirst Server. Must be 9443.
server_hostname	Mandatory. Host name of IBM HTTP servers. It is mapped to the host output attribute of IBM HTTP servers in the pattern template.

# MFP Open Firewall Ports for WAS

This script package is only applicable for Custom nodes in the MobileFirst (WAS ND) pattern template (WebSphere Application Server Network Deployment). Its purpose is to open the necessary firewall ports of the Custom nodes that host the MobileFirst Administration Services and runtime. As well as defining some WebSphere Application Server predefined ports, you need to specify the other ports for connecting to the DB2 server and the LDAP server.

Parameter	Description
	Mandatory. Installation directory of WebSphere Application Server Network Deployment Custom
WAS_ROOT	nodes in the CustomNode node. In the pattern templates, it is mapped to output attribute
	install_directory of Custom nodes server.
	Mandatory. The profile name that contains the files for the WebSphere Application Server runtime
profile_name	environment. In the pattern templates, it is mapped to output attribute cn_profile_name of Custom
	nodes.
WAS_admin_use	erMandatory. It is mapped to the was_admin output attribute of Custom nodes in the pattern template.
	Mandatory. Other ports that need to be opened for connecting to DB2 server and LDAP server
Ports	(optional). Port values can be separated by semicolons; for example, '50000;636'
	Default value: 50000.

### MFP WAS SDK Level

This script package is only applicable where ever the WAS Profiles are available in the pattern template (WebSphere Application Server Network Deployment).

#### **Parameter Description**

Installation directory of WebSphere Application Server Liberty profile or WebSphere Application Server full WAS\_ROOT profile in the MobileFirst Platform Server node or the installation directory of the Deployment manager in the DmgrNode node. In the pattern templates, it is mapped to output attribute **install\_directory** of Liberty profile server, Standalone server, or Deployment manager.

The profile name that contains the files for the WebSphere Application Server runtime environment. In the profile\_namepattern templates, it is mapped to output attribute **dmgr\_profile\_name** of Deployment manager or **sa\_profile\_name** of Standalone server.

SDK name Name of the SDK that needs to be enabled for this WebSphere installation

#### MFP Runtime DB

This script package sets up the runtime database schema in a DB2 database.

Parameter	Description
db_user	Mandatory. User name to create the Runtime database. It can be mapped to the Instance name of the
	Database Server component. Default value: db2inst1.
db_name	Mandatory. Database name to create the Runtime database. Default value: WLRTIME.
db_password	Mandatory. User password to create the Runtime database. It can be mapped to the Instance owner
	password of the Database Server component. Default value: passw0rd (as pattern level parameter).
other_db_args	Mandatory. Four parameters to create the Runtime database:SQL type, Codeset, Territory and Collate.
	Mandatory. Four parameters to create the Runtime database:SQL type, Codeset,Territory and Collate. Default value: DB2 UTF-8 US SYSTEM.

# **MFP Server Administration**

This script package sets up the MobileFirst Administration component (including the MobileFirst Operations Console) in a WebSphere Application Server full profile or WebSphere Application Server Liberty profile server, and setting up the connection and mapping administration security roles to an external TDS or AD server.

The script package must be used with the WebSphere Application Server Liberty profile server software component or the WebSphere Application Server full profile software component (display name: Standalone server), and must be installed after the MFP Server Prerequisite but prior to any other MFP \* Script Packages in the MobileFirst Platform Server VM node.

Parameter	Description
WAS_ROOT	Mandatory. Installation directory of WebSphere Application Server Liberty profile or WebSphere Application Server full profile in the MobileFirst Platform Server node or the installation directory of the Deployment manager in the DmgrNode node. In the pattern templates, it is mapped to output attributeinstall_directory of Liberty profile server, Standalone server, or Deployment manager.  Optional. The profile name that contains the files for the WebSphere Application
profile_name	Server runtime environment. In the pattern templates, it is mapped to output attribute dmgr_profile_name of Deployment manager or sa_profile_name of Standalone server.
NUMBER_OF_CLUSTERMEMBER	Optional. Only applicable for the MobileFirst Platform (WAS ND) pattern template. SIt specifies the number of cluster members for the cluster to deploy the MFP administration service. Default value: 2.
db_user	Mandatory. User name that created the Administration database. It is mapped to the db_user output attribute of the MFP Administration DB script package in the pattern template.
db_name	Mandatory. Name of the Administration database. It is mapped to thedb_name output attribute of the MFP Administration DB script package in the pattern template.
db_password	Mandatory. password for user who created the Administration database. It is mapped to the db_password output attribute of the MFP Administration DB script package in the pattern template.
db_ip	IP address of the DB server where the Administration database is installed. It is mapped to the IP output attribute of the Database Server software component in the pattern template.
db_port	Port number of the DB server where the Administration database is installed. It is mapped to the instancePort output attribute of the Database Server software component in the pattern template.  User name that has MobileFirst Server administration privilege.{::nomarkdown} <ul><li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&gt;<li>Val&lt;<li>Val&lt;<li>Val&lt;<li>Val&lt;<li>Val&lt;<li>Val&lt;<li>Val&lt;<li>Val&lt;</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val</li><li>Val&lt;</li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></li></ul>
admin_user	LDAP_TYPE is set to TivoliDirectoryServer or ActiveDirectory and other LDAP parameters are specified according to your LDAP server configuration, the admin_user value should be taken from the configured LDAP user repository. Not required when the MobileFirst Server is to be deployed on a single node of WebSphere Application Server full profile.
admin_password	Password of the admin user. <ul><li>When LDAP_TYPE is None, create the default admin user password.</li><li>When an external LDAP server is configured, the user password is taken from the LDAP repository. Not required when the MobileFirst Server is to be deployed on a single node of WebSphere Application Server full profile.</li></ul>
install_console	Whether the MobileFirst Operations Console is to be deployed in the MobileFirst Platform Server node. Default value: Selected. (Check box)  Optional. When the MobileFirst Server is deployed on WebSphere Application
WAS_admin_user	Server full profile, it is mapped to the was_adminoutput attribute of Standalone server in the pattern template. When the MobileFirst Server is deployed on WebSphere Application Server Network Deployment, it is mapped to the was_admin output attribute of Deployment manager in the pattern template.

**Parameter** Description Optional. When the MobileFirst Server is deployed on WebSphere Application Server full profile, it is mapped to the was admin password output attribute of Standalone server in the pattern template. When the MobileFirst Server is WAS\_admin\_password deployed on WebSphere Application Server Network Deployment, it is mapped to the was\_admin\_password output attribute of Deployment manager in the pattern template. Mandatory. Host name of the MobileFirst Server or Deployment manager. Mapped to the host output attribute of Liberty profile server, Standalone Server, or server hostname Deployment manager. Mandatory. Whether the MobileFirst Server is to be deployed in server farm mode. Must be selected for a server farm topology and must be cleared for a server farm mode standalone topology. Default value: set according to the topology defined in the pattern template. Optional. When IBM HTTP servers is deployed in the pattern template, this webserver ip parameter is mapped to the IP output attribute of IBM HTTP servers. (LDAP parameter) Mandatory. LDAP server type of your user registry. One of the following values:None - LDAP connection is disabled. When this value is selected, all the other LDAP parameters are treated as placeholders only. LDAP\_TYPE TivoliDirectoryServer: Select this value if the LDAP repository is IBM Tivoli Directory ServerActiveDirectory: Select this value if the LDAP repository is Microsoft Active Directory{:/}Default value: None. LDAP IP (LDAP parameter) LDAP server IP address. LDAP SSL PORT (LDAP parameter) LDAP port for secure connection. LDAP\_PORT (LDAP parameter) LDAP port for non-secure connection. BASE DN (LDAP parameter) Base DN. BIND DN (LDAP parameter) Bind DN. BIND\_PASSWORD (LDAP parameter) Bind DN password. (LDAP parameter) Set to true for secure connection to LDAP server. • When true, the LDAP\\_SSL\\_PORT is used and CERT\\_FILE\\_PATH is required to locate the certification file of the LDAP server. REQUIRE SSL • When false, LDAP PORT is used. Default value: false. USER FILTER (LDAP parameter) User filter that searches the existing user registry for users. (LDAP parameter) LDAP group filter that searches the existing user registry for **GROUP FILTER** groups. LDAP\_REPOSITORY\_NAME (LDAP parameter) LDAP server name. (LDAP parameter) Target path of the uploaded LDAP server certification. It is CERT\_FILE\_PATH mandatory when REQUIRE SSL is set to true. Admin role for MobileFirst Server. One of the following values: None No user. AllAuthenticatedUsers mfpadmin Authenticated users Everyone All users.

Default value: None.

Parameter Description

(LDAP parameter) Deployer role for MobileFirst Server:

None No user.

mfpdeployer AllAuthenticatedUsers
Authenticated users

Everyone All users.

Default value: None.

(LDAP parameter) Monitor role for MobileFirst Server:

None No user.

mfpmonitor

AllAuthenticatedUsers

Authenticated users

Everyone All users.

Default value: None.

(LDAP parameter) Operator role for MobileFirst Server:

None No user.

mfpoperator AllAuthenticatedUsers
Authenticated users

Everyone All users.

Default value: None.

# **MFP Server Application Adapter Deployment**

This script package deploys applications and adapters to the MobileFirst Server. It must be installed after the corresponding MFP Server Runtime Deployment script package that installed the runtime where the application and adapter are to be deployed.

Parameter	Description
artifact dir	Mandatory. Installation path of application and adapter for deployment. It is mapped to the
artiiact_uii	target_pathoutput attribute of the MobileFirst App component in the pattern template.
admin_context	Mandatory. Must be mfpadmin.
	Mandatory. Align with the runtime context root specified in the MFP Server Runtime Deployment
runtime_context	component. It is mapped to runtime_contextRoot output attribute of the MFP Server Runtime
	Deployment component.
deployer_user	Mandatory. User account with application and adapter deployment privilege. Set as pattern level
	parameter in the pattern template.
doplovor passwor	Mandatory. User password with application and adapter deployment privilege. Set as pattern level
deployel_passwol	parameter in the pattern template.
webserver ip	Optional. When IBM HTTP servers is deployed in the pattern template, it is mapped to the same
wenselvel_ih	output attribute of MFP Server Administration.

# **MFP Server Application Center**

This script package sets up the MobileFirst Application Center server in a WebSphere Application Server full profile or WebSphere Application Server Liberty profile server. It must be used with the WebSphere Application Server Liberty profile server and MFP Server Prerequisite or WebSphere Application Server full profile (Standalone server), MFP WAS SDK Level and MFP Server Prerequisite. It must be installed after the Liberty profile or Standalone server software component.

Parameter	Description
WAS_ROOT	Mandatory. Installation directory of WebSphere Application Server Liberty profile or WebSphere Application Server full profile in the MobileFirst Platform Server node. In the pattern templates, it is mapped to output attributeinstall_directory of Liberty profile server or Standalone server.
profile_name	The profile name that contains the files for the WebSphere Application Server runtime environment. In the pattern templates, it is mapped to output attribute sa_profile_name of Standalone server.
db_instance	Name of the database instance. It is mapped to the instancePort output attribute of the Database Server software component in the pattern template.
db_user	User name that created the Administration database. It is mapped to the db_user output attribute of the MFP Administration DB script package in the pattern template.
db_name	Name of the Administration database. It is mapped to thedb_name output attribute of the MFP Administration DB script package in the pattern template.
db_password	Password for user who created the Administration database. It is mapped to the db_password output attribute of the MFP Administration DB script package in the pattern template.
db_ip	IP address of the DB server where the Administration database is installed. It is mapped to the IP output attribute of the Database Server software component in the pattern template.
db_port	Port number of the DB server where the Administration database is installed. It is mapped to the instancePort output attribute of the Database Server software component in the pattern template.
	User name that has MobileFirst Server administration privilege.
admin_user	In the pattern template, it is associated with the parameter of the same name in the MFP Server Administration script package as a pattern level parameter to ensure they are set to the same value admin user password.
admin_password	In the pattern template, it is associated with the parameter of the same name in the MFP Server Administration script package as a pattern level parameter to ensure they are set to the same value
WAS_admin_user	Mandatory for WebSphere Application Server. Optional for WebSphere Application Server Liberty. When the MobileFirst Server is deployed on WebSphere Application Server full profile, it is mapped to the was_adminoutput attribute of Standalone server in the pattern template.
	When the MobileFirst Server is deployed on WebSphere Application Server Network Deployment, it is mapped to the was_admin output attribute of Deployment manager in the pattern template.
WAS_admin_password	Mandatory for WebSphere Application Server. Optional for WebSphere Application Server Liberty. When the MobileFirst Server is deployed on WebSphere Application Server full profile, it is mapped to the was_admin_password output attribute of Standalone server in the pattern template.
server_hostname	Host name of the MobileFirst Server. It is mapped to the host output attribute of Liberty profile server or Standalone Server.

Parameter Description

(LDAP parameter) Mandatory. LDAP server type of your user registry:

None

LDAP connection is disabled. When this is set, all the other LDAP parameters are treated

as placeholders only.

LDAP\_TYPE TivoliDirectoryServer

Select this if the LDAP repository is an IBM Tivoli Directory Server.

ActiveDirectory

Select this if the LDAP repository is a Microsoft Active Directory.

Default value: None.

LDAP IP (LDAP parameter). LDAP server IP address.

LDAP\_SSL\_PORT (LDAP parameter) LDAP port for secure connection.

LDAP\_PORT (LDAP parameter) LDAP port for non-secure connection.

BASE\_DN (LDAP parameter) Base DN. BIND\_DN (LDAP parameter) Bind DN.

BIND PASSWORD (LDAP parameter) Bind DN password.

(LDAP parameter) Set it to true for secure connection to LDAP server.{::nomarkdown}

REQUIRE SSL Vhen it is true, LDAP\_SSL\_PORT is used and CERT\_FILE\_PATH is required to

locate the certification file of the LDAP server.

used.Default value: false.

USER\_FILTER (LDAP parameter) LDAP user filter that searches the existing user registry for users.

GROUP\_FILTER (LDAP parameter) LDAP group filter that searches the existing user registry for groups.

LDAP REPOSITORY NAME(LDAP parameter) LDAP server name.

CERT FILE PATH (LDAP parameter) Target path of the uploaded LDAP server certification. It is mandatory

when REQUIRE\_SSL is set to true.

Admin role for MobileFirst Application Center. Use one of the following values:
None
No user
AllAuthenticatedUsers

EveryoneAll users<!/>Default value: None

# **MFP Server Prerequisite**

This script package includes all prerequisites that are required to install the MobileFirst Server, including the DB2 JDBC driver and Apache Ant. The script package must be used with the WebSphere Application Server Liberty profile server software component or the WebSphere Application Server full profile software component (display name: Standalone server), and must be installed after the server software component but prior to any other MFP\* script packages in the MobileFirst Platform Server node.

#### **ParameterDescription**

appcenteradmin

None No parameters for this script package.

# MFP Server Runtime Deployment

This script package installs the MobileFirst runtime in a WebSphere Application Server full profile or WebSphere Application Server Liberty profile server with the MobileFirst Operations Console installed. The script package also sets up the connection to the MobileFirst Analytics server. It must be installed after the MFP Server Administration script package.

Parameter	Description
	Mandatory. Installation directory of WebSphere Application Server Liberty profile
	or WebSphere Application Server full profile in the MobileFirst Platform Server
WAS_ROOT	node, or installation directory of Deployment manager in the DmgrNode node. In
	the pattern templates, it is mapped to output attribute install_directory of Liberty
	profile server or Standalone server.

**Parameter** Description Optional. The profile name that contains the files for the WebSphere Application Server runtime environment. In the pattern templates, it is mapped to output profile\_name attribute dmgr\_profile\_name of Deployment manager or sa\_profile\_name of Standalone server. Optional. Only applicable for the MobileFirst Platform (WAS ND) pattern template. NUMBER\_OF\_CLUSTERMEMBERSIt specifies the number of cluster members for the cluster to deploy MFP runtime. Default value: 2. IP address of the DB server where the Runtime (and optional Reports) database db\_ip is installed. It is mapped to the IP output attribute of the Database Server software component in the pattern template. Port number of the DB server where the Runtime (and optional Reports) database is installed. It is mapped to theinstancePort output attribute of the Database db\_port Server software component in the pattern template. Mandatory. User name that has MobileFirst Server administration privilege. In the pattern template, it is associated with the parameter of the same name in the MFP admin user Server Administration script package as a pattern level parameter to ensure they are set to the same value Mandatory. admin user password. In the pattern template, it is associated with the parameter of the same name in the MFP Server Administration script package as admin password a pattern level parameter to ensure they are set to the same value Mandatory. Runtime WAR file installed path. For example: it can be mapped to runtime path the target\_path output attribute of MFP Server Runtime in the pattern template. Mandatory. Runtime context root. Must start with a forward slash, /; for example, runtime contextRoot "/HelloWorld". It is set as a pattern level parameter in the pattern template. Mandatory. Name of the Runtime database. It is mapped to thedb name output rtdb name attribute of the MFP Runtime DB script package in the pattern template. Mandatory. User that created the Runtime database. It is mapped to the db\_user rtdb user output attribute of the MFP Runtime DB script package in the pattern template. Mandatory. Password of the user that created the Runtime database. It is mapped rtdb\_password to the db\_password output attribute of the MFP Runtime DB script package in the pattern template. Optional. Name of the Reports database. It is mapped to thedb\_name output attribute of the MFP Reports DB script package in the pattern template. Leave rptdb\_name blank if you do not want to connect to a Reports database. Optional. User that created the Reports database. It is mapped to thedb\_user rptdb user output attribute of the MFP Reports DB script package in the pattern template. Optional. Password of the user that created the Reports database. It is mapped to rptdb password the db password output attribute of MFP Reports DB script package in the pattern template. \ Optional. When the MobileFirst Server is deployed on WebSphere Application Server full profile, it is mapped to the was\_adminoutput attribute of Standalone was\_admin\_user server in the pattern template. When the MobileFirst Server is deployed on WebSphere Application Server Network Deployment, it is mapped to the was\_admin output attribute of Deployment manager in the pattern template. Optional. When the MobileFirst Server is deployed on WebSphere Application Server full profile, it is mapped to thewas\_admin\_password output attribute of Standalone server in the pattern template. When the MobileFirst Server is was admin password deployed on WebSphere Application Server Network Deployment, it is mapped to the was admin password output attribute of Deployment manager in the pattern template. Mandatory. Map it to the same attribute of MFP Server Administration. server\_farm\_mode Mandatory. Host name of the MobileFirst Server. It is mapped to the host output server\_hostname attribute of Liberty profile server, Standalone Server, or Deployment manager. Optional. MobileFirst Analytics Node IP address to enable the Analytics capability analytics\_ip in the MFP Server Runtime. Optional. Administrator name of the MobileFirst Analytics server. analytics\_admin\_user Optional. Password of administrator of the MobileFirst Analytics server. analytics\_admin\_password

# **Upgrading IBM MobileFirst Platform Foundation System Pattern**

To upgrade IBM MobileFirst Application Pattern, upload the .tgz file that contains the latest updates.

- 1. Log into IBM PureApplication System with an account that is allowed to upload new system plugins.
- 2. From the IBM PureApplication System console, navigate to Catalog → System Plug-ins.
- 3. Upload the IBM MobileFirst Application Pattern .tgz file that contains the updates.
- 4. Enable the plugins you have uploaded.
- 5. Redeploy the pattern.

Last modified on November 17, 2016