## MobileFirst Platform {dev}

# **NTLM** authentication

#### Relevant to:



### **Overview**

The NTLM protocol is a challenge-response mechanism for authentication users in Windows operating systems. This tutorial explains how to use a MobileFirst adapter when connecting to a back end or resource that is protected by NTLM protocol for user authentication.

#### Topics:


- Back-end connection settings (connectAs="endUser/server")
- Using NTLM authentication with ServerIdentity
- Using NTLM authentication with UserIdentity

## Back-end connection settings (connectAs="endUser/server")

For MobileFirst Server to handle sessions when connecting to a back-end system, you can use either of the following 2 approaches:


#### • connectAS="server":

All sessions use the same connection context to the back end. This is the MobileFirst Server default behavior.



#### connectAS="endUser":

Each session is authenticated separately and has a unique connection context against the back end.



For a procedure to be connected as "end user", you must declare it with a connectAs="endUser" attribute in the adapter XML file:

```
cprocedure name="MyProcedure" connectAs="endUser"/>
```

For more information about the connectAs attribute, read the blog post about <u>Configuring HTTP</u> adapters for stateless/stateful back-end connectivity and user identity propagation.

## Using NTLM authentication with ServerIdentity

When you use a procedure to connect to a back-end server that uses NTLM protocol without specifying the connectAs attribute, use the <serveridentity> element of the adapter XML file as child element of the <authentication> element. Also add the <ntlm workstation> child element, so that MobileFirst Server knows which authentication method to use when connecting to the back end.

Make sure to pass the server and user names to the back-end server in the following pattern: server-name/user-name.

```
<connectivity>
  <connectionPolicy xsi:type="http:HTTPConnectionPolicyType">
    cprotocol>http
    <domain>your-domain-here</domain>
    <port>80</port>
    <connectionTimeoutInMilliseconds>30000</connectionTimeoutInMilliseconds>
    <socketTimeoutInMilliseconds>30000</socketTimeoutInMilliseconds>
    <authentication>
      <ntlm workstation="ServerName"/>
      <serverIdentity>
        <username>your-server-name/your-username-here</username>
        <password>your-password-here</password>
      </serverIdentity>
    </authentication>
    <maxConcurrentConnectionsPerNode>50</maxConcurrentConnectionsPerNode>
  </connectionPolicy>
</connectivity>
```

**Note:** When the NTLM protocol is used, the user name is always specified in the {server-name/user-name} format.

## Using NTLM authentication with UserIdentity

### **Configure MobileFirst Server authentication**

1. Create a security test to protect the procedure:

```
<customSecurityTest name="NTLMSecurityTest">
    <test isInternalUserID="true" realm="NTLMAuthRealm"/>
</customSecurityTest>
```

2. Use BasicAuthenticator, AdapterBasedAuthenticator, or any other authenticator that handles userIdentity, as the class for the realm used by the security test:

```
<realm name="NTLMAuthRealm" loginModule="AuthLoginModule">
        <className>com.worklight.integration.auth.AdapterAuthenticator</className>
        <parameter name="login-function" value="MyAdapter.onAuthRequired"/>
        <parameter name="logout-function" value="MyAdapter.onLogout"/>
        </realm>
```

3. Add some login module to create and store user identities to be used by this realm:

```
<loginModule name="AuthLoginModule">
    <className>com.worklight.core.auth.ext.NonValidatingLoginModule</className>
</loginModule>
```

4. Add the <authentication> element and its <ntlm workstation> child element to the adapter XML file, so that MobileFirst Server knows which authentication method to use when connecting to the back end:

5. Assign this security test to the procedure that is used to connect to the back end protected by NTLM protocol, and add connectAs="endUser" to the procedure declaration in the adapter XML file:

```
cprocedure name="getNTLMData" securityTest="NTLMSecurityTest" connectAs="endUser"/>
```

### Adapter JavaScript code

Create a UserIdentity that contains a user identifier and credentials properties. Format the userId as servername/username:

```
function submitAuthentication(username, password){
  var userIdentity = {
    userId: "MyServerName\/"+ username,
    credentials: password
  };
  WL.Server.setActiveUser("NTLMAuthRealm", null);
  WL.Server.setActiveUser("NTLMAuthRealm", userIdentity);
}
```

```
8/11/2015
```

Create an http request to the NTLM protected back end:

```
function getSecretData(){
  var input = {
    method : 'get',
    returnedContentType : 'html',
    path : "index.html"
  };
  return WL.Server.invokeHttp(input);
}
```