Push Notifications in Native Android Applications

Overview

This tutorial explains how to configure a MobileFirst Native Android application to support push notifications.

Also mentioned are the addresses and ports that are required for notifications to arrive to the supported Android Push Notification Service vendor (GCM).

Prerequisite: Make sure that you read the Configuring a native Android application with the MobileFirst Platform SDK (../../helloworld/configuring-a-native-android-application-with-the-mfp-sdk/) tutorial first.

Setting up the project

1. Create a MobileFirst project and add a MobileFirst Android Native API. PushNotificationsNative

In this tutorial and the accompanying sample, the application is called "androidnativepush". Be sure to replace this value with your own application name.

The native API includes the following push-related file:

The push.png file is an icon file that is displayed when a push notification arrives. Copy
this file from your native API folder and put it in your native project's res/drawable
folders.

2. Edit the application-descriptor.xml file.

These settings are also editable with the Application Descriptor Editor in Design mode.

Add the pushSender child-element inside the nativeAndroidApp element. Replace the key and senderId values with your API key and project number respectively. In case you do not have these, you can get them from the Google Developer Console (https://console.developers.google.com).



▶ ➡ Java Resources ▶ ➡ JavaScript Resources ▼ adapters ▼ b PushAdapter PushAdapter-impl.js PushAdapter.xml ▼ b AndroidNativePush armeabi armeabi-v7a jsonstore ▶ mips ▶ ≈ x86 android-async-http.jar application-descriptor.xml proguard-project.txt push.png uicandroid.iar wlclient.properties worklight-android.jar

3. Edit the wlclient.properties file.

Edit the wlclient.properties file in your native Android project and enter appropriate values for the following fields:

- wlServerHost The hostname or IP address of MobileFirst Server.
- wlServerPort The port on which MobileFirst Server is listening.
- o GcmSenderld The project number that you obtained through the Google API console.

```
wlServerProtocol = http
wlServerHost =
wlServerPort = 10080
wlServerContext = /MobileFirst-Project-Name/
wlAppld = MobileFirst-App-Name
wlAppVersion = 1.0
wlEnvironment = Androidnative
wlUid = wY/mbnwKTDDYQUvuQCdSgg==
wlPlatformVersion = 7.1.0.0
#languagePreferences = Add locales in order of preference (e.g. en, fr, fr-CA)
#For Push Notifications,uncomment below line and assign value to it
GcmSenderId =
```

4. Add Google Play Services (optional)

For instructions about how to setup Google Play Services review the Setting Up Google Play Services (http://developer.android.com/google/play-services/setup.html) topic at the Android Developer website.

5. Modify the native Android project.

Verify that the following permissions exist in the AndroidManifest.xml file of your Android project.

```
<permission android:name="com.example.project.permission.C2D_MESSAGE" android:protectionLevel="signature" />
< uses-permission android:name="android.permission.INTERNET" />
<uses-permission android:name="android.permission.GET_TASKS"/>
<uses-permission android:name="com.example.project.permission.C2D_MESSAGE" />
<uses-permission android:name="com.google.android.c2dm.permission.RECEIVE" />
<uses-permission android:name="android.permission.WAKE_LOCK" />
<uses-permission android:name="android.permission.GET_ACCOUNTS" />
<uses-permission android:name="android.permission.USE_CREDENTIALS" />
<uses-permission android:name="android.permission.WRITE_EXTERNAL_STORAGE" />
<uses-permission android:name="android.permission.ACCESS_WIFI_STATE"/></uses-permission android:name="android.permission.ACCESS_WIFI_STATE"/>
```

Replace all com.example.project with your Android project package name.

Add the launchMode attribute to the application element. Set its value to singleTask.

```
<application
android:allowBackup="true"
android:icon="@drawable/ic_launcher"

android:label="@string/app_name"
android:theme="@style/AppTheme"
android:launchMode="singleTask">
```

Add an intent-filter to the activity element for notifications.

```
<activity
android:name=".ActivityName"<
android:label="@string/app_name">
<intent-filter>
<action android:name="com.example.project.app_name.NOTIFICATION" /
>
<category android:name="android.intent.category.DEFAULT" />
</intent-filter>
```

Replace the **com.example.project.app_name** with your Android project package name and the app_name string as it appears in the res/values/string.xml file. For example: com.sample.notifications.NativeAndroidNotifications.

Add the GCMIntentService and add an intent-filter for RECEIVE and REGISTRATION of notifications.

Replace all com.example.project with your Android project package name.

Android Push Notifications Service

The following ports must be open: 443, 5228, 5229, and 5230. GCM typically uses only 5228, but it sometimes uses 5229 and 5230. GCM does not provide specific IP addresses, so you must allow your firewall to accept outgoing connections to all IP addresses that are contained in the IP blocks listed in Google ASN of 15169.

Notification Types

Last modified on

IBM	Social	Site
Legal notices	Facebook	RSS feed
(file:////home/travis/build/MFPSamples/DevCenter/https://eigal/w.facebook.com/ibmmolpil/effest/p/latfore/flyravis/build/MFPSamples/DevCe		
notices/)	Twitter	Open issue
Privacy	(https://twitter.com/ibmmobiledev)	(https://github.com/MobileFirst-
(http://www.ibm.com/privacy/us/en/)	YouTube	Platform-Developer-
Terms of use	(https://www.youtube.com/channel/	UCenter/DevCenter/issues/new)
(file:////home/travis/build/MFPSamples/DevCente	∍r <u>C</u> ₹ite⁄/jtearfús nci2Qusu97Q)	Contribute
of-use/)	GitHub	(https://github.com/MobileFirst-
Third party notice	(https://github.com/MobileFirst-	Platform-Developer-
(file:////home/travis/build/MFPSamples/DevCente	er.P.lsitfe/thirdDeveloper-	Center/DevCenter/blob/master/contributing.m
party-notice/)	Center)	Report abuse
		(https://www.ibm.com/developerworks/commi