Push Notifications in Native Android Applications


Overview

This tutorial explains how to configure a MobileFirst Native Android application to support push notifications.

Also mentioned are the addresses and ports that are required for notifications to arrive to the supported Android Push Notification Service vendor (GCM).

Prerequisite: Make sure that you read the Configuring a native Android application with the MobileFirst Platform SDK (../../../configuring-the-mfpf-sdk/configuring-a-native-android-application-with-the-mfp-sdk/) tutorial first.

Setting up the project



(http://developer.ibm.com/mobilefirstplatform/wp-content/uploads/sites/32/2014/12/NativeAndroidPushAdapterExpanded-70.png)

Create a MobileFirst project and add a MobileFirst Android Native API.

In this tutorial and the accompanying sample, the application is called "androidnative push". Be sure to replace this value with your own application name.

The native API includes the following push-related file:

• The push.png file is an icon file that is displayed when a push notification arrives. Copy this file from your native API folder and put it in your native project's res/drawable folders.

2. Edit the application-descriptor.xml file.

These settings are also editable with the Application Descriptor Editor in Design mode.

• Add the pushSender child-element inside the nativeAndroidApp element . Replace the key and senderId values with your API key and project number respectively. In case you do not have these, you can get them from the Google Developer Console (https://console.developers.google.com). [code lang="xml" highlight="9"] <nativeAndroidApp id="AppName" platformVersion="7.1.0.00.20150812-0731"</p> version="1.0" xmlns="http://www.worklight.com/native-android-descriptor"> <displayName>AppName</displayName> <description>AppName</description> <publicSigningKey></publicSigningKey> <packageName></packageName> <accessTokenExpiration>3600</accessTokenExpiration> <userIdentityRealms></userIdentityRealms> <pushSender key="" senderId=""/> </nativeAndroidApp> [/code]

3. Edit the wlclient.properties file.

Edit the wlclient.properties file in your native Android project and enter appropriate values for the following fields:

- wlServerHost The hostname or IP address of MobileFirst Server.
- wlServerPort The port on which MobileFirst Server is listening.
- GcmSenderld The project number that you obtained through the Google API console.

```
[code lang="xml"]
wlServerProtocol = http
wlServerHost =
wlServerPort = 10080
wlServerContext = /MobileFirst-Project-Name/
wlAppId = MobileFirst-App-Name
wlAppVersion = 1.0
```

```
wlEnvironment = Androidnative
wlUid = wY/mbnwKTDDYQUvuQCdSgg==
wlPlatformVersion = 7.1.0.0
#languagePreferences = Add locales in order of preference (e.g. en, fr, fr-CA)
#For Push Notifications,uncomment below line and assign value to it
GcmSenderId =
[/code]
```

4. Add Google Play Services.

For instructions about how to setup Google Play Services review the Setting Up Google Play Services (http://developer.android.com/google/play-services/setup.html) topic at the Android Developer website.

5. Modify the native Android project.

Verify that the following permissions exist in the AndroidManifest.xml file of your Android project.

```
[code lang="xml"]

<permission android:name="com.example.project.permission.C2D_MESSAGE"
android:protectionLevel="signature" />

<uses-permission android:name="android.permission.INTERNET" />

<uses-permission android:name="android.permission.GET_TASKS"/>

<uses-permission android:name="com.example.project.permission.C2D_MESSAGE" />

<uses-permission android:name="com.google.android.c2dm.permission.RECEIVE" />

<uses-permission android:name="android.permission.WAKE_LOCK" />

<uses-permission android:name="android.permission.GET_ACCOUNTS" />

<uses-permission android:name="android.permission.USE_CREDENTIALS" />

<uses-permission android:name="android.permission.WRITE_EXTERNAL_STORAGE" />

<uses-permission android:name="android.permission.WRITE_EXTERNAL_STORAGE" />

<uses-permission android:name="android.permission.ACCESS_WIFI_STATE"/>[/code]</uses-permission android:name="android.permission.ACCESS_WIFI_STATE"/>[/code]</uses-permission android:name="android.permission.ACCESS_WIFI_STATE"/>[/code]</uses-permission android:name="android.permission.ACCESS_WIFI_STATE"/>[/code]</uses-permission android:name="android.permission.ACCESS_WIFI_STATE"/>[/code]</uses-permission android:name="android.permission.ACCESS_WIFI_STATE"/>[/code]</uses-permission.ACCESS_WIFI_STATE"/>[/code]</uses-permission.ACCESS_WIFI_STATE"/>[/code]</uses-permission.ACCESS_WIFI_STATE"/>[/code]</uses-permission.ACCESS_WIFI_STATE"/>[/code]</uses-permission.ACCESS_WIFI_STATE"/>[/code]</uses-permission.ACCESS_WIFI_STATE"/>[/code]</uses-permission.ACCESS_WIFI_STATE"/>[/code]</uses-permission.ACCESS_WIFI_STATE"/>[/code]</uses-permission.ACCESS_WIFI_STATE"/>[/code]</uses-permission.ACCESS_WIFI_STATE"/>[/code]</uses-permission.ACCESS_WIFI_STATE"/>[/code]</uses-permission.ACCESS_WIFI_STATE"/>[/code]</uses-permission.ACCESS_WIFI_STATE"/>[/code]</uses-permission.ACCESS_WIFI_STATE"//[/code]</uses-permission.ACCESS_WIFI_STATE"//[/code]</uses-permission.ACCESS_WIFI_STATE"//[/code]</uses-permission.ACCESS_WIFI_STATE"//[/code]</uses-permission.ACCESS_WIFI_STATE"//[
```

Replace all com.example.project with your Android project package name.

Add the launchMode attribute to the application element. Set its value to singleTask.

```
[code lang="xml"]
<application
android:allowBackup="true"
android:icon="@drawable/ic_launcher"
android:label="@string/app_name"
android:theme="@style/AppTheme"
android:launchMode="singleTask" >
[/code]
```

Add an intent-filter to the activity element for notifications.

```
[code lang="xml"]
<activity
android:name=".ActivityName"
android:label="@string/app_name" >
<intent-filter>
<action android:name="com.example.project.app_name.NOTIFICATION" />
<category android:name="android.intent.category.DEFAULT" />
</intent-filter>
[/code]
```

Replace the **com.example.project.app_name** with your Android project package name and the app_name string as it appears in the res/values/string.xml file. For example: com.sample.notifications.NativeAndroidNotifications.

Add the GCMIntentService and add an intent-filter for RECEIVE and REGISTRATION of notifications.

```
[code lang="xml"]

<service android:name="com.worklight.wlclient.push.GCMIntentService" />

<receiver android:name="com.worklight.wlclient.push.WLBroadcastReceiver"
android:permission="com.google.android.c2dm.permission.SEND">

<intent-filter>

<action android:name="com.google.android.c2dm.intent.RECEIVE" />

<category android:name="com.example.project" />

</intent-filter>

<action android:name="com.google.android.c2dm.intent.REGISTRATION" />

<category android:name="com.google.android.c2dm.intent.REGISTRATION" />

<category android:name="com.example.project" />

</intent-filter>

</irrceiver>[/code]
```

Replace all com.example.project with your Android project package name.

Android Push Notifications Service

The following ports must be open: 443, 5228, 5229, and 5230. GCM typically uses only 5228, but it sometimes uses 5229 and 5230.

GCM does not provide specific IP addresses, so you must allow your firewall to accept outgoing connections to all IP addresses that are contained in the IP blocks listed in Google ASN of 15169.

Notification Types