


Computer Networks

Amir Mahdi Sadeghzadeh, Ph.D.



Chapter 1 Introduction



Computer Networking: A Top-Down Approach

8th edition Jim Kurose, Keith Ross Pearson, 2020



The Internet: a "nuts and bolts" view



Billions of connected computing *devices*:

- hosts = end systems
- running network apps at Internet's "edge"





Packet switches: forward packets (chunks of data)

routers, switches




Communication links

- fiber, copper, radio, satellite
- transmission rate: bandwidth



Networks

collection of devices, routers, links: managed by an organization





Chapter 1: roadmap

- What is the Internet?
- What is a protocol?
- Network edge: hosts, access network, physical media
- Network core: packet/circuit switching, internet structure
- Performance: loss, delay, throughput
- Security
- Protocol layers, service models
- History






A closer look at Internet structure

Network edge:

- hosts: clients and servers
- servers often in data centers






A closer look at Internet structure

Network edge:

- hosts: clients and servers
- servers often in data centers

Access networks, physical media:

wired, wireless communication links





A closer look at Internet structure

Network edge:


- hosts: clients and servers
- servers often in data centers

Access networks, physical media:

wired, wireless communication links

Network core:

- interconnected routers
- network of networks







Access networks and physical media

Q: How to connect end systems to edge router?

- residential access nets
- institutional access networks (school, company)
- mobile access networks (WiFi, 4G/5G)



Access networks: digital subscriber line (DSL)




- use existing telephone line to central office DSLAM
 - data over DSL phone line goes to Internet
 - voice over DSL phone line goes to telephone net
- 24-52 Mbps dedicated downstream transmission rate
- 3.5-16 Mbps dedicated upstream transmission rate

- Audio frequency range of 0.3KHz to 3.4KHz
- The upper limit can be tens of MHz
- DSL takes advantage of this unused bandwidth
- Usable channels is then split into upstream and downstream traffic




Access networks: cable-based access



frequency division multiplexing (FDM): different channels transmitted in different frequency bands




Access networks: cable-based access



- HFC: hybrid fiber coax
 - asymmetric: up to 40 Mbps 1.2 Gbps downstream transmission rate, 30-100 Mbps upstream transmission rate
- network of cable, fiber attaches homes to ISP router
 - homes share access network to cable headend



Access networks: home networks






Wireless access networks

Shared wireless access network connects end system to router

via base station aka "access point"


Wireless local area networks (WLANs)

- typically within or around building (~100 ft)
- 802.11b/g/n (WiFi): 11, 54, 450Mbps transmission rate




Wide-area cellular access networks

- provided by mobile, cellular network operator (10's km)
- 10's Mbps
- 4G/5G cellular networks





Access networks: enterprise networks



- companies, universities, etc.
- mix of wired, wireless link technologies, connecting a mix of switches and routers (we'll cover differences shortly)
 - Ethernet: wired access at 100Mbps, 1Gbps, 10Gbps
 - WiFi: wireless access points at 11, 54, 450 Mbps




Access networks: data center networks

 high-bandwidth links (10s to 100s
 Gbps) connect hundreds to thousands of servers together, and to Internet



Courtesy: Massachusetts Green High Performance Computing Center (mghpcc.org)






Host: sends packets of data

host sending function:

- takes application message
- breaks into smaller chunks,
 known as packets, of length L bits
- transmits packet into access network at transmission rate R
 - link transmission rate, aka link capacity, aka link bandwidth



packet time needed to transmission = transmit
$$L$$
-bit = $\frac{L}{R}$ (bits/sec)




Links: physical media

- bit: propagates between transmitter/receiver pairs
- physical link: what lies between transmitter & receiver
- guided media:
 - signals propagate in solid media: copper, fiber, coax
- unguided media:
 - signals propagate freely, e.g., radio

Twisted pair (TP)

- two insulated copper wires
 - Category 5: 100 Mbps, 1 Gbps Ethernet
 - Category 6: 10Gbps Ethernet





Links: physical media

Coaxial cable:

- two concentric copper conductors
- bidirectional
- broadband:
 - multiple frequency channels on cable
 - 100's Mbps per channel



Fiber optic cable:

- glass fiber carrying light pulses, each pulse a bit
- high-speed operation:
 - high-speed point-to-point transmission (10's-100's Gbps)
- low error rate:
 - repeaters spaced far apart
 - immune to electromagnetic noise





Links: physical media

Wireless radio

- signal carried in various "bands" in electromagnetic spectrum
- no physical "wire"
- broadcast, "half-duplex" (sender to receiver)
- propagation environment effects:
 - reflection
 - obstruction by objects
 - Interference/noise

Radio link types:

- Wireless LAN (WiFi)
 - 10-100's Mbps; 10's of meters
- wide-area (e.g., 4G/5G cellular)
 - 10's Mbps (4G) over ~10 Km
- Bluetooth: cable replacement
 - short distances, limited rates
- terrestrial microwave
 - point-to-point; 45 Mbps channels
- satellite
 - up to < 100 Mbps (Starlink) downlink
 - 270 msec end-end delay (geostationary)



Chapter 1: roadmap


- What is the Internet?
- What is a protocol?
- Network edge: hosts, access network, physical media
- Network core: packet/circuit switching, internet structure
- Performance: loss, delay, throughput
- Security
- Protocol layers, service models
- History





The network core

- mesh of interconnected routers
- packet-switching: hosts break application-layer messages into packets
 - network forwards packets from one router to the next, across links on path from source to destination






Two key network-core functions

Forwarding:

- aka "switching"
- local action: move arriving packets from router's input link to appropriate router output link



Routing:

- global action: determine sourcedestination paths taken by packets
- routing algorithms












Packet-switching: store-and-forward




- packet transmission delay: takes L/R seconds to transmit (push out) L-bit packet into link at R bps
- store and forward: entire packet must arrive at router before it can be transmitted on next link

One-hop numerical example:

- *L* = 10 Kbits
- *R* = 100 Mbps
- one-hop transmission delay= 0.1 msec



Packet-switching: queueing



Queueing occurs when work arrives faster than it can be serviced:










Packet-switching: queueing



Packet queuing and loss: if arrival rate (in bps) to link exceeds transmission rate (bps) of link for some period of time:


- packets will queue, waiting to be transmitted on output link
- packets can be dropped (lost) if memory (buffer) in router fills up



Alternative to packet switching: circuit switching

end-end resources allocated to, reserved for "call" between source and destination

- in diagram, each link has four circuits.
 - call gets 2nd circuit in top link and 1st circuit in right link.
- dedicated resources: no sharing
 - circuit-like (guaranteed) performance
- circuit segment idle if not used by call (no sharing)
- commonly used in traditional telephone networks



^{*} Check out the online interactive exercises for more examples: http://gaia.cs.umass.edu/kurose_ross/interactive




Circuit switching: FDM and TDM


Frequency Division Multiplexing (FDM)

- optical, electromagnetic frequencies divided into (narrow) frequency bands
- each call allocated its own band, can transmit at max rate of that narrow band

Time Division Multiplexing (TDM)

- time divided into slots
- each call allocated periodic slot(s), can transmit at maximum rate of (wider) frequency band (only) during its time slot(s)








Packet switching versus circuit switching

example:

- 1 Gb/s link
- each user:
 - 100 Mb/s when "active"
 - active 10% of time



Q: how many users can use this network under circuit-switching and packet switching?

- circuit-switching: 10 users
- packet switching: with 35 users, probability > 10 active at same time is less than .0004 *

Q: how did we get value 0.0004?

^{*} Check out the online interactive exercises for more examples: http://gaia.cs.umass.edu/kurose_ross/interactive




Binomial Probability Distribution

- A fixed number of observations (trials), n
 - e.g., 20 tosses of a coin
- Binary random variable
 - e.g., Head or tail in coin toss
 - Often called as success or failure
 - Prob of success is p, and prob of failure is 1-p
- Constant probability for each observation



Binomial distribution

• If you have only two possible outcomes (call them 1/0 or yes/no or success/failure) in n independent trials, then the probability of exactly X "successes"






Packet switching versus circuit switching

example:

- 1 Gb/s link
- each user:
 - 100 Mb/s when "active"
 - active 10% of time



Q: how many users can use this network under circuit-switching and packet switching?

- circuit-switching: 10 users
- packet switching: with 35 users, probability > 10 active at same time is less than .0004 *

Q: how did we get value 0.0004?

A:
$$\sum_{n=11}^{35} {35 \choose n} p^n (1-p)^{35-n} \leq 0.0004$$

^{*} Check out the online interactive exercises for more examples: http://gaia.cs.umass.edu/kurose_ross/interactive



Packet switching versus circuit switching


Is packet switching a "slam dunk winner"?

- great for "bursty" data sometimes has data to send, but at other times not
 - resource sharing
 - simpler, no call setup
- excessive congestion possible: packet delay and loss due to buffer overflow
 - protocols needed for reliable data transfer, congestion control
- Q: How to provide circuit-like behavior with packet-switching?
 - "It's complicated." We'll study various techniques that try to make packet switching as "circuit-like" as possible.

Q: human analogies of reserved resources (circuit switching) versus on-demand allocation (packet switching)?




- hosts connect to Internet via access
 Internet Service Providers (ISPs)
- access ISPs in turn must be interconnected
 - so that *any* two hosts (anywhere!) can send packets to each other
- resulting network of networks is very complex
 - evolution driven by economics, national policies



Let's take a stepwise approach to describe current Internet structure




Question: given millions of access ISPs, how to connect them together?






Question: given millions of access ISPs, how to connect them together?






Option: connect each access ISP to one global transit ISP?

Customer and provider ISPs have economic agreement.






But if one global ISP is viable business, there will be competitors






But if one global ISP is viable business, there will be competitors who will want to be connected






... and regional networks may arise to connect access nets to ISPs






... and content provider networks (e.g., Google, Microsoft, Akamai) may run their own network, to bring services, content close to end users







At "center": small # of well-connected large networks

- "tier-1" commercial ISPs (e.g., Level 3, Sprint, AT&T, NTT), national & international coverage
- content provider networks (e.g., Google, Facebook): private network that connects its data centers to Internet, often bypassing tier-1, regional ISPs