




INTERVLAN USING SVI

Create vlan, port mapping & trunk configuration in layer2 switch-1

```
L2-SW-1
L2-SW-1(config)# vlan 10
L2-SW-1(config-vlan)#name HR
L2-SW-1(config-vlan)#ex
L2-SW-1(config)# vlan 20
L2-SW-1(config-vlan)#name SALES
L2-SW-1(config-vlan)#ex
L2-SW-1(config)#
L2-SW-1(config)#int e0/0
L2-SW-1(config-if)#sw a vlan 10
L2-SW-1(config-if)#ex
L2-SW-1(config)#
L2-SW-1(config)#int e0/1
L2-SW-1(config-if)#sw a vlan 20
*Sep 20 05:47:38.516: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (g Wizard)
L2-SW-1(config-if)#sw a vlan 20
L2-SW-1(config-if)#ex
```

Create vlan & trunk in layer3 switch

```
CORE
CORE(config)#vlan 10
CORE(config-vlan)#ex
CORE(config)#vlan 20
CORE(config-vlan)#ex
CORE(config)#
CORE(config)#int e0/
*Sep 20 05:51:45.269: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (g Wizard)
CORE(config)#int e0/0
CORE(config-if)#sw t en
CORE(config-if)#sw t encapsulation dot1q
CORE(config-if)#sw m t
CORE(config-if)#ex
```

Create SVI interface for both vlans

```
CORE
CORE(config)#interface vlan 10
CORE(config-if)#
*Sep 20 05:54:49.686: %LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan10, changed state to down
CORE(config-if)#ip add 10.0.0.1 255.0.0.0
CORE(config-if)#no sh
CORE(config-if)#ex
CORE(config)#
*Sep 20 05:55:16.912: %LINK-3-UPDOWN: Interface Vlan10, changed state to up
*Sep 20 05:55:17.912: %LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan10, changed state to up
CORE(config)#
CORE(config)#interface vlan 20
CORE(config-if)#ip add
*Sep 20 05:55:30.840: %LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan20, changed state to down
CORE(config-if)#ip add 20.0.0.1 255.0.0.0
CORE(config-if)#no sh
CORE(config-if)#ex
CORE(config)#
*Sep 20 05:55:46.483: %LINK-3-UPDOWN: Interface Vlan20, changed state to up
*Sep 20 05:55:47.483: %LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan20, changed state to up
CORE(config)#
```

Enable routing function in layer 3 switch

```
CORE
CORE(config)#
CORE(config)#ip rout
CORE(config)#ip routi
CORE(config)#ip routing
CORE(config)#
```

INTERVLAN USING ROUTER ON A STICK


Create vlan,port mapping & trunk configuration in layer2 switch-2

```
L2-SW-2
L2-SW-2(config)#vlan 10
L2-SW-2(config-vlan)#name HR
L2-SW-2(config-vlan)#ex
L2-SW-2(config)#vlan 20
L2-SW-2(config-vlan)#name SALES
L2-SW-2(config-vlan)#ex
L2-SW-2(config)#
L2-SW-2(config)#int e0/
*Sep 20 06:01:24.904: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery Wizard)
L2-SW-2(config)#int e0/0
L2-SW-2(config-if)#sw a vlan 10
L2-SW-2(config-if)#ex
L2-SW-2(config)#
L2-SW-2(config)#int e0/1
L2-SW-2(config-if)#sw a vlan 20
L2-SW-2(config-if)#ex
```


Create subinterface in cisco router

```
ROUTER
ROUTER(config)#int e0/0
ROUTER(config-if)#no sh
ROUTER(config-if)#ex
ROUTER(config)#
ROUTER(config)#int e0/0.1
ROUTER(config-subif)#encapsulation dot1q 10
ROUTER(config-subif)#ip add 30.0.0.1 255.0.0.0
ROUTER(config-subif)#no sh
ROUTER(config-subif)#ex
ROUTER(config)#
ROUTER(config)#int e0/0.2
ROUTER(config-subif)#encapsulation dot1q 20
ROUTER(config-subif)#ip add 40.0.0.1 255.0.0.0
ROUTER(config-subif)#no sh
ROUTER(config-subif)#ex
ROUTER(config-subif)#
```

L3 DEVICE INTERFACE IP CONFIGURATIONS



Add static Route



Connectivity check

