

the complete step-by-step guide to building a Windows Mobile / Pocket PC deployment .cab file with Start Menu integration directly inside Visual Studio.

### Step 1: Add the Smart Device CAB Project

1. Open your Windows Mobile application solution in Visual Studio.
2. In the **Solution Explorer**, right-click the top-level **Solution** node.
3. Select **Add > New Project...**
4. Expand **Other Project Types > Setup and Deployment**, then select **Smart Device CAB Project**.
5. Name your CAB project (e.g., `adan_setup`) and click **OK**.

### Step 2: Add Application Files and Primary Output

1. Right-click your new CAB project in the **Solution Explorer**, then select **View > File System**.
2. Click **Application Folder** in the left panel to highlight it.
3. In the right pane, right-click an empty space and select **Add > Project Output...**
4. Choose your main executable project (`adan`) from the dropdown, select **Primary output**, and click **OK**.
5. To include assets (audio files, icons, images):
  - o Right-click the right pane under **Application Folder** and select **Add > File...**
  - o Select your files (`adhan.wav`, `prefajr.wav`, `home.jpg`, `mute.jpg`, `icon.ico`) and click **Open**.

### Step 3: Set Up the Programs Menu Shortcut

1. In the left panel of the File System view, right-click **File System on Target Machine**.
2. Select **Add Special Folder > Programs Folder**.
3. Go back to **Application Folder** in the left panel.
4. Right-click **Primary output from adan (Active)** in the middle pane and click **Create Shortcut to Primary output from adan (Active)**.
5. Rename the generated shortcut to `Adan` (or the exact name you want displayed in the Start Menu).
6. Drag the renamed shortcut from the middle pane and drop it into **Programs Folder** in the left panel.

### Step 4: Configure Metadata and Target Paths

1. Click the CAB project name in **Solution Explorer**.
2. In the **Properties** window (bottom right):
  - o Set **Manufacturer** (e.g., your name or brand).
  - o Set **AppName** (e.g., `Adan`).
3. Click **Application Folder** in the File System view and verify in the Properties window that **Property** is set to `%InstallDir%` (this forces installation into `\Program Files\adan\` on the mobile device).

### Step 5: Build and Locate the CAB File

1. Set your solution configuration to **Release** (or **Debug**) in the top toolbar.
2. In **Solution Explorer**, right-click your CAB project node.
3. Click **Build**.
4. Once the output window shows `Build: 1 succeeded`, open your project folder on disk:  
`...\adan\adan_setup\Release\` (or `Debug\`)
5. Copy the compiled .cab file directly to your target device, SD card, or emulator to run the installation.