Pages / Copernicus Knowledge Base

Surface Radiation Parameters: Joule/m2 to Watt/m2

Created by Karl Hennermann, last modified by Paul Berrisford on Jun 12, 2018

For data produced at ECMWF, the radiation parameters for surface and single levels, e.g. Surface Solar Radiation, are so-called accumulated parameters, i.e. the data is accumulated over a certain time period. The units are Joule per square metre, accumulated over the respective period.

To get Watts per square metre, divide the accumulated values by the time period in seconds over which the data has been accumulated:

Examples

For **ERA5 daily** data (stream=oper), the accumulation period is 1 hour (3600 seconds). Hence to convert to W/m2:

```
SSR [W/m2] = SSR [J/m2] / (3600 seconds)
```

The result will be the average flux over the one hour ending at 'Step'.

For ERA5 daily ensemble data (stream=enda), the accumulation period is 3 hours. Hence to convert to W/m2:

```
SSR [W/m2] = SSR [J/m2] / (3 * 3600 seconds)
```

The result will be the average flux over the three hours ending at 'Step'.

More about ERA5 'steps'

List of ERA5 accumulated parameters (Table 3)

In ERA5, for "surface and single level parameters" mean rates are available, in addition to the accumulations. These mean rates represent the accumulation over a time period, divided by the length of the time period in seconds (in addition, the hydrological parameters have been scaled by the density of water). The units include "per second", such as W/m2. See the ERA5 data documentation, List of ERA5 mean rate parameters (Table 4).

For **ERA-Interim daily** data (as for ECMWF operational data), the accumulation period is specified by the 'Step', in hours from the beginning of the forecast. Hence to convert to W/m2:

```
SSR [W/m2] = SSR [J/m2] / ('Step' * 3600 seconds)
```

The result will be the average flux over 'Step' hours, from the beginning of the forecast.

More about ERA-Interim 'steps'

List of ERA-Interim surface accumulated parameters (Table 9)

The mean flux in a time interval is obtained by taking the difference of the accumulated values between the corresponding time steps divided by the time difference in seconds. The result is a mean value for that time interval.

Related articles

ERA5 data documentation

C3S seasonal forecasts known issues

C3S seasonal forecasts: wrong data of pressure level variables for DWD data

C3S seasonal forecasts: wrong values of snowfall amount for CMCC data

What is ERA5

c3s cams era-interim era5

Powered by a free **Atlassian Confluence Open Source Project License** granted to ECMWF. Evaluate Confluence today.

This Confluence installation runs a Free Gliffy License - Evaluate the Gliffy Confluence Plugin for your Wiki!