

## C interfaces to GALAHAD PRESOLVE

Jari Fowkes and Nick Gould STFC Rutherford Appleton Laboratory Tue Apr 5 2022

1 GALAHAD C package presolve		1
1.1 Introduction	 	 1
1.1.1 Purpose	 	 1
1.1.2 Authors	 	 1
1.1.3 Originally released	 	 2
1.1.4 Terminology	 	 2
1.1.5 Method	 	 2
1.1.6 Reference	 	 4
1.1.7 Call order	 	 4
1.1.8 Unsymmetric matrix storage formats	 	 4
1.1.8.1 Dense storage format	 	 5
1.1.8.2 Sparse co-ordinate storage format	 	 5
1.1.8.3 Sparse row-wise storage format	 	 5
1.1.9 Symmetric matrix storage formats	 	 5
1.1.9.1 Dense storage format	 	 5
1.1.9.2 Sparse co-ordinate storage format	 	 5
1.1.9.3 Sparse row-wise storage format	 	 5
1.1.9.4 Diagonal storage format	 	 6
1.1.9.5 Multiples of the identity storage format	 	 6
1.1.9.6 The identity matrix format	 	 6
1.1.9.7 The zero matrix format	 	 6
2 File Index		7
2.1 File List		7
2.11110 List	 	 ,
3 File Documentation		9
3.1 galahad_presolve.h File Reference	 	 9
3.1.1 Data Structure Documentation	 	 9
3.1.1.1 struct presolve_control_type	 	 9
3.1.1.2 struct presolve_inform_type	 	 15
3.1.2 Function Documentation	 	 19
3.1.2.1 presolve_initialize()	 	 19
3.1.2.2 presolve_read_specfile()	 	 19
3.1.2.3 presolve_import_problem()	 	 20
3.1.2.4 presolve_transform_problem()	 	 22
3.1.2.5 presolve_restore_solution()	 	 24
3.1.2.6 presolve_information()	 	 26
3.1.2.7 presolve_terminate()	 	 26
4 Example Documentation		27
4.1 presolvet.c		27
4.1 presolvetf.c		29
7.2 preservent.	 	 29
Index		33

## **Chapter 1**

## **GALAHAD C package presolve**

## 1.1 Introduction

#### 1.1.1 Purpose

Presolving aims to **improve the formulation of a given optimization problem by applying a sequence of simple transformations**, and thereby to produce a *reduced* problem in a *standard form* that should be simpler to solve. This reduced problem may then be passed to an appropriate solver. Once the reduced problem has been solved, it is then *restored* to recover the solution for the original formulation.

This package applies presolving techniques to a linear

minimize 
$$l(x) = g^T x + f$$

or quadratic program

$$\text{minimize} \ \ q(x) = \frac{1}{2} x^T H x + g^T x + f$$

subject to the general linear constraints

$$c_i^l \le a_i^T x \le c_i^u, \quad i = 1, \dots, m,$$

and the simple bound constraints

$$x_j^l \le x_j \le x_j^u, \quad j = 1, \dots, n,$$

where the n by n symmetric matrix H, the vectors g,  $a_i$ ,  $c^l$ ,  $c^u$ ,  $x^l$ ,  $x^u$  and the scalar f are given. Any of the constraint bounds  $c_i^l$ ,  $c_i^u$ ,  $x_i^l$  and  $x_i^u$  may be infinite.

In addition, bounds on the Lagrange multipliers y associated with the general linear constraints and on the dual variables z associated with the simple bound constraints

$$y_i^l \le y_i \le y_i^u, \quad i = 1, \dots, m,$$

and

$$z_i^l \le z_i \le z_i^u, \quad i = 1, \dots, n,$$

are also provided, where the m-dimensional vectors  $y^l$  and  $y^u$ , as well as the n-dimensional vectors  $x^l$  and  $x^u$  are given. Any component of  $c^l$ ,  $c^u$ ,  $x^l$ ,  $x^u$ ,  $y^l$ ,  $y^u$ ,  $z^l$  or  $z^u$  may be infinite.

#### 1.1.2 Authors

N. I. M. Gould, STFC-Rutherford Appleton Laboratory, England and Ph. L. Toint, University of Namur, Belgium

C interface, additionally J. Fowkes, STFC-Rutherford Appleton Laboratory.

## 1.1.3 Originally released

March 2002, C interface March 2022.

#### 1.1.4 Terminology

The required solution x necessarily satisfies the primal optimality conditions

$$Ax = c$$

and

$$(1b) c^l \le c \le c^u, \quad x^l \le x \le x^u,$$

the dual optimality conditions

where

(2b) 
$$y = y^l + y^u, z = z^l + z^u, y^l \ge 0, y^u \le 0, z^l \ge 0 \text{ and } z^u \le 0,$$

and the complementary slackness conditions

(3) 
$$(Ax - c^l)^T y^l = 0$$
,  $(Ax - c^u)^T y^u = 0$ ,  $(x - x^l)^T z^l = 0$  and  $(x - x^u)^T z^u = 0$ ,

where the vectors y and z are known as the Lagrange multipliers for 2 the general linear constraints, and the dual variables for the bounds, respectively, and where the vector inequalities hold component-wise.

#### 1.1.5 Method

The purpose of presolving is to exploit these equations in order to reduce the problem to the standard form defined as follows:

· The variables are ordered so that their bounds appear in the order

Fixed variables are removed. Within each category, the variables are further ordered so that those with non-zero diagonal Hessian entries occur before the remainder.

· The constraints are ordered so that their bounds appear in the order

Free constraints are removed.

1.1 Introduction 3

• In addition, constraints may be removed or bounds tightened, to reduce the size of the feasible region or simplify the problem if this is possible, and bounds may be tightened on the dual variables and the multipliers associated with the problem.

The presolving algorithm proceeds by applying a (potentially long) series of simple transformations to the problem, each transformation introducing a further simplification of the problem. These involve the removal of empty and singleton rows, the removal of redundant and forcing primal constraints, the tightening of primal and dual bounds, the exploitation of linear singleton, linear doubleton and linearly unconstrained columns, the merging dependent variables, row sparsification and split equalities. Transformations are applied in successive passes, each pass involving the following actions:

- 1. remove empty and singletons rows,
- 2. try to eliminate variables that are linearly unconstrained,
- 3. attempt to exploit the presence of linear singleton columns,
- 4. attempt to exploit the presence of linear doubleton columns,
- 5. complete the analysis of the dual constraints,
- 6. remove empty and singletons rows,
- 7. possibly remove dependent variables,
- 8. analyze the primal constraints,
- 9. try to make A sparser by combining its rows,
- 10. check the current status of the variables, dual variables and multipliers.

All these transformations are applied to the structure of the original problem, which is only permuted to standard form after all transformations are completed. *Note that the Hessian and Jacobian of the resulting reduced problem are always stored in sparse row-wise format.* The reduced problem is then solved by a quadratic or linear programming solver, thus ensuring sufficiently small primal-dual feasibility and complementarity. Finally, the solution of the simplified problem is re-translated in the variables/constraints/format of the original problem formulation by a *restoration* phase.

If the number of problem transformations exceeds <code>control.transf\_buffer\_size</code>, the transformation buffer size, then they are saved in a `'history'' file, whose name may be chosen by specifying the control.transf\_file\_name control parameter, When this is the case, this file is subsequently reread by <code>presolve\_restore\_solution</code>. It must not be altered by the user.

Overall, the presolving process follows one of the two sequences:

$$\begin{tabular}{ll} \hline initialize & \rightarrow & [apply transformations] & \rightarrow & (solve problem) & \rightarrow & [restore] & \rightarrow & [terminate] \\ \hline or & & \\ \hline initialize & \rightarrow & [read specfile] & \rightarrow & [apply transformations] & \rightarrow & (solve problem) & \rightarrow & [restore] & \rightarrow & [terminate] \\ \hline \end{tabular}$$

where the procedure's control parameter may be modified by reading the specifie, and where (solve problem) indicates that the reduced problem is solved. Each of the `boxed" steps in these sequences corresponds to calling a specific routine of the package In the diagrams above, brackated subsequence of steps means that they can be repeated with problem having the same structure. The value of the problem.new\_problem\_structure must be true on entry of presolve\_apply\_to\_problem on the first time it is used in this repeated subsequence. Such a subsequence must be terminated by a call to presolve\_terminate before presolving is applied to a problem with a different structure.

Note that the values of the multipliers and dual variables (and thus of their respective bounds) depend on the functional form assumed for the Lagrangian function associated with the problem. This form is given by

$$L(x, y, z) = qx) - y\_sign * y^T(Ax - c) - z\_sign * z,$$

(considering only active constraints Ax=c), where the parameters y\_{sign} and z\_{sign} are +1 or -1 and can be chosen by the user. Thus, if  $y_{sign}=+1$ , the multipliers associated to active constraints originally posed as inequalities are non-negative if the inequality is a lower bound and non-positive if it is an upper bound. Obvioulsy they are not constrained in sign for constraints originally posed as equalities. These sign conventions are reversed if  $y_{sign}=-1$ . Similarly, if  $z_{sign}=+1$ }, the dual variables associated to active bounds are non-negative if the original bound is an lower bound, non-positive if it is an upper bound, or unconstrained in sign if the variables is fixed; and this convention is reversed in  $z_{sign}=-1$ }. The values of  $z_{sign}$  and  $y_{sign}$  may be chosen by setting the corresponding components of the control structure to 1 or -1.

#### 1.1.6 Reference

The algorithm is described in more detail in

N. I. M. Gould and Ph. L. Toint (2004). Presolving for quadratic programming. Mathematical Programming **100**(1), pp 95–132.

#### 1.1.7 Call order

To solve a given problem, functions from the presolve package must be called in the following order:

- presolve\_initialize provide default control parameters and set up initial data structures
- · presolve\_read\_specfile (optional) override control values by reading replacement values from a file
- presolve\_import\_problem import the problem data and report the dimensions of the transformed problem
- presolve\_transform\_problem apply the presolve algorithm to transform the data
- presolve\_restore\_solution restore the solution from that of the transformed problem
- presolve\_information (optional) recover information about the solution and solution process
- presolve\_terminate deallocate data structures

See Section 4.1 for examples of use.

#### 1.1.8 Unsymmetric matrix storage formats

The unsymmetric m by n constraint matrix A may be presented and stored in a variety of convenient input formats.

Both C-style (0 based) and fortran-style (1-based) indexing is allowed. Choose control.f\_indexing as false for C style and true for fortran style; the discussion below presumes C style, but add 1 to indices for the corresponding fortran version.

Wrappers will automatically convert between 0-based (C) and 1-based (fortran) array indexing, so may be used transparently from C. This conversion involves both time and memory overheads that may be avoided by supplying data that is already stored using 1-based indexing.

1.1 Introduction 5

#### 1.1.8.1 Dense storage format

The matrix A is stored as a compact dense matrix by rows, that is, the values of the entries of each row in turn are stored in order within an appropriate real one-dimensional array. In this case, component n\*i+j of the storage array A\_val will hold the value  $A_{ij}$  for  $0 \le i \le m-1$ ,  $0 \le j \le n-1$ .

#### 1.1.8.2 Sparse co-ordinate storage format

Only the nonzero entries of the matrices are stored. For the l-th entry,  $0 \le l \le ne-1$ , of A, its row index i, column index j and value  $A_{ij}$ ,  $0 \le i \le m-1$ ,  $0 \le j \le n-1$ , are stored as the l-th components of the integer arrays A\_row and A\_col and real array A\_val, respectively, while the number of nonzeros is recorded as A\_ne = ne.

#### 1.1.8.3 Sparse row-wise storage format

Again only the nonzero entries are stored, but this time they are ordered so that those in row i appear directly before those in row i+1. For the i-th row of A the i-th component of the integer array A\_ptr holds the position of the first entry in this row, while A\_ptr(m) holds the total number of entries plus one. The column indices j,  $0 \le j \le n-1$ , and values  $A_{ij}$  of the nonzero entries in the i-th row are stored in components I = A\_ptr(i), ..., A\_ptr(i+1)-1,  $0 \le i \le m-1$ , of the integer array A\_col, and real array A\_val, respectively. For sparse matrices, this scheme almost always requires less storage than its predecessor.

#### 1.1.9 Symmetric matrix storage formats

Likewise, the symmetric n by n objective Hessian matrix H may be presented and stored in a variety of formats. But crucially symmetry is exploited by only storing values from the lower triangular part (i.e, those entries that lie on or below the leading diagonal).

#### 1.1.9.1 Dense storage format

The matrix H is stored as a compact dense matrix by rows, that is, the values of the entries of each row in turn are stored in order within an appropriate real one-dimensional array. Since H is symmetric, only the lower triangular part (that is the part  $h_{ij}$  for  $0 \le j \le i \le n-1$ ) need be held. In this case the lower triangle should be stored by rows, that is component i\*i/2+j of the storage array H\_val will hold the value  $h_{ij}$  (and, by symmetry,  $h_{ji}$ ) for  $0 \le j \le i \le n-1$ .

#### 1.1.9.2 Sparse co-ordinate storage format

Only the nonzero entries of the matrices are stored. For the l-th entry,  $0 \le l \le ne-1$ , of H, its row index i, column index j and value  $h_{ij}$ ,  $0 \le j \le i \le n-1$ , are stored as the l-th components of the integer arrays H\_row and H\_col and real array H\_val, respectively, while the number of nonzeros is recorded as H\_ne = ne. Note that only the entries in the lower triangle should be stored.

#### 1.1.9.3 Sparse row-wise storage format

Again only the nonzero entries are stored, but this time they are ordered so that those in row i appear directly before those in row i+1. For the i-th row of H the i-th component of the integer array H\_ptr holds the position of the first entry in this row, while H\_ptr(n) holds the total number of entries plus one. The column indices j,  $0 \le j \le i$ , and values  $h_{ij}$  of the entries in the i-th row are stored in components I = H\_ptr(i), ..., H\_ptr(i+1)-1 of the integer array H\_col, and real array H\_val, respectively. Note that as before only the entries in the lower triangle should be stored. For sparse matrices, this scheme almost always requires less storage than its predecessor.

#### 1.1.9.4 Diagonal storage format

If H is diagonal (i.e.,  $H_{ij}=0$  for all  $0 \le i \ne j \le n-1$ ) only the diagonals entries  $H_{ii}$ ,  $0 \le i \le n-1$  need be stored, and the first n components of the array H\_val may be used for the purpose.

## 1.1.9.5 Multiples of the identity storage format

If H is a multiple of the identity matrix, (i.e.,  $H=\alpha I$  where I is the n by n identity matrix and  $\alpha$  is a scalar), it suffices to store  $\alpha$  as the first component of H\_val.

### 1.1.9.6 The identity matrix format

If H is the identity matrix, no values need be stored.

#### 1.1.9.7 The zero matrix format

The same is true if H is the zero matrix.

# Chapter 2

# File Index

## 2.1 File List

Here is a list of all files with brief descriptions:	
galahad_presolve.h	9

8 File Index

## **Chapter 3**

## **File Documentation**

## 3.1 galahad presolve.h File Reference

```
#include <stdbool.h>
#include "galahad_precision.h"
```

#### **Data Structures**

- struct presolve\_control\_type
- struct presolve\_inform\_type

#### **Functions**

- void presolve\_initialize (void \*\*data, struct presolve\_control\_type \*control, int \*status)
- void presolve\_read\_specfile (struct presolve\_control\_type \*control, const char specfile[])
- void presolve\_import\_problem (struct presolve\_control\_type \*control, void \*\*data, int \*status, int n, int m, const char H\_type[], int H\_ne, const int H\_row[], const int H\_col[], const int H\_ptr[], const real\_wp\_ H\_val[], const real\_wp\_g[], const real\_wp\_f, const char A\_type[], int A\_ne, const int A\_row[], const int A\_col[], const int A\_ptr[], const real\_wp\_ A\_val[], const real\_wp\_ c\_l[], const real\_wp\_ c\_u[], const real\_wp\_ x\_l[], con
- void presolve\_transform\_problem (void \*\*data, int \*status, int n, int m, int H\_ne, int H\_col[], int H\_ptr[], real—
   \_wp\_ H\_val[], real\_wp\_ g[], real\_wp\_ \*f, int A\_ne, int A\_col[], int A\_ptr[], real\_wp\_ A\_val[], real\_wp\_ c\_l[],
   real\_wp\_ c\_u[], real\_wp\_ x\_l[], real\_wp\_ y\_l[], real\_wp\_ y\_u[], real\_wp\_ z\_l[], real\_wp\_
   z\_u[])
- void presolve\_restore\_solution (void \*\*data, int \*status, int n\_in, int m\_in, const real\_wp\_ x\_in[], const real\_wp\_ c\_in[], const real\_wp\_ z\_in[], int n, int m, real\_wp\_ x[], real\_wp\_ c[], real\_wp\_ y[], real\_wp\_ z[])
- void presolve information (void \*\*data, struct presolve inform type \*inform, int \*status)
- void presolve\_terminate (void \*\*data, struct presolve\_control\_type \*control, struct presolve\_inform\_type \*inform)

#### 3.1.1 Data Structure Documentation

#### 3.1.1.1 struct presolve\_control\_type

control derived type as a C struct

**Examples** 

presolvet.c, and presolvetf.c.

bool	f_indexing	use C or Fortran sparse matrix indexing
int	termination	Determines the strategy for terminating the presolve analysis. Possible values are:
		<ul> <li>1 presolving is continued as long as one of the sizes of the problem (n, m, a_ne, or h_ne) is being reduced;</li> </ul>
		<ul> <li>2 presolving is continued as long as problem transformations remain possible. NOTE: the maximum number of analysis passes (control.max_nbr_passes) and the maximum number of problem transformations (control.max_nbr_transforms) set an upper limit on the presolving effort irrespective of the choice of control.termination. The only effect of this latter parameter is to allow for early termination.</li> </ul>
int	max_nbr_transforms	The maximum number of problem transformations, cumulated over all calls to presolve.
int	max_nbr_passes	The maximum number of analysis passes for problem analysis during a single call of presolve_transform_problem.
real_wp_	c_accuracy	The relative accuracy at which the general linear constraints are satisfied at the exit of the solver. Note that this value is not used before the restoration of the problem.
real_wp_	z_accuracy	The relative accuracy at which the dual feasibility constraints are satisfied at the exit of the solver. Note that this value is not used before the restoration of the problem.
real_wp_	infinity	The value beyond which a number is deemed equal to plus infinity (minus infinity being defined as its opposite)
int	out	The unit number associated with the device used for printout.
int	errout	The unit number associated with the device used for error ouput.
int	print_level	The level of printout requested by the user. Can take the values:
		0 no printout is produced
		1 only reports the major steps in the analysis
		2 reports the identity of each problem transformation
		3 reports more details
		4 reports lots of information.
		5 reports a completely silly amount of information
bool	dual_transformations	true if dual transformations of the problem are allowed. Note that this implies that the reduced problem is solved accurately (for the dual feasibility condition to hold) as to be able to restore the problem to the original constraints and variables. false prevents dual transformations to be applied, thus allowing for inexact solution of the reduced problem. The setting of this control parameter overides that of get_z, get_z_bounds, get_y, get_y_bounds, dual_constraints_freq, singleton_columns_freq, doubleton_columns_freq, z_accuracy, check_dual_feasibility.
bool	redundant_xc	true if the redundant variables and constraints (i.e. variables that do not appear in the objective function and appear with a consistent sign in the constraints) are to be removed with their associated constraints before other transformations are attempted.

int	primal_constraints_freq	The frequency of primal constraints analysis in terms of presolving passes. A value of $j=2$ indicates that primal constraints are analyzed every 2 presolving passes. A zero value indicates that they are never analyzed.
int	dual_constraints_freq	The frequency of dual constraints analysis in terms of presolving passes. A value of $j=2$ indicates that dual constraints are analyzed every 2 presolving passes. A zero value indicates that they are never analyzed.
int	singleton_columns_freq	The frequency of singleton column analysis in terms of presolving passes. A value of $j=2$ indicates that singleton columns are analyzed every 2 presolving passes. A zero value indicates that they are never analyzed.
int	doubleton_columns_freq	The frequency of doubleton column analysis in terms of presolving passes. A value of j indicates that doubleton columns are analyzed every 2 presolving passes. A zero value indicates that they are never analyzed.
int	unc_variables_freq	The frequency of the attempts to fix linearly unconstrained variables, expressed in terms of presolving passes. A value of $j=2$ indicates that attempts are made every 2 presolving passes. A zero value indicates that no attempt is ever made.
int	dependent_variables_freq	The frequency of search for dependent variables in terms of presolving passes. A value of $j=2$ indicates that dependent variables are searched for every 2 presolving passes. A zero value indicates that they are never searched for.
int	sparsify_rows_freq	The frequency of the attempts to make A sparser in terms of presolving passes. A value of j = 2 indicates that attempts are made every 2 presolving passes. A zero value indicates that no attempt is ever made.
int	max_fill	The maximum percentage of fill in each row of A. Note that this is a row-wise measure: globally fill never exceeds the storage initially used for A, no matter how large control.max_fill is chosen. If max_fill is negative, no limit is put on row fill.
int	transf_file_nbr	The unit number to be associated with the file(s) used for saving problem transformations on a disk file.
int	transf_buffer_size	The number of transformations that can be kept in memory at once (that is without being saved on a disk file).
int	transf_file_status	The exit status of the file where problem transformations are saved:  • 0 the file is not deleted after program termination  • 1 the file is not deleted after program termination
char	transf_file_name[31]	The name of the file (to be) used for storing problem transformation on disk. NOTE: this parameter must be identical for all calls to presolve following presolve_read_specfile. It can then only be changed after calling presolve_terminate.

int	y_sign	Determines the convention of sign used for the multipliers associated with the general linear constraints.
		<ul> <li>1 All multipliers corresponding to active inequality constraints are non-negative for lower bound constraints and non-positive for upper bounds constraints.</li> </ul>
		<ul> <li>-1 All multipliers corresponding to active inequality constraints are non-positive for lower bound constraints and non-negative for upper bounds constraints.</li> </ul>
int	inactive_y	Determines whether or not the multipliers corresponding to constraints that are inactive at the unreduced point corresponding to the reduced point on input to presolve_restore_solution must be set to zero. Possible values are: associated with the general linear constraints.
		<ul> <li>0 All multipliers corresponding to inactive inequality constraints are forced to zero, possibly at the expense of deteriorating the dual feasibility condition.</li> </ul>
		<ul> <li>1 Multipliers corresponding to inactive inequality constraints are left unaltered.</li> </ul>
int	z_sign	Determines the convention of sign used for the dual variables associated with the bound constraints.
		1 All dual variables corresponding to active lower bounds are non-negative, and non-positive for active upper bounds.
		<ul> <li>-1 All dual variables corresponding to active lower bounds are non-positive, and non-negative for active upper bounds.</li> </ul>
int	inactive_z	Determines whether or not the dual variables corresponding to bounds that are inactive at the unreduced point corresponding to the reduced point on input to presolve_restore_solution must be set to zero. Possible values are: associated with the general linear constraints.
		<ul> <li>0: All dual variables corresponding to inactive bounds are forced to zero, possibly at the expense of deteriorating the dual feasibility condition.</li> </ul>
		1 Dual variables corresponding to inactive bounds are left unaltered.

int	final_x_bounds	The type of final bounds on the variables returned by the package.  This parameter can take the values:
		<ul> <li>0 the final bounds are the tightest bounds known on the variables (at the risk of being redundant with other constraints, which may cause degeneracy);</li> </ul>
		<ul> <li>1 the best known bounds that are known to be non-degenerate. This option implies that an additional real workspace of size 2 * n must be allocated.</li> </ul>
		<ul> <li>2 the loosest bounds that are known to keep the problem equivalent to the original problem. This option also implies that an additional real workspace of size 2 * n must be allocated.</li> </ul>
		NOTE: this parameter must be identical for all calls to presolve (except presolve_initialize).
int	final_z_bounds	The type of final bounds on the dual variables returned by the package. This parameter can take the values:
		<ul> <li>0 the final bounds are the tightest bounds known on the dual variables (at the risk of being redundant with other constraints, which may cause degeneracy);</li> </ul>
		<ul> <li>1 the best known bounds that are known to be non-degenerate. This option implies that an additional real workspace of size 2 * n must be allocated.</li> </ul>
		<ul> <li>2 the loosest bounds that are known to keep the problem equivalent to the original problem. This option also implies that an additional real workspace of size 2 * n must be allocated.</li> </ul>
		NOTE: this parameter must be identical for all calls to presolve (except presolve_initialize).
int	final_c_bounds	The type of final bounds on the constraints returned by the package. This parameter can take the values:
		<ul> <li>0 the final bounds are the tightest bounds known on the constraints (at the risk of being redundant with other constraints, which may cause degeneracy);</li> </ul>
		1 the best known bounds that are known to be non-degenerate. This option implies that an additional real workspace of size 2 * m must be allocated.
		<ul> <li>2 the loosest bounds that are known to keep the problem equivalent to the original problem. This option also implies that an additional real workspace of size 2 * n must be allocated.</li> </ul>
		NOTES: 1) This parameter must be identical for all calls to presolve (except presolve_initialize). 2) If different from 0, its value must be identical to that of control.final_x_bounds.

int	final_y_bounds	The type of final bounds on the multipliers returned by the package. This parameter can take the values:
		0 the final bounds are the tightest bounds known on the multipliers (at the risk of being redundant with other constraints, which may cause degeneracy);
		<ul> <li>1 the best known bounds that are known to be non-degenerate. This option implies that an additional real workspace of size 2 * m must be allocated.</li> </ul>
		<ul> <li>2 the loosest bounds that are known to keep the problem equivalent to the original problem. This option also implies that an additional real workspace of size 2 * n must be allocated.</li> </ul>
		NOTE: this parameter must be identical for all calls to presolve (except presolve_initialize).
int	check_primal_feasibility	The level of feasibility check (on the values of $x$ ) at the start of the restoration phase. This parameter can take the values:
		0 no check at all;
		<ul> <li>1 the primal constraints are recomputed at x and a message issued if the computed value does not match the input value, or if it is out of bounds (if control.print_level &gt;= 2);</li> </ul>
		<ul> <li>2 the same as for 1, but presolve is terminated if an incompatibility is detected.</li> </ul>
int	check_dual_feasibility	The level of dual feasibility check (on the values of x, y and z) at the start of the restoration phase. This parameter can take the values:
		0 no check at all;
		<ul> <li>1 the dual feasibility condition is recomputed at (x, y, z) and a message issued if the computed value does not match the input value (if control.print_level &gt;= 2);</li> </ul>
		<ul> <li>2 the same as for 1, but presolve is terminated if an incompatibility is detected. The last two values imply the allocation of an additional real workspace vector of size equal to the number of variables in the reduced problem.</li> </ul>
real_wp_	pivot_tol	The relative pivot tolerance above which pivoting is considered as numerically stable in transforming the coefficient matrix A. A zero value corresponds to a totally unsafeguarded pivoting strategy (potentially unstable).
real_wp_	min_rel_improve	The minimum relative improvement in the bounds on x, y and z for a tighter bound on these quantities to be accepted in the course of the analysis. More formally, if lower is the current value of the lower bound on one of the x, y or z, and if new_lower is a tentative tighter lower bound on the same quantity, it is only accepted if. new_lower $>=$ lower + tol * MAX( 1, ABS( lower ) ), where
		tol = control.min_rel_improve.  Similarly, a tentative tighter upper bound new_upper only replaces the current upper bound upper if
		new_upper <= upper - tol * MAX( 1, ABS( upper ) ).  Note that this parameter must exceed the machine precision significantly.

## Data Fields

real_wp_	max_growth_factor	The maximum growth factor (in absolute value) that is accepted	
		between the maximum data item in the original problem and any data	
		item in the reduced problem. If a transformation results in this bound	
		being exceeded, the transformation is skipped.	

## 3.1.1.2 struct presolve\_inform\_type

inform derived type as a C struct

## Examples

presolvet.c, and presolvetf.c.

#### Data Fields

## int status

The presolve exit condition. It can take the following values (symbol in parentheses is the related Fortran code):

- · (OK) successful exit;
- 1 (MAX\_NBR\_TRANSF) the maximum number of problem transformation has been reached NOTE: this exit is not really an error, since the problem can nevertheless be permuted and solved. It merely signals that further problem reduction could possibly be obtained with a larger value of the parameter control.max\_nbr\_transforms
- -21 (PRIMAL\_INFEASIBLE) the problem is primal infeasible;
- -22 (DUAL\_INFEASIBLE) the problem is dual infeasible;
- -23 (WRONG\_G\_DIMENSION) the dimension of the gradient is incompatible with the problem dimension;
- -24 (WRONG\_HVAL\_DIMENSION) the dimension of the vector containing the entries of the Hessian is erroneously specified;
- -25 (WRONG\_HPTR\_DIMENSION) the dimension of the vector containing the addresses of the first entry of each Hessian row is erroneously specified;
- -26 (WRONG\_HCOL\_DIMENSION) the dimension of the vector containing the column indices of the nonzero Hessian entries is erroneously specified;
- -27 (WRONG\_HROW\_DIMENSION) the dimension of the vector containing the row indices of the nonzero Hessian entries is erroneously specified;
- -28 (WRONG\_AVAL\_DIMENSION) the dimension of the vector containing the entries of the Jacobian is erroneously specified;
- -29 (WRONG\_APTR\_DIMENSION) the dimension of the vector containing the addresses of the first entry of each Jacobian row is erroneously specified;
- -30 (WRONG\_ACOL\_DIMENSION) the dimension of the vector containing the column indices of the nonzero Jacobian entries is erroneously specified;
- -31 (WRONG\_AROW\_DIMENSION) the dimension of the vector containing the row indices of the nonzero Jacobian entries is erroneously specified;
- -32 (WRONG\_X\_DIMENSION) the dimension of the vector of variables is incompatible with the problem dimension;
- -33 (WRONG\_XL\_DIMENSION) the dimension of the vector of lower bounds on the variables is incompatible with the problem dimension;
- -34 (WRONG\_XU\_DIMENSION) the dimension of the vector of upper bounds on the variables is incompatible with the problem dimension;
- -35 (WRONG\_Z\_DIMENSION) the dimension of the vector of dual variables is incompatible with the problem dimension;
- -36 (WRONG\_ZL\_DIMENSION) the dimension of the vector of lower bounds on the dual variables is incompatible with the problem dimension;
- -37 (WRONG\_ZU\_DIMENSION) the dimension of the vector of upper bounds on the dual variables is incompatible with the problem dimension;

#### Data Fields

## int status continue

continuation of status (name in previous column should be status, doxygen issue):

- -38 (WRONG\_C\_DIMENSION) the dimension of the vector of constraints values is incompatible with the problem dimension;
- -39 (WRONG\_CL\_DIMENSION) the dimension of the vector of lower bounds on the constraints is incompatible with the problem dimension;
- -40 (WRONG\_CU\_DIMENSION) the dimension of the vector of upper bounds on the constraints is incompatible with the problem dimension;
- -41 (WRONG\_Y\_DIMENSION) the dimension of the vector of multipliers values is incompatible with the problem dimension;
- -42 (WRONG\_YL\_DIMENSION) the dimension of the vector of lower bounds on the multipliers is incompatible with the problem dimension;
- -43 (WRONG\_YU\_DIMENSION) the dimension of the vector of upper bounds on the multipliers is incompatible with the problem dimension:
- -44 (STRUCTURE\_NOT\_SET) the problem structure has not been set or has been cleaned up before an attempt to analyze;
- -45 (PROBLEM\_NOT\_ANALYZED) the problem has not been analyzed before an attempt to permute it;
- -46 (PROBLEM\_NOT\_PERMUTED) the problem has not been permuted or fully reduced before an attempt to restore it
- -47 (H\_MISSPECIFIED) the column indices of a row of the sparse Hessian are not in increasing order, in that they specify an entry above the diagonal;
- -48 (CORRUPTED\_SAVE\_FILE) one of the files containing saved problem transformations has been corrupted between writing and reading;
- -49 (WRONG\_XS\_DIMENSION) the dimension of the vector of variables' status is incompatible with the problem dimension:
- -50 (WRONG\_CS\_DIMENSION) the dimension of the vector of constraints' status is incompatible with the problem dimension;
- -52 (WRONG N) the problem does not contain any (active) variable;
- -53 (WRONG\_M) the problem contains a negative number of constraints;
- -54 (SORT TOO LONG) the vectors are too long for the sorting routine;
- -55 (X\_OUT\_OF\_BOUNDS) the value of a variable that is obtained by substitution from a constraint is incoherent with the variable's bounds. This may be due to a relatively loose accuracy on the linear constraints. Try to increase control.c\_accuracy.
- -56 (X\_NOT\_FEASIBLE) the value of a constraint that is obtained by recomputing its value on input of presolve\_restore\_solution from the current x is incompatible with its declared value or its bounds. This may caused the restored problem to be infeasible.

int	status_continued	continuation of status (name in previous column should be status, doxygen issue):
		• -58 (Z_CANNOT_BE_ZEROED) a dual variable whose value is nonzero because the corresponding primal is at an artificial bound cannot be zeroed while maintaining dual feasibility (on restoration). This can happen when $(x,y,z)$ on input of RESTORE are not (sufficiently) optimal.
		-1 (MEMORY_FULL) memory allocation failed
		<ul> <li>-2 (FILE_NOT_OPENED) a file intended for saving problem transformations could not be opened;</li> </ul>
		<ul> <li>-3 (COULD_NOT_WRITE) an IO error occurred while saving transformations on the relevant disk file;</li> </ul>
		-4 (TOO_FEW_BITS_PER_BYTE) an integer contains less than NBRH + 1 bits.
		-60 (UNRECOGNIZED_KEYWORD) a keyword was not recognized in the analysis of the specification file
		<ul> <li>-61 (UNRECOGNIZED_VALUE) a value was not recognized in the analysis of the specification file</li> </ul>
		-63 (G_NOT_ALLOCATED) the vector G has not been allocated although it has general values
		• -64 (C_NOT_ALLOCATED) the vector C has not been allocated although m > 0
		<ul> <li>-65 (AVAL_NOT_ALLOCATED) the vector A.val has not been allocated although m &gt; 0</li> </ul>
		<ul> <li>-66 (APTR_NOT_ALLOCATED) the vector A.ptr has not been allocated although m &gt; 0 and A is stored in row-wise sparse format</li> </ul>
		<ul> <li>-67 (ACOL_NOT_ALLOCATED) the vector A.col has not been allocated although m &gt; 0 and A is stored in row-wise sparse format or sparse coordinate format</li> </ul>
		-68 (AROW_NOT_ALLOCATED) the vector A.row has not been allocated although m > 0 and A is stored in sparse coordinate format
		<ul> <li>-69 (HVAL_NOT_ALLOCATED) the vector H.val has not been allocated although H.ne &gt; 0</li> </ul>
		-70 (HPTR_NOT_ALLOCATED) the vector H.ptr has not been allocated although H.ne > 0 and H is stored in row-wise sparse format
		<ul> <li>-71 (HCOL_NOT_ALLOCATED) the vector H.col has not been allocated although H.ne &gt; 0 and H is stored in row-wise sparse format or sparse coordinate format</li> </ul>
		-72 (HROW_NOT_ALLOCATED) the vector H.row has not been allocated although H.ne > 0 and A is stored in sparse coordinate format
		• -73 (WRONG_ANE) incompatible value of A_ne
		-74 (WRONG_HNE) incompatible value of H_ne
int	nbr_transforms	The final number of problem transformations, as reported to the user at exit.

#### Data Fields

char	message[3][81]	A few lines containing a description of the exit condition on exit of PRESOLVE,	
		typically including more information than indicated in the description of	
		control.status above. It is printed out on device errout at the end of execution if	
		control.print_level >= 1.	

### 3.1.2 Function Documentation

### 3.1.2.1 presolve\_initialize()

Set default control values and initialize private data

#### **Parameters**

in,out	data	holds private internal data
out	control	is a struct containing control information (see presolve_control_type)
out	status	is a scalar variable of type int, that gives the exit status from the package. Possible values are (currently):
		0. The import was succesful.

### Examples

presolvet.c, and presolvetf.c.

### 3.1.2.2 presolve\_read\_specfile()

Read the content of a specification file, and assign values associated with given keywords to the corresponding control parameters

in,out	control	is a struct containing control information (see presolve_control_type)
in	specfile	is a character string containing the name of the specification file

#### 3.1.2.3 presolve\_import\_problem()

```
void presolve_import_problem (
             struct presolve_control_type * control,
             void ** data,
             int * status,
             int n,
             int m_{*}
             const char H_type[],
             int H_ne,
             const int H_row[],
             const int H_col[],
             const int H_ptr[],
             const real_wp_ H_val[],
             const real_wp_ g[],
             const real_wp_ f,
             const char A_type[],
             int A_ne,
             const int A_row[],
             const int A_{col[]},
             const int A_ptr[],
             const real_wp_ A_val[],
             const real_wp_ c_1[],
             const real_wp_ c_u[],
             const real_wp_ x_1[],
             const real_wp_ x_u[],
             int * n_out,
             int * m_out,
             int * H_ne_out,
             int * A_ne_out )
```

Import the initial data, and apply the presolve algorithm to report crucial characteristics of the transformed variant

in	control	is a struct whose members provide control paramters for the remaining prcedures
		(see presolve_control_type)
in,out	data	holds private internal data

in,out	status	is a scalar variable of type int, that gives the exit status from the package. Possible values are:
		0. The import was succesful
		<ul> <li>-1. An allocation error occurred. A message indicating the offending array is written on unit control.error, and the returned allocation status and a string containing the name of the offending array are held in inform.alloc_status and inform.bad_alloc respectively.</li> </ul>
		<ul> <li>-2. A deallocation error occurred. A message indicating the offending array is written on unit control.error and the returned allocation status and a string containing the name of the offending array are held in inform.alloc_status and inform.bad_alloc respectively.</li> </ul>
		-3. The restrictions $n>0$ or $m>0$ or requirement that a type contains its relevant string 'dense', 'coordinate', 'sparse_by_rows' or 'diagonal' has been violated.
		23. An entry from the strict upper triangle of ${\cal H}$ has been specified.
in	n	is a scalar variable of type int, that holds the number of variables.
in	m	is a scalar variable of type int, that holds the number of general linear constraints.
in	H_type	is a one-dimensional array of type char that specifies the symmetric storage scheme used for the Hessian, $H$ . It should be one of 'coordinate', 'sparse_by_rows', 'dense', 'diagonal', 'scaled_identity', 'identity', 'zero' or 'none', the latter pair if $H=0$ ; lower or upper case variants are allowed.
in	H_ne	is a scalar variable of type int, that holds the number of entries in the lower triangular part of $H$ in the sparse co-ordinate storage scheme. It need not be set for any of the other schemes.
in	H_row	is a one-dimensional array of size $H_n$ e and type int, that holds the row indices of the lower triangular part of $H$ in the sparse co-ordinate storage scheme. It need not be set for any of the other three schemes, and in this case can be NULL.
in	H_col	is a one-dimensional array of size $H_n$ e and type int, that holds the column indices of the lower triangular part of $H$ in either the sparse co-ordinate, or the sparse row-wise storage scheme. It need not be set when the dense, diagonal or (scaled) identity storage schemes are used, and in this case can be NULL.
in	H_ptr	is a one-dimensional array of size $n+1$ and type int, that holds the starting position of each row of the lower triangular part of $H$ , as well as the total number of entries plus one, in the sparse row-wise storage scheme. It need not be set when the other schemes are used, and in this case can be NULL.
in	H_val	is a one-dimensional array of size h_ne and type double, that holds the values of the entries of the lower triangular part of the Hessian matrix $H$ in any of the available storage schemes.
in	g	is a one-dimensional array of size n and type double, that holds the linear term $g$ of the objective function. The j-th component of g, j = 0,, n-1, contains $g_j$ .
in	f	is a scalar of type double, that holds the constant term $f$ of the objective function.
in	A_type	is a one-dimensional array of type char that specifies the unsymmetric storage scheme used for the constraint Jacobian, $A$ . It should be one of 'coordinate', 'sparse_by_rows' or 'dense; lower or upper case variants are allowed.
in	A_ne	is a scalar variable of type int, that holds the number of entries in $A$ in the sparse co-ordinate storage scheme. It need not be set for any of the other schemes.
in	A_row	is a one-dimensional array of size A_ne and type int, that holds the row indices of $A$ in the sparse co-ordinate storage scheme. It need not be set for any of the other schemes, and in this case can be NULL.

### **Parameters**

in	A_col	is a one-dimensional array of size A_ne and type int, that holds the column indices of $A$ in either the sparse co-ordinate, or the sparse row-wise storage scheme. It need not be set when the dense or diagonal storage schemes are used, and in this case can be NULL.
in	A_ptr	is a one-dimensional array of size $n+1$ and type int, that holds the starting position of each row of $A$ , as well as the total number of entries plus one, in the sparse row-wise storage scheme. It need not be set when the other schemes are used, and in this case can be NULL.
in	A_val	is a one-dimensional array of size a_ne and type double, that holds the values of the entries of the constraint Jacobian matrix $A$ in any of the available storage schemes.
in	c_I	is a one-dimensional array of size m and type double, that holds the lower bounds $c^l$ on the constraints $Ax$ . The i-th component of c_l, i = 0,, m-1, contains $c^l_i$ .
in	c_u	is a one-dimensional array of size m and type double, that holds the upper bounds $c^l$ on the constraints $Ax$ . The i-th component of c_u, i = 0,, m-1, contains $c^u_i$ .
in	x_I	is a one-dimensional array of size n and type double, that holds the lower bounds $x^l$ on the variables $x$ . The j-th component of x_l, j = 0,, n-1, contains $x_j^l$ .
in	x_u	is a one-dimensional array of size n and type double, that holds the upper bounds $x^l$ on the variables $x$ . The j-th component of x_u, j = 0,, n-1, contains $x^l_j$ .
out	n_out	is a scalar variable of type int, that holds the number of variables in the transformed problem.
out	m_out	is a scalar variable of type int, that holds the number of general linear constraints in the transformed problem.
out	H_ne_out	is a scalar variable of type int, that holds the number of entries in the lower triangular part of ${\cal H}$ in the transformed problem.
out	A_ne_out	is a scalar variable of type int, that holds the number of entries in ${\cal A}$ in the transformed problem.

## **Examples**

presolvet.c, and presolvetf.c.

### 3.1.2.4 presolve\_transform\_problem()

```
void presolve_transform_problem (
    void ** data,
    int * status,
    int n,
    int m,
    int H_ne,
    int H_col[],
    int H_ptr[],
    real_wp_ H_val[],
    real_wp_ g[],
    real_wp_ * f,
    int A_ne,
    int A_col[],
    int A_ptr[],
```

```
real_wp_ A_val[],
real_wp_ c_l[],
real_wp_ c_u[],
real_wp_ x_l[],
real_wp_ x_u[],
real_wp_ y_l[],
real_wp_ y_u[],
real_wp_ z_l[],
```

Apply the presolve algorithm to simplify the input problem, and output the transformed variant

in,out	data	holds private internal data
in,out	status	is a scalar variable of type int, that gives the exit status from the package. Possible values are:
		0. The import was succesful
		<ul> <li>-1. An allocation error occurred. A message indicating the offending array is written on unit control.error, and the returned allocation status and a string containing the name of the offending array are held in inform.alloc_status and inform.bad_alloc respectively.</li> </ul>
		<ul> <li>-2. A deallocation error occurred. A message indicating the offending array is written on unit control.error and the returned allocation status and a string containing the name of the offending array are held in inform.alloc_status and inform.bad_alloc respectively.</li> </ul>
		<ul> <li>-3. The input values n, m, A_ne or H_ne do not agree with those output as necessary from presolve_import_problem.</li> </ul>
out	n	is a scalar variable of type int, that holds the number of variables in the transformed problem. This must match the value n_out from the last call to presolve_import_problem.
out	m	is a scalar variable of type int, that holds the number of general linear constraints. This must match the value m_out from the last call to presolve_import_problem.
out	H_ne	is a scalar variable of type int, that holds the number of entries in the lower triangular part of the transformed $H$ . This must match the value $H_ne_out$ from the last call to presolve_import_problem.
out	H_col	is a one-dimensional array of size $H_ne$ and type int, that holds the column indices of the lower triangular part of the transformed $H$ in the sparse row-wise storage scheme.
out	H_ptr	is a one-dimensional array of size $n+1$ and type int, that holds the starting position of each row of the lower triangular part of the transformed $H$ in the sparse row-wise storage scheme.
out	H_val	is a one-dimensional array of size h_ne and type double, that holds the values of the entries of the lower triangular part of the transformed Hessian matrix $H$ in the sparse row-wise storage scheme.
out	g	is a one-dimensional array of size n and type double, that holds the the transformed linear term $g$ of the objective function. The j-th component of $g$ , $j$ = 0,, n-1, contains $g_j$ .
out	f	is a scalar of type double, that holds the transformed constant term $f$ of the objective function.
out	A_ne	is a scalar variable of type int, that holds the number of entries in the transformed $A$ . This must match the value $A_ne_0$ trom the last call to presolve_import_problem.
out	A_col	is a one-dimensional array of size A_ne and type int, that holds the column indices of the transformed $\cal A$ in the sparse row-wise storage scheme.

#### **Parameters**

out	A_ptr	is a one-dimensional array of size $n+1$ and type int, that holds the starting position of each row of the transformed $A$ , as well as the total number of entries plus one, in the sparse row-wise storage scheme.
out	A_val	is a one-dimensional array of size a_ne and type double, that holds the values of the entries of the transformed constraint Jacobian matrix $A$ in the sparse row-wise storage scheme.
out	c_I	is a one-dimensional array of size m and type double, that holds the transformed lower bounds $c^l$ on the constraints $Ax$ . The i-th component of c_l, i = 0,, m-1, contains $c^l_i$ .
out	c_u	is a one-dimensional array of size m and type double, that holds the transformed upper bounds $c^l$ on the constraints $Ax$ . The i-th component of c_u, i = 0,, m-1, contains $c^u_i$ .
out	x_I	is a one-dimensional array of size n and type double, that holds the transformed lower bounds $x^l$ on the variables $x$ . The j-th component of x_l, j = 0,, n-1, contains $x^l_j$ .
out	x_u	is a one-dimensional array of size n and type double, that holds the transformed upper bounds $x^l$ on the variables $x$ . The j-th component of x_u, j = 0,, n-1, contains $x^l_j$ .
out	y_I	is a one-dimensional array of size m and type double, that holds the implied lower bounds $y^l$ on the transformed Lagrange multipliers $y$ . The i-th component of y_l, i = 0, , m-1, contains $y^l_i$ .
out	<i>y_u</i>	is a one-dimensional array of size m and type double, that holds the implied upper bounds $y^u$ on the transformed Lagrange multipliers $y$ . The i-th component of y_u, i = 0,, m-1, contains $y^u_i$ .
out	z_l	is a one-dimensional array of size m and type double, that holds the implied lower bounds $y^l$ on the transformed dual variables $z$ . The j-th component of z_l, j = 0,, n-1, contains $z^l_i$ .
out	z_u	is a one-dimensional array of size m and type double, that holds the implied upper bounds $y^u$ on the transformed dual variables $z$ . The j-th component of z_u, j = 0,, n-1, contains $z^u_i$ .

### Examples

presolvet.c, and presolvetf.c.

### 3.1.2.5 presolve\_restore\_solution()

```
void presolve_restore_solution (
    void ** data,
    int * status,
    int n_in,
    int m_in,
    const real_wp_ x_in[],
    const real_wp_ c_in[],
    const real_wp_ z_in[],
    int n,
    int m,
    real_wp_ x[],
    real_wp_ z[],
    real_wp_ z[],
    real_wp_ z[])
```

Given the solution  $(x_in,c_in,y_in,z_in)$  to the transformed problem, restore to recover the solution (x,c,y,z) to the original

### **Parameters**

in,out	data	holds private internal data
in,out	status	is a scalar variable of type int, that gives the exit status from the package. Possible values are:
		0. The import was succesful
		<ul> <li>-1. An allocation error occurred. A message indicating the offending array is written on unit control.error, and the returned allocation status and a string containing the name of the offending array are held in inform.alloc_status and inform.bad_alloc respectively.</li> </ul>
		<ul> <li>-2. A deallocation error occurred. A message indicating the offending array is written on unit control.error and the returned allocation status and a string containing the name of the offending array are held in inform.alloc_status and inform.bad_alloc respectively.</li> </ul>
		<ul> <li>-3. The input values n, m, n_in and m_in do not agree with those input to and output as necessary from presolve_import_problem.</li> </ul>
out	n_in	is a scalar variable of type int, that holds the number of variables in the transformed problem. This must match the value n_out from the last call to presolve_import_problem.
out	m_in	is a scalar variable of type int, that holds the number of general linear constraints. This must match the value m_out from the last call to presolve_import_problem.
in	x_in	is a one-dimensional array of size n_in and type double, that holds the transformed values $x$ of the optimization variables. The j-th component of x, j = 0,, n-1, contains $x_j$ .
in	c_in	is a one-dimensional array of size m and type double, that holds the transformed residual $c(x)$ . The i-th component of c, j = 0,, n-1, contains $c_j(x)$ .
in	y_in	is a one-dimensional array of size n_in and type double, that holds the values $y$ of the transformed Lagrange multipliers for the general linear constraints. The j-th component of y, j = 0,, n-1, contains $y_j$ .
in	z_in	is a one-dimensional array of size n_in and type double, that holds the values $z$ of the transformed dual variables. The j-th component of z, j = 0,, n-1, contains $z_j$ .
in	n	is a scalar variable of type int, that holds the number of variables in the transformed problem. This must match the value n as input to presolve_import_problem.
in	m	is a scalar variable of type int, that holds the number of general linear constraints. This must match the value m as input to presolve_import_problem.
out	Х	is a one-dimensional array of size n and type double, that holds the transformed values $x$ of the optimization variables. The j-th component of x, j = 0,, n-1, contains $x_j$ .
out	С	is a one-dimensional array of size m and type double, that holds the transformed residual $c(x)$ . The i-th component of c, j = 0,, n-1, contains $c_j(x)$ .
out	У	is a one-dimensional array of size n and type double, that holds the values $y$ of the transformed Lagrange multipliers for the general linear constraints. The j-th component of y, j = 0,, n-1, contains $y_j$ .
out	Z	is a one-dimensional array of size n and type double, that holds the values $z$ of the transformed dual variables. The j-th component of z, j = 0,, n-1, contains $z_j$ .

## Examples

presolvet.c, and presolvetf.c.

## 3.1.2.6 presolve\_information()

#### Provides output information

#### **Parameters**

in,out	data	holds private internal data
out	inform	is a struct containing output information (see presolve_inform_type)
out	status	is a scalar variable of type int, that gives the exit status from the package. Possible values are (currently):
		0. The values were recorded succesfully

### **Examples**

presolvet.c, and presolvetf.c.

### 3.1.2.7 presolve\_terminate()

### Deallocate all internal private storage

## Parameters

in,out	data	holds private internal data
out	control	is a struct containing control information (see presolve_control_type)
out	inform	is a struct containing output information (see presolve_inform_type)

## Examples

presolvet.c, and presolvetf.c.

## **Chapter 4**

## **Example Documentation**

## 4.1 presolvet.c

This is an example of how to use the package to solve a quadratic program. A variety of supported Hessian and constraint matrix storage formats are shown.

Notice that C-style indexing is used, and that this is flaggeed by setting control.f\_indexing to false.

```
/* presolvet.c >
/* Full test for the PRESOLVE C interface using C sparse matrix indexing \star/
#include <stdio.h>
#include <math.h>
#include "galahad_presolve.h"
int main(void) {
      // Derived types
      void *data;
      struct presolve_control_type control;
      struct presolve_inform_type inform;
      // Set problem data
      int n = 6; // dimension
int m = 5; // number of general constraints
int H_ne = 1; // Hesssian elements
      int H_row[] = {0}; // row indices, NB lower triangle
int H_col[] = {0}; // column indices, NB lower tria
                                            // column indices, NB lower triangle
      int H_ptr[] = {0, 1, 1, 1, 1, 1, 1}; // row pointers double H_val[] = {1.0}; // values
      double g[] = \{1.0, 1.0, 1.0, 1.0, 1.0, 1.0, 1.0\}; // linear term in the objective double f = 1.0; // constant term in the objective int A_ne = 8; // Jacobian elements
      int A_ne = 8; // Jacobian elements
int A_row[] = {2, 2, 2, 3, 3, 4, 4, 4}; // row indices
int A_col[] = {2, 3, 4, 2, 5, 3, 4, 5}; // column indices
int A_ptr[] = {0, 0, 0, 3, 5, 8}; // row pointers
double A_val[] = {1.0, 1.0, 1.0, 1.0, 1.0, 1.0, 1.0, 1.0}; // values
double c_l[] = { 0.0, 0.0, 2.0, 1.0, 3.0}; // constraint lower bound
double c_u[] = {1.0, 1.0, 3.0, 3.0, 3.0}; // constraint upper bound
double x_l[] = {-3.0, 0.0, 0.0, 0.0, 0.0, 0.0}; // variable lower bound
double x_u[] = {3.0, 1.0, 1.0, 1.0, 1.0, 1.0}; // variable upper bound
// Set output storage
      // Set output storage
      char st;
      int status:
      printf(" C sparse matrix indexing\n\n");
      printf(" basic tests of qp storage formats\n\n");
       for( int d=1; d <= 7; d++){
          int n_trans, m_trans, H_ne_trans, A_ne_trans;
              // Initialize PRESOLVE
             presolve_initialize( &data, &control, &status );
             // Set user-defined control options
control.f_indexing = false; // C sparse matrix indexing
             switch(d){
                    case 1: // sparse co-ordinate storage
    st = 'C';
                           presolve_import_problem( &control, &data, &status, n, m,
                                               "coordinate", H_ne, H_row, H_col, NULL, H_val, g, f, "coordinate", A_ne, A_row, A_col, NULL, A_val,
                                              c_1, c_u, x_1, x_u,
```

```
&n_trans, &m_trans, &H_ne_trans, &A_ne_trans);
        break;
    printf(" case %li break\n",d);
    case 2: // sparse by rows
        st = 'R';
        presolve_import_problem( &control, &data, &status, n, m,
                "sparse_by_rows", H_ne, NULL, H_col, H_ptr, H_val, g, f, "sparse_by_rows", A_ne, NULL, A_col, A_ptr, A_val,
                c_1, c_u, x_1, x_u,
                &n_trans, &m_trans, &H_ne_trans, &A_ne_trans);
        break:
    case 3: // dense
st = 'D';
        int H_{dense_ne} = n*(n+1)/2; // number of elements of H
        int A_dense_ne = m*n; // number of elements of A
        double H_dense[] = \{1.0,
                              0.0, 0.0,
                              0.0, 0.0, 0.0,
                              0.0, 0.0, 0.0, 0.0,
                              0.0, 0.0, 0.0, 0.0, 0.0,
                              0.0, 0.0, 0.0, 0.0, 0.0, 0.0};
        double A_dense[] = {0.0, 0.0, 0.0, 0.0, 0.0, 0.0,
                              0.0, 0.0, 0.0, 0.0, 0.0, 0.0,
                              0.0, 0.0, 0.0, 1.0, 1.0, 1.0};
        presolve_import_problem( &control, &data, &status, n, m,
                      "dense", H_dense_ne, NULL, NULL, NULL, H_dense, g,
                      f, "dense", A_dense_ne, NULL, NULL, NULL, A_dense,
                     c_1, c_u, x_1, x_u,
                     &n_trans, &m_trans, &H_ne_trans, &A_ne_trans);
        break;
    case 4: // diagonal
st = 'L';
        "sparse_by_rows", A_ne, NULL, A_col, A_ptr, A_val, c_l, c_u, x_l, x_u,
                      &n_trans, &m_trans, &H_ne_trans, &A_ne_trans);
        break;
    case 5: // scaled identity
   st = 'S';
        c_1, c_u, x_1, x_u,
                 &n_trans, &m_trans, &H_ne_trans, &A_ne_trans);
        break;
    case 6: // identity
st = 'I';
        presolve_import_problem( &control, &data, &status, n, m,
                      "identity", 0, NULL, NULL, NULL, NULL, g, f,
                      "sparse_by_rows", A_ne, NULL, A_col, A_ptr, A_val,
                      c_1, c_u, x_1, x_u,
                     &n_trans, &m_trans, &H_ne_trans, &A_ne_trans);
        break;
    case 7: // zero
        st = 'Z';
        c_1, c_u, x_1, x_u,
&n_trans, &m_trans, &H_ne_trans, &A_ne_trans);
//printf("%c: n, m, h_ne, a_ne = %2i, %2i, %2i, %2i\n",
// st, n_trans, m_trans, H_ne_trans, A_ne_trans);
double f_trans; // transformed constant term in the objective
int H_ptr_trans[n_trans+1]; // transformed Hessian row pointers
int H_col_trans[H_ne_trans]; // transformed Hessian column indices
double H_val_trans[H_ne_trans]; // transformed Hessian values
double g_trans[n_trans]; // transformed gradient
int A_ptr_trans[m_trans+1]; // transformed Jacobian row pointers
int A_col_trans[A_ne_trans]; // transformed Jacobian column indices
double A_val_trans[A_ne_trans]; // transformed Jacobian values
double x_l_trans[n_trans]; // transformed lower variable bounds
double x_u_trans[n_trans]; // transformed upper variable bounds
double c_l_trans[m_trans]; // transformed lower constraint bounds double c_u_trans[m_trans]; // transformed upper constraint bounds double y_l_trans[m_trans]; // transformed lower multiplier bounds
double y_u_trans[m_trans]; // transformed upper multiplier bounds
double z_l_trans[n_trans]; // transformed lower dual variable bounds
double z_u_trans[n_trans]; // transformed upper dual variable bounds
presolve_transform_problem( &data, &status, n_trans, m_trans,
                         H_ne_trans, H_col_trans, H_ptr_trans,
                         H_val_trans, g_trans, &f_trans, A_ne_trans,
A_col_trans, A_ptr_trans, A_val_trans,
```

4.2 presolvetf.c 29

```
c_l_trans, c_u_trans, x_l_trans, x_u_trans,
y_l_trans, y_u_trans, z_l_trans, z_u_trans);
double x_trans[n_trans]; // transformed variables
for( int i = 0; i < n_trans; i++) x_trans[i] = 0.0;</pre>
double c_trans[m_trans]; // transformed constraints
for (int i = 0; i < m trans; i++) c trans[i] = 0.0;
double y_trans[m_trans]; // transformed Lagrange multipliers
for( int i = 0; i < m_trans; i++) y_trans[i] = 0.0;</pre>
double z_trans[n_trans]; // transformed dual variables
for( int i = 0; i < n_trans; i++) z_trans[i] = 0.0; double x[n]; // primal variables double c[m]; // constraint values
double v[m]; // Lagrange multipliers
double z[n]; // dual variables
//printf("%c: n_trans, m_trans, n, m = %2i, %2i, %2i, %2i\n",
// st, n_trans, m_trans, n, m );
presolve_restore_solution( &data, &status, n_trans, m_trans,
x_trans, c_trans, y_trans, z_trans, n, m, x, c, y, z);
presolve_information( &data, &inform, &status );
if (inform.status == 0) {
    printf("%c:%6i transformations, n, m = %2i, %2i, status = %1in",
             st, inform.nbr_transforms, n_trans, m_trans, inform.status);
}else{
    printf("%c: PRESOLVE_solve exit status = %li\n", st, inform.status);
//printf("x: ");
//for( int i = 0; i < n; i++) printf("%f ", x[i]);
//printf("\n");
//printf("gradient: ");
//for( int i = 0; i < n; i++) printf("%f ", g[i]);
//printf("\n");
// Delete internal workspace
presolve_terminate( &data, &control, &inform );
```

## 4.2 presolvetf.c

This is the same example, but now fortran-style indexing is used.

```
/* presolvetf.c */
/* Full test for the PRESOLVE C interface using Fortran sparse matrix indexing */
#include <stdio.h>
#include <math.h>
#include "galahad_presolve.h"
int main(void) {
      // Derived types
      void *data;
      struct presolve_control_type control;
      struct presolve_inform_type inform;
      // Set problem data
      int n = 6; // dimension
     int m = 5; // number of general constraints int H_ne = 1; // Hesssian elements
      int H_row[] = {1}; // row indices, NB lower triangle
int H_col[] = {1}; // column indices, NB lower triangle
      int H_ptr[] = {1, 2, 2, 2, 2, 2, 2}; // row pointers double H_val[] = {1.0}; // values
      double g[] = {1.0, 1.0, 1.0, 1.0, 1.0, 1.0}; // linear term in the objective double f = 1.0; // constant term in the objective int A_ne = 8; // Jacobian elements
      int A_row[] = {3, 3, 3, 4, 4, 5, 5, 5}; // row indices
      int A_col[] = {3, 4, 5, 3, 6, 4, 5, 6}; // column indices
int A_ptr[] = {1, 1, 1, 4, 6, 9}; // row pointers
     int A_ptr[] = {1, 1, 1, 4, 6, 9}; // row pointers
double A_val[] = {1.0, 1.0, 1.0, 1.0, 1.0, 1.0, 1.0, 1.0}; // values
double c_l[] = { 0.0, 0.0, 2.0, 1.0, 3.0}; // constraint lower bound
double c_u[] = {1.0, 1.0, 3.0, 3.0, 3.0}; // constraint upper bound
double x_l[] = {-3.0, 0.0, 0.0, 0.0, 0.0, 0.0}; // variable lower bound
double x_u[] = {3.0, 1.0, 1.0, 1.0, 1.0, 1.0}; // variable upper bound
      // Set output storage
      char st:
      int status:
      printf(" Fortran sparse matrix indexing\n\n");
      printf(" basic tests of qp storage formats\n\n");
      for( int d=1; d <= 7; d++) {
         int n_trans, m_trans, H_ne_trans, A_ne_trans;
            // Initialize PRESOLVE
            presolve_initialize( &data, &control, &status );
// Set user-defined control options
            control.f_indexing = true; // Fortran sparse matrix indexing
```

```
case 1: // sparse co-ordinate storage
    st = 'C';
         presolve_import_problem( &control, &data, &status, n, m,
                       "coordinate", H_ne, H_row, H_col, NULL, H_val, g, f, "coordinate", A_ne, A_row, A_col, NULL, A_val, c_l, c_u, x_l, x_u,
                       &n_trans, &m_trans, &H_ne_trans, &A_ne_trans);
         break;
     printf(" case %li break\n",d);
     case 2: // sparse by rows
st = 'R';
         presolve_import_problem( &control, &data, &status, n, m,
                  "sparse_by_rows", H_ne, NULL, H_col, H_ptr, H_val, g, f, "sparse_by_rows", A_ne, NULL, A_col, A_ptr, A_val,
                  c_1, c_u, x_1, x_u,
                  &n_trans, &m_trans, &H_ne_trans, &A_ne_trans);
         break:
     case 3: // dense
         st = 'D';
          int H_dense_ne = n*(n+1)/2; // number of elements of H
          int A_dense_ne = m*n; // number of elements of A
         double H_dense[] = {1.0,
                                  0.0, 0.0,
                                  0.0, 0.0, 0.0,
0.0, 0.0, 0.0, 0.0,
                                  0.0, 0.0, 0.0, 0.0, 0.0,
                                  0.0, 0.0, 0.0, 0.0, 0.0, 0.0);
         double A_dense[] = {0.0, 0.0, 0.0, 0.0, 0.0, 0.0,
                                  0.0, 0.0, 0.0, 0.0, 0.0, 0.0,
                                  0.0, 0.0, 1.0, 1.0, 1.0, 0.0,
                                  presolve_import_problem( &control, &data, &status, n, m,
                        "dense", H_dense_ne, NULL, NULL, NULL, H_dense, g,
                        f, "dense", A_dense_ne, NULL, NULL, NULL, A_dense,
                        c_1, c_u, x_l, x_u,
&n_trans, &m_trans, &H_ne_trans, &A_ne_trans);
         break;
     case 4: // diagonal
    st = 'L';
         c_l, c_u, x_l, x_u,
&n_trans, &m_trans, &H_ne_trans, &A_ne_trans);
         break;
     case 5: // scaled identity
   st = 'S';
         c_1, c_u, x_1, x_u,
                   &n_trans, &m_trans, &H_ne_trans, &A_ne_trans);
     break;
case 6: // identity
st = 'I';
         presolve_import_problem( &control, &data, &status, n, m,
                         "identity", 0, NULL, NULL, NULL, NULL, g, f,
                        "sparse_by_rows", A_ne, NULL, A_col, A_ptr, A_val,
                        c_1, c_u, x_1, x_u,
                        &n_trans, &m_trans, &H_ne_trans, &A_ne_trans);
         break;
     case 7: // zero
st = 'Z';
         presolve_import_problem( &control, &data, &status, n, m,
                        "zero", 0, NULL, NULL, NULL, NULL, g, f,
"sparse_by_rows", A_ne, NULL, A_col, A_ptr, A_val,
                        c_1, c_u, x_1, x_u,
&n_trans, &m_trans, &H_ne_trans, &A_ne_trans);
         break:
//printf("%c: n, m, h_ne, a_ne = %2i, %2i, %2i, %2i\n",
// st, n_trans, m_trans, H_ne_trans, A_ne_trans);
double f_trans; // transformed constant term in the objective
int H_ptr_trans[n_trans+1]; // transformed Hessian row pointers
int H_col_trans[H_ne_trans]; // transformed Hessian column indices
double H_val_trans[H_ne_trans]; // transformed Hessian values
double g_trans[n_trans]; // transformed gradient
int A_ptr_trans[m_trans+1]; // transformed Jacobian row pointers
int A_col_trans[A_ne_trans]; // transformed Jacobian column indices
double A_val_trans[A_ne_trans]; // transformed Jacobian values
double x_l_trans[n_trans]; // transformed lower variable bounds double x_u_trans[n_trans]; // transformed upper variable bounds double c_l_trans[m_trans]; // transformed lower constraint bounds
double c_u_trans[m_trans]; // transformed upper constraint bounds double y_l_trans[m_trans]; // transformed lower multiplier bounds double y_u_trans[m_trans]; // transformed upper multiplier bounds
```

4.2 presolvetf.c 31

```
double z_l_trans[n_trans]; // transformed lower dual variable bounds double z_u_trans[n_trans]; // transformed upper dual variable bounds
presolve_transform_problem( &data, &status, n_trans, m_trans,
                               H_ne_trans, H_col_trans, H_ptr_trans,
                               H_val_trans, g_trans, &f_trans, A_ne_trans,
A_col_trans, A_ptr_trans, A_val_trans,
c_l_trans, c_u_trans, x_l_trans, x_u_trans,
                               y_l_trans, y_u_trans, z_l_trans, z_u_trans );
double x_{trans[n_{trans}]; // transformed variables}
for( int i = 0; i < n_trans; i++) x_trans[i] = 0.0;</pre>
double c_trans[m_trans]; // transformed constraints
for( int i = 0; i < m_trans; i++) c_trans[i] = 0.0;
double y_trans[m_trans]; // transformed Lagrange multipliers
for( int i = 0; i < m_trans; i++) y_trans[i] = 0.0;</pre>
double z_trans[n_trans]; // transformed dual variables
for( int i = 0; i < n_trans; i++) z_trans[i] = 0.0; double x[n]; // primal variables double c[m]; // constraint values
double y[m]; // Lagrange multipliers
double z[n]; // dual variables
//printf("%c: n_trans, m_trans, n, m = %2i, %2i, %2i, %2i\n",
// st, n_trans, m_trans, n, m );
presolve_restore_solution( &data, &status, n_trans, m_trans,
x_trans, c_trans, y_trans, z_trans, n, m, x, c, y, z );
presolve_information( &data, &inform, &status );
if (inform.status == 0) {
     printf("%c:%6i transformations, n, m = %2i, %2i, status = %1in",
               st, inform.nbr_transforms, n_trans, m_trans, inform.status);
}else{
    printf("%c: PRESOLVE_solve exit status = %1i\n", st, inform.status);
//printf("x: ");
//for( int i = 0; i < n; i++) printf("%f ", x[i]);
//printf("\n");
//printf("gradient: ");
//for( int i = 0; i < n; i++) printf("%f ", g[i]); //printf("\n");
// Delete internal workspace
presolve_terminate( &data, &control, &inform );
```

## Index

```
galahad_presolve.h, 9
    presolve_import_problem, 20
    presolve_information, 25
    presolve_initialize, 19
    presolve_read_specfile, 19
    presolve_restore_solution, 24
    presolve_terminate, 26
    presolve_transform_problem, 22
presolve_control_type, 9
presolve_import_problem
    galahad_presolve.h, 20
presolve_inform_type, 15
presolve_information
    galahad_presolve.h, 25
presolve_initialize
    galahad_presolve.h, 19
presolve_read_specfile
    galahad_presolve.h, 19
presolve_restore_solution
     galahad_presolve.h, 24
presolve_terminate
    galahad_presolve.h, 26
presolve_transform_problem
    galahad_presolve.h, 22
```