# **LAB 02**

# COMPUTER ORGANIZATION AND ASSEMBLY LANG(COAL)



STUDENT NAME	ROLL NO SEC
	SIGNATURE & DAT
MARKS AW	ARDED:
NATIONAL UNIVERSITY OF COMPUT	
(NUCES), KA	
Prepared by: Amin Sadiq	Version: 1.0  Date:

### Lab Session 02

# **Objectives:**

- Debugging of programs
- Basic elements of Assembly language
- Defining Data
- Intrinsic Data Types

# Steps Involved in Creating and Running a Program:

### Assemble R:

It converts the assembly language to machine language (Object Code) May contain unresolved references (i.e. file contains some or all of complete program)

#### LINKER:


A program that combines object files to create a single "executable" file. Major functional difference is that all references are resolved. (i.e. Program contains all parts needed to run) A program that loads executable files into memory, and may initialize some registers (e.g. IP) and starts it going.

#### **Debugger:**

Instructor: Qurat ul ain

A program that loads but controls the execution of the program. To start/stop execution, to view and modify state variables.

### Steps in Creating & Running Code:



## Section 1: Debugging our program

We have seen how to configure Visual Studio 2019 for Assembly Language and tested it with a sample program. The output of our sample program was displayed using a console window but it is usually more desirable to watch the step by step execution of our program with each line of code using breakpoints.

Let us briefly define the keywords relevant to debugging in Visual Studio and then we will cover an example for understanding.

#### **Debugger**

The (Visual Studio) debugger helps us observe the run-time behavior of our program and find problems. With the debugger, we can break the execution of our program to examine our code,

examine and edit variables, view registers, see the instructions created from our source code, and view the memory space used by our application.

#### **B**REAKPOINT

A breakpoint is a signal that tells the debugger to temporarily suspend execution of your program at a certain point. When execution is suspended at a breakpoint, your program is said to be in break mode.

#### CODE STEPPING

One of the most common debugging procedures is stepping: executing code one line at a time. The Debug menu provides three commands for stepping through code:


- Step Into (By pressing F11)
- Step Over (By pressing F10)
- Step Out (Shift+F11)

#### SINGLE STEPPING


To see the values of internal registers and memory variables during execution, let us use an example. Copy the following code onto your Test.asm file.k

```
TITLE Add and Subtract
INCLUDE Irvine32.inc
.code
main PROC
mov eax, 10000h
                   ; EAX = 10000h
add eax, 40000h
                   ; EAX = 50000h
sub eax, 20000h
                   ; EAX = 30000h
call DumpRegs
exit
main ENDP
END main
```


1. Right-click on line 6 to insert a breakpoint.




2. Click on **Debug** tab from the toolbar, select **Start Debugging** OR press **F10** to start stepping over the code.




3. Click on **Debug** tab than select Windows after that open menu and select **Registers** option.




4. Breakpoint set on 1<sup>st</sup> instruction





Press F10 again to execute next line.





Again press **F10** key for next instruction execution.





Press **F10** again, the program will not terminate after executing the current instruction and as soon as it reaches the line with a call to **DumpRegs** 

### Section 3: Introduction to registers

To speed up the processor operations, the processor includes some internal memory storage locations, called **Registers**. The registers store data elements for processing without having to access the memory.

#### PROCESSOR REGISTERS

There are ten 32-bit and six 16-bit processor registers in IA-32 architecture. The registers are grouped into three categories:

- General registers.
- Control registers.
- Segment registers.

Furthermore, the general registers are further divided into the following groups:

- Data registers.
- Pointer registers.

Instructor: Qurat ul ain

Index registers.

#### DATA REGISTERS

Four 32-bit data registers are used for arithmetic, logical, and other operations. These 32-bit registers can be used in three ways:

- As complete 32-bit data registers: EAX, EBX, ECX, EDX.
- Lower halves of the 32-bit registers can be used as four 16-bit data registers: AX, BX, CX and DX.
- Lower and higher halves of the above-mentioned four 16-bit registers can be used as eight 8-bit data registers: AH, AL, BH, BL, CH, CL, DH, and DL

2-bit registers		16-bit register	s
31	16 15 8	7 0	
EAX	AH	AL AX Accu	ımulator
EBX	ВН	BL BX Base	2
ECX	СН	CL CX Cour	nter
EDX	DH	DL DX Data	9

**AX (Accumulator)**: It is used in input/output and most arithmetic instructions. For example, in multiplication operation, one operand is stored in EAX or AX or AL register according to the size of the operand.

**BX** (Base register): It could be used in indexed addressing.

**CX** (Counter register): The ECX, CX registers store the loop count in iterative operations.

**DX** (**Data register**): It is also used in input/output operations. It is also used with AX register along with DX for multiply and division operations involving large values.

#### POINTER REGISTERS

The pointer registers are 32-bit EIP, ESP, and EBP registers and corresponding 16-bit right portions IP, SP, and BP. There are three categories of pointer registers:

**Instruction Pointer (IP)**: The 16-bit IP register stores the offset address of the next instruction to be executed. IP in association with the CS register (as CS:IP) gives the complete address of the current instruction in the code segment.

**Stack Pointer (SP):** The 16-bit SP register provides the offset value within the program stack. SP in association with the SS register (SS:SP) refers to be current position of data or address within the program stack.

**Base Pointer (BP):** The 16-bit BP register mainly helps in referencing the parameter variables passed to a subroutine. The address in SS register is combined with the offset in BP to get the location of the parameter. BP can also be combined with DI and SI as base register for special addressing.

	Pointer registers	
31	16 15	0
ESP	SP	Stack Pointer
EBP	BP	Base Pointer

## **Index Registers**

Instructor: Qurat ul ain

The 32-bit index registers, ESI and EDI, and their 16-bit rightmost portions. SI and DI, are used for indexed addressing and sometimes used in addition and subtraction. There are two sets of index pointers.

**Source Index (SI):** It is used as source index for string operations.

**Destination Index (DI):** It is used as destination index for string operations.

	Index registers	
31	16 15	0
ESI	S	Source Index
EDI	D	Destination Index

### BASIC ELEMENT OF ASSEMBLY LANGUAGE

### INTEGER CONSTANTS

Integer constants are made up of an optional leading sign, one or more digits and an optional suffix character.

#### Format:

[ {+ | -}] digits radix

#### **Examples:**

26	for decimal
26d	for decimal
10111110b	for binary
42o	for octal

1Ah for Hexadecimal0A3h for Hexadecimal

### CHARACTER CONSTANTS

Character constants are made up of a single character enclosed in either single or double quotes.

#### Example:

'A' "d"

#### STRING CONSTANTS

A string of characters enclosed in either single or double quotes.

#### Example:

"Hello World"



#### **IDENTIFIERS**

An identifier is a programmer-defined name of a variable, procedure or code label.

#### Format:

They may contain between 1 and 247 characters. They are not case sensitive. The first character must be a letter (A..Z, a..z), underscore (\_), @, ?, or \$. Subsequent characters may also be digits.

An identifier cannot be the same as an assembler reserved word. For example: reserved words are instruction mnemonics, directives, attributes, operators, predefined symbols.

#### **Examples:**

myVar \_abc hello2

#### **MEMORY SEGMENTS**

A segmented memory model divides the system memory into groups of independent segments referenced by pointers located in the segment registers. Each segment defines the area of our program that contains data variables, code and stack, respectively.

**Data segment:** It is the memory region, where data elements are stored for the program. This section cannot be expanded after the data elements are declared, and it remains static throughout the program.

**Code segment:** This section defines an area in memory that stores the instruction codes. This is also a fixed area.

**Stack segment:** This segment contains data values passed to procedures within the program.

#### DIRECTIVES

A directive is a command embedded in the source code that is recognized and acted upon by the assembler. Directives do not execute at runtime. They can assign names to memory segments. In

National University of Computer & Emerging Sciences, Karachi Page 11 of 15

Instructor: Qurat ul ain

MASM, directives are case insensitive. For example, it recognizes data, .DATA and .Data as equivalent.

Let us see what different directives we can use to define segments of our program:

The **.DATA** directive identifies the area of a program containing variables:

#### Syntax:

.data

The **.CODE** directive identifies the area of a program containing executable instructions:

#### Syntax:

.code

The .STACK directive identifies the area of a program holding the runtime stack, setting its size:

#### Syntax:

stack 100h

#### Instructions

An instruction is a statement that becomes executable when a program is assembled. Instructions are translated by the assembler into machine language bytes, which are loaded and executed by the CPU at runtime. An instruction contains four basic parts:

- Label (optional)
- Instruction mnemonic (required)
- Operand(s) (usually required)
- Comment (optional)

The basic syntax of an Assembly Language instruction is as:

#### [label:] mnemonic [operands] [;comment]

where elements in square brackets are optional. We will now see what each of these elements.

**Label:** A label is an identifier that acts as a place marker for instructions and data. A label placed just before an instruction implies the instruction's address. Similarly, a label placed just before a variable implies the variable's address.

<u>Mnemonics</u>: An instruction mnemonic is a short word that identifies an instruction to perform an operation. Following are examples of instruction mnemonics:

mov: Moves (assigns) one value to another.

add: Adds two values

**sub**: Subtracts one value from another

mul: Multiplies two valuesjmp: Jumps to a new location

call: Calls a procedure

**Operands:** Assembly language instructions can have between zero and three operands, each of which can be a register, memory operand, constant expression, or input-output port.

Example	Operand Type
96	Constant (immediate value)
2 + 4	Constant expression
eax	Register
count	Memory

### Example:

The MOV instruction has two operands:

Instructor: Qurat ul ain

mov count, ebx; move EBX to count

Instructor: Qurat ul ain

In a two-operand instruction, the first operand is called the destination. The second operand is the source. In general, the contents of the destination operand are modified by the instruction.

Comments: Comments are an important way for the writer of a program to communicate information about the program's design to a person reading the source code.

#### Comments can be specified in two ways:

- Single-line comments: beginning with a semicolon character (;). All characters following the semicolon on the same line are ignored by the assembler.
- **Block comments**: beginning with the COMMENT directive and a user-specified symbol. For example,

#### COMMENT!

This line is a comment.

This line is also a comment.

!

#### DATA TYPES

MASM defines intrinsic data types, each of which describes a set of values that can be assigned to variables and expressions of the given type.

**BYTE** 8-bit unsigned integer

**SBYTE** 8-bit signed integer. S stands for signed

**WORD** 16-bit unsigned integer **SWORD** 16-bit signed integer

32-bit unsigned. D stands for double **DWORD QWORD** 64-bit integer. Q stands for quad **TBYTE** 80-bit integer. T stands for ten



# **SECTION 4: EXERCISE**

Instructor: Qurat ul ain

Implement all of these equations in assembly language.

- 47 + 39 + 60 + 85 + 64 + 540 0Ah
- 30-9+186-150
- 101110 + 50Ah + 6710d + 1010001 + F
- 10001101 D83h + 385+10 + 1111101 E+F

Write a program in assembly language that implements following expression:

- edx = eax + 1 + ebx + edx ecx + 0Ah-65o+73d
- eax = 5ADh eax + 65o + 65d 11110111 + 150

# Task 1:

#### **Source Code**

```
Title Task 1
INCLUDE IRVINE32.inc
.code
main PROC
mov eax, 0h; sub eax, eax xor eax, eax
add eax, 47d
add eax, 39d
add eax, 60d
add eax, 85d
add eax, 64d
add eax, 54o
sub eax, OAh
call DumpRegs
exit
main ENDP
End main
```

#### **Output File**

```
EAX=00000149 EBX=7EFDE000 ECX=0000000 EDX=012410AA
ESI=00000000 EDI=00000000 EBP=0034F7C8 ESP=0034F7C0
EIP=0124367F EFL=00000212 CF=0 SF=0 ZF=0 OF=0 AF=1 PF=0

C:\Users\k200353\source\repos\Project1\Debug\Project1.exe (process 49220) exited with code 0.
To automatically close the console when debugging stops, enable Tools=>Options=> Debugging=>Automatically close the console when debugging stops.
Press any key to close this window . . .
```

Comment: Adding And Subtracting different values in the register EAX

#### Debugging:

#### Step1:

```
EAX = 7731342B EBX = 7EFDE000 ECX = 00000000 EDX = 013D10AA ESI = 00000000 EDI = 00000000 EIP = 013D3660 ESP = 0036FCCC EBP = 0036FCD4 EFL = 00000246
       Title Task 1
       INCLUDE IRVINE32.inc
       main PROC
       mov eax, 0h; sub eax,eax xor eax, eax
        add eax, 47d
       add eax, 39d
       add eax, 60d
        add eax, 85d
    10 add eax, 64d
    11 add eax, 54o
       sub eax, OAh
    13 call DumpRegs
    14 exit
       main ENDP
    16 End main
                                                                                                                          Ln: 5 Ch: 1 TABS CRLF
```


#### Step 2:




Step 3:



#### Step 4:




#### Step 5:



#### Step 6:



#### Step 7:




#### Step 8:



#### Step 9:



#### **Step 10:**



# Task 2:

#### **Source Code**

```
Title Task 2
INCLUDE IRVINE32.Inc
.code
main PROC
xor eax, eax
add eax, 30d
sub eax, 9d
add eax, 186d
sub eax, 150d
call DumpRegs
exit
main ENDP
end Main
```

#### **Output File**

```
EAX=00000039 EBX=7EFDE000 ECX=00000000 EDX=00DB10AA
ESI=00000000 EDI=00000000 EBP=002DF9E8 ESP=002DF9E0
EIP=00DB3677 EFL=00000206 CF=0 SF=0 ZF=0 OF=0 AF=0 PF=1


C:\Users\k200353\source\repos\Project1\Debug\Project1.exe (process 49176) exited with code 0.
To automatically close the console when debugging stops, enable Tools=>Options=>Debugging=>Automatically close the console when debugging stops.

Press any key to close this window . . .
```


**Comment:** Learning How To Use Xor to set the value of EAX to 0 and getting more familiar with the directives and operands.

#### **Debugging**


#### Step 1:



#### Step 2:




#### Step 3:




#### Step 4:




#### Step 5:



Step 6:



#### Step 7:



#### Step 8:



# Task 3:

#### **Source Code**

```
Title Task 3
INCLUDE IR VINE32.inc
.code
main PROC
sub eax,eax
add eax,101110b
add eax, 50Ah
add eax, 6710d
add eax, 0Fh
add eax, 1010001b
call DumpRegs
exit
main ENDP
end main
```

#### **Output File**

```
EAX=00001FCE EBX=7EFDE000 ECX=00000000 EDX=012210AA
ESI=00000000 EDI=00000000 EBP=001EFDA8 ESP=001EFDA0
EIP=0122367A EFL=00000202 CF=0 SF=0 ZF=0 OF=0 AF=0 PF=0
C:\Users\k200353\source\repos\Project1\Debug\Project1.exe (process 40784) exited with code 0.
Press any key to close this window . . .
```

**Comment:** The Code was running successfully

# Task 4:

#### **Source Code**

```
Title Task 4
INCLUDE IRVINE32.inc
.code
main PROC
xor eax,eax
add eax,10001101b
sub eax, 0D83h
add eax, 385d
add eax, 10d
add eax, 1111101b
sub eax, OEh
add eax, OFh
call DumpRegs
exit
main ENDP
end main
```

#### **Output File**

```
EAX=FFFFF513 EBX=7EFDE000 ECX=00000000 EDX=010A10AA ESI=00000000 EDI=00000000 EBP=001AF7B8 ESP=001AF7B0 EIP=010A3682 EFL=00000292 CF=0 SF=1 ZF=0 OF=0 AF=1 PF=0 :\Users\k200353\source\repos\Project1\Debug\Project1.exe (process 48304) exited with code 0. o automatically close the console when debugging stops, enable Tools=>Options=> lebugging=>Automatically close the console when debugging stops. ress any key to close this window . . .
```

**Comment:** Code was running as predicted

# Task 5:

#### **Source Code**

```
Title Task 5
Include Irvine32.inc
.code
main PROC
add eax,1d
add eax, ebx
add eax,edx
sub eax, ecx
add eax, OAh
sub eax,650
add eax,73d
mov edx, eax
call DumpRegs
exit
main ENDP
end main
```

#### **Output File**

```
EAX=01BD1AAB EBX=00C52000 ECX=009910AA EDX=01BD1AAB
ESI=009910AA EDI=009910AA EBP=00F7FA40 ESP=00F7FA34
EIP=00993679 EFL=00000202 CF=0 SF=0 ZF=0 OF=0 AF=0 PF=0
```

**Comment:** Running per default values

# Task 6:

#### **Source Code**

```
Title Task 6
Include Irvine32.inc
.code
main PROC
mov eax, 7d
mov ebx, 83h
mov ecx, 247o
mov edx, 0FFh
add eax,1d
add eax, ebx
add eax, edx
sub eax, ecx
add eax, OAh
sub eax,650
add eax,73d
mov edx,eax
call DumpRegs
exit
main ENDP
end main
```

#### **Output File**

```
EAX=00000101 EBX=00000083 ECX=0000000A7 EDX=00000101
ESI=00CF10AA EDI=00CF10AA EBP=00CDFA44 ESP=00CDFA38
EIP=00CF368D EFL=000000212 CF=0 SF=0 ZF=0 OF=0 AF=1 PF=0
```

**Comment:** Using Pre Defined Values for the registers

# Task7:

#### **Source Code**

```
Title Task 7
INCLUDE IRVINE32.inc
.code
main PROC
mov eax , 5ADh
sub eax, eax
add eax, 65o
add eax, 65d
sub eax, 11110111b
add eax, 150d
call DumpRegs
exit
main ENDP
END main
```

#### **Output File**

```
EAX=00000015 EBX=7EFDE000 ECX=00000000 EDX=010B10AA
ESI=00000000 EDI=00000000 EBP=0034FE54 ESP=0034FE4C
EIP=010B367C EFL=00000213 CF=1 SF=0 ZF=0 OF=0 AF=1 PF=0

C:\Users\k200353\source\repos\Project1\Debug\Project1.exe \(\text{process 48408}\) exited with code 0.

To automatically close the console when debugging stops, enable Tools=>Options=>Debugging=>Automatically close the console when debugging stops.

Press any key to close this window . . .
```

**Comment:** Running per default values for the registers

# Task 8:

#### **Source Code**

```
Title Task 8
INCLUDE IRVINE32.inc
.code
main PROC
mov eax, 5d
mov eax, 5ADh
sub eax, eax
add eax, 65o
add eax, 65d
sub eax, 11110111b
add eax, 150d
call DumpRegs
exit
main ENDP
END main
```

#### **Output File**

```
EAX=00000015 EBX=7EFDE000 ECX=00000000 EDX=011310AA ESI=00000000 EDI=00000000 EBP=0035F7C4 ESP=0035F7BC EIP=01133681 EFL=000000213 CF=1 SP=0 ZF=0 OF=0 AF=1 PF=0

C:\Users\k200353\source\repos\Project1\Debug\Project1.exe \(\rho\reprocess 47388\rangle\) exited with code 0.

To automatically close the console when debugging stops, enable Tools=>0ptions=>0ebugging=>Automatically close the console when debugging stops.

Press any key to close this window . . .
```

**Comment:** Using Pre Defined Values for the registers