
Multiprocessors connected by a network

- Restrictions of the bus architecture: high bandwidth, low latency and long length are incompatible
- Shared memory (single address space) vs. multiple private memories
- Centralized memory vs. distributed memory (physically distributed single address space)



Parallel programming by message passing

Summing 100000 numbers by 100 processors

- The processor containing 100000 numbers sends subsets of 1000 to the others.
- Each processor individually sums the 1000 numbers:

```
sum=0;
for (i=0; i<1000; i++) sum=sum+Al[i];</pre>
```

• Adding the 100 partial sums (send(Pr,Val), receive()):


```
half=100;
limit=100;
repeat
    half=(half+1)/2;
if (Pn>= half && Pn <limit) send (Pn-half, sum)
    if (Pn< limit/2+1) sum=sum+receive()
    limit=half;
until (half==1);
```

Distributed memory communication


- Explicit communication: send and receive instead of load and store
- *Shared virtual memory*: addind a software layer on top of sends and receives to provide a single address space
- Cache coherency (snooping does not work): *directories*. A single directory contains infromation for each block of memory: which caches have copies of the block, whether it is dirty etc.
- When there is a write to a shared block the *directory controller* sends messages to each processor that has a copy of the block.


Memory allocation (single address space)


- The programmer or the compiler allocates data to the processor that is likely to use it.
- *Cache-only memory*: Add a second level of coherence to the main memory for every processor: moving blocks of memory between the processors.



Cost, performance, and cost/performance








Clusters


- A network (LAN) of loosely coupled machines
- Drawbacks:
 - High cost of administering
 - Slow connection through the I/O bus;
 - Division of memory
- Hybrid clusters (clustered shared memory)

Network topology


- *Network cost*: number of switches, number of links on a switch, width (bits) of a link, length of links
- Performance metrics:
 - Total network bandwidth (best case)
 - Bisection bandwidth (worst case)
- Topologies:
 - Fully connected network
 - Ring
 - Multistage networks




a. 2D grid or mesh of 16 nodes



b. n-cube tree of 8 nodes $(8 = 2^3 \text{ so n} = 3)$







c. Omega network switch box